

IBM Unica Marketing Operations  
Version 8 Release 5  
February 22, 2012

*Installation Guide*



**Note**

Before using this information and the product it supports, read the information in "Notices" on page 103.

This edition applies to version 8, release 5, modification 0 of IBM Unica Marketing Operations (product number 5725-D24) and to all subsequent releases and modifications until otherwise indicated in new editions.

© **Copyright IBM Corporation 2002, 2012.**

US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

---

# Contents

## Chapter 1. Contacting IBM Unica technical support. . . . . 1

## Chapter 2. Preparing to Install . . . . . 3

Where to install Marketing Operations and the Marketing Platform . . . . .	3
Prerequisites . . . . .	4
System requirements. . . . .	4
Marketing Platform requirement. . . . .	4
Knowledge requirement . . . . .	4
Client machines . . . . .	4
Access permissions . . . . .	5
Where to find more information . . . . .	5
If you are upgrading . . . . .	6

## Chapter 3. Preparing the IBM Unica Marketing Operations data source . . . . . 7

Step: Set up the Marketing Operations database . . . . .	7
Step: Configure the web application server for your JDBC driver . . . . .	7
Step: Create the JDBC connections in the web application server. . . . .	8
Information for JDBC connections . . . . .	8
Marketing Operations data source information checklist . . . . .	10

## Chapter 4. Installing IBM Unica Marketing Operations . . . . . 11

Copying installation files (DVD only). . . . .	11
How the IBM Unica Marketing installers work . . . . .	11
Single directory requirement for installer files . . . . .	11
Choosing product installation directories . . . . .	12
Installation types . . . . .	12
Installation modes . . . . .	12
Installing multiple times using unattended mode . . . . .	13
Creating EAR files for clustered deployments . . . . .	13
IBM Site ID . . . . .	14
Step: Obtain the installation archive . . . . .	14
Step: Obtain required information . . . . .	14
Step: Run the IBM Unica installer . . . . .	15
To create an EAR file after running the installer . . . . .	16

## Chapter 5. Configuring IBM Unica Marketing Operations before deployment. . . . . 19

Step: Create and populate the Marketing Operations system tables with the umodbsetup utility, if necessary . . . . .	19
Step: Register Marketing Operations manually, if necessary . . . . .	20
Step: Set environment variables (WebLogic/Windows only) . . . . .	21

## Chapter 6. Deploying IBM Unica Marketing Operations . . . . . 23

Guidelines for deploying Marketing Operations on WebSphere . . . . .	23
IBM WebSphere Application Server V7.0 requires fixpack 7.0.0.17 or higher . . . . .	24
Guidelines for deploying Marketing Operations on WebLogic . . . . .	24

## Chapter 7. Configuring IBM Unica Marketing Operations after deployment. 27

Step: Verify your installation. . . . .	27
Step: Give the asm_admin user access to Marketing Operations . . . . .	27
Step: Configure the markup option, if necessary . . . . .	28
Step: Configure the email settings . . . . .	28
Step: Configure the integration with Campaign, if necessary . . . . .	29

## Chapter 8. Installing reports . . . . . 31

Install reporting components . . . . .	31
Step: Set up a user with the ReportsSystem role, if necessary . . . . .	31
Step: Determine which authentication mode to configure . . . . .	32
Optional step: Obtain email server information . . . . .	32
Install and test IBM Cognos 8 BI . . . . .	32
IBM Cognos 8 BI, IBM Unica reporting, and domains . . . . .	32
IBM Cognos 8 BI applications . . . . .	33
IBM Cognos 8 BI installation options and Cognos documentation . . . . .	33
IBM Cognos 8 BI web applications and the web server . . . . .	33
IBM Cognos 8 BI and locale . . . . .	34
Test the IBM Cognos 8 BI installation. . . . .	34
Install IBM Unica integration components and report models on the Cognos system . . . . .	35
Installation checklist: IBM Cognos integration . . . . .	35
Step: Obtain the JDBC driver for the Marketing Platform system tables. . . . .	35
Step: Install the reporting models and integration component on the IBM Cognos system . . . . .	36
Step: Create the IBM Cognos data sources for the IBM Unica application databases . . . . .	36
Optional step: Set up email notification . . . . .	37
Step: Configure the IBM Cognos application's firewall. . . . .	38
Step: Import the reports folder in Cognos Connection . . . . .	38
Step: Configure and publish the data model, if necessary . . . . .	39
Step: Enable internal links in the reports. . . . .	40
Step: Verify the data source names and publish . . . . .	40

Step: Configure the reporting properties in IBM Unica Marketing. . . . .	41
Step: Test your configuration without authentication enabled. . . . .	41
Configure IBM Cognos to use IBM Unica authentication . . . . .	42
Step: Create the reporting system user, if necessary . . . . .	42
Step: Configure the Cognos authentication properties in IBM Unica Marketing . . . . .	43
Step: Configure IBM Cognos to use the IBM Unica Authentication Provider . . . . .	43
Step: Test your configuration with authentication configured. . . . .	45
Next steps for reporting . . . . .	45

**Chapter 9. Installing IBM Unica Marketing Operations in a cluster . . . 47**

Installing on a cluster in WebLogic . . . . .	47
Installing on a cluster in WebSphere . . . . .	49
Configure the shared folder properties . . . . .	50
Configuring Ehcache . . . . .	51

**Chapter 10. Upgrading IBM Unica Marketing Operations . . . . . 53**

Upgrade prerequisites for all IBM Unica Marketing products . . . . .	53
About upgrading with existing campaign projects or requests . . . . .	54
Marketing Operations upgrade scenarios . . . . .	54
To upgrade Marketing Operations. . . . .	54
Step: Back up the system before you begin the upgrade . . . . .	54
Step: Verify that the Marketing Platform has been upgraded . . . . .	55
Step: Run the installer and update the configuration properties . . . . .	55
Step: Upgrade your database manually, if necessary . . . . .	56
Step: Deploy the upgraded web application and run the upgrade processes . . . . .	57
Step: Restore trigger procedures, if necessary . . . . .	58
Step: Upgrade reporting . . . . .	58
Upgrading Marketing Operations in a clustered environment . . . . .	59

**Appendix A. Uninstalling IBM Unica products . . . . . 61**

To uninstall IBM Unica products . . . . .	61
---	----

**Appendix B. The configTool utility . . . 63**

**Appendix C. Marketing Operations configuration properties . . . . . 67**

Marketing Operations . . . . .	67
Marketing Operations   Navigation . . . . .	67
Marketing Operations   About . . . . .	69
Marketing Operations   umoConfiguration. . . . .	70
Marketing Operations   umoConfiguration   templates . . . . .	75
Marketing Operations   umoConfiguration   attachmentFolders . . . . .	76
Marketing Operations   umoConfiguration   email . . . . .	78
Marketing Operations   umoConfiguration   markup. . . . .	79
Marketing Operations   umoConfigurations   grid . . . . .	81
Marketing Operations   umoConfiguration   workflow . . . . .	82
Marketing Operations   umoConfiguration   integrationServices . . . . .	83
Marketing Operations   umoConfiguration   campaignIntegration . . . . .	84
Marketing Operations   umoConfiguration   reports . . . . .	84
Marketing Operations   umoConfiguration   invoiceRollup. . . . .	85
Marketing Operations   umoConfiguration   database . . . . .	86
Marketing Operations   umoConfiguration   listingPages . . . . .	88
Marketing Operations   umoConfiguration   objectCodeLocking . . . . .	89
Marketing Operations   umoConfiguration   thumbnailGeneration . . . . .	91
Marketing Operations   umoConfiguration   notifications . . . . .	91
Marketing Operations   umoConfiguration   notifications   email . . . . .	93
Marketing Operations   umoConfiguration   notifications   project . . . . .	95
Marketing Operations   umoConfiguration   notifications   projectRequest . . . . .	97
Marketing Operations   umoConfiguration   notifications   program . . . . .	98
Marketing Operations   umoConfiguration   notifications   marketingObject. . . . .	98
Marketing Operations   umoConfiguration   notifications   approval . . . . .	99
Marketing Operations   umoConfiguration   notifications   asset . . . . .	100
Marketing Operations   umoConfiguration   notifications   invoice . . . . .	100

**Notices . . . . . 103**

Trademarks . . . . .	105
----------------------	-----

---

## Chapter 1. Contacting IBM Unica technical support

If you encounter a problem that you cannot resolve by consulting the documentation, your company's designated support contact can log a call with IBM® Unica® technical support. Use the information in this section to ensure that your problem is resolved efficiently and successfully.

If you are not a designated support contact at your company, contact your IBM Unica administrator for information.

### Information to gather

Before you contact IBM Unica technical support, gather the following information:

- A brief description of the nature of your issue.
- Detailed error messages you see when the issue occurs.
- Detailed steps to reproduce the issue.
- Related log files, session files, configuration files, and data files.
- Information about your product and system environment, which you can obtain as described in "System information."

### System information

When you call IBM Unica technical support, you might be asked to provide information about your environment.

If your problem does not prevent you from logging in, much of this information is available on the About page, which provides information about your installed IBM Unica applications.

You can access the About page by selecting **Help > About**. If the About page is not accessible, you can obtain the version number of any IBM Unica application by viewing the `version.txt` file located under the installation directory for each application.

### Contact information for IBM Unica technical support

For ways to contact IBM Unica technical support, see the IBM Unica Product Technical Support website: (<http://www.unica.com/about/product-technical-support.htm>).



---

## Chapter 2. Preparing to Install


Installing IBM Unica products is a multi-step process that involves working with a number of software and hardware elements that are not provided by IBM Unica . While the IBM Unica documentation provides some guidance regarding specific configurations and procedures required to install IBM Unica products , for details on working with these systems that are not provided by IBM Unica , consult those products' documentation.

Before you begin to install the IBM Unica Marketing software, plan your installation, including both your business objectives and the hardware and software environment required to support them.

---

### Where to install Marketing Operations and the Marketing Platform

The following diagram provides a brief overview of where to install Marketing Operations. This is the basic installation that will function. You may require a more complex, disparate installation to meet your security and performance requirements.



**Marketing Operations**—For best performance, IBM Unica recommends that you install Marketing Operations on its own machine, where no other IBM Unica Marketing products are installed, or on a machine that it shares with only the Marketing Platform.

The Marketing Operations system tables should be **on a separate machine**.

**Marketing Operations reports package**—The reports package for Marketing Operations contains the IBM Cognos® package only. (Other applications also have reporting schemas to configure, but Marketing Operations does not.) Install the report package on the IBM Cognos system.

**Marketing Platform**—The Marketing Platform application contains the IBM Unica common navigation, reporting, user administration, security, scheduling, and

configuration management features. For each IBM Unica Marketing environment, you must install and deploy the Marketing Platform once.

---

## Prerequisites

The following are prerequisites for installing IBM Unica Marketing products.

### System requirements

For detailed system requirements, see the *Recommended Software Environments and Minimum System Requirements* guide for the IBM Unica Marketing products you plan to install.

#### JVM requirement

IBM Unica Marketing applications within a suite must be deployed on a dedicated Java Virtual Machine (JVM). IBM Unica Marketing products customize the JVM used by the web application server. You might need to create an Oracle WebLogic or WebSphere® domain dedicated to IBM Unica Marketing products if you encounter JVM-related errors.

#### Network domain requirement

IBM Unica Marketing products that are installed as a Suite must be installed on the same network domain, to comply with browser restrictions designed to limit cross-site scripting security risks.

### Marketing Platform requirement

Before you install any IBM Unica Marketing products, the Marketing Platform must be fully installed and deployed.

Marketing Platform must be running so that:

- The products you install can register their configuration properties and security roles.
- You can set values for configuration properties on the Marketing Platform's Configuration page.

For each group of products that you plan to have work together, you need to install the Marketing Platform only once.

### Knowledge requirement

To install IBM Unica Marketing products, you must possess or work with people who possess a thorough knowledge of the environment in which the products are installed. This knowledge includes the operating systems, databases, and web application servers.

### Client machines

Client machines should meet the following configuration requirements.

- The browser should not cache pages. In Internet Explorer, select **Tools > Internet Options > Settings** and choose the option that causes the browser to check for a newer version of the page on each visit.
- If pop-up blocker (ad blocker) software is installed on the client machine, Marketing Operations might not function properly. We recommend disabling pop-up blocker software while running Marketing Operations.



## Access permissions

Verify that your network permissions allow you to perform the procedures in this guide, and that you have access to all appropriate logins, including the following.

- The administrative password for your web application server.
- Administration access for all necessary databases.
- Write permission for all files that you must edit.
- Write permission for all directories where you must save a file, such as the installation directory and the backup directory if you are upgrading.
- Appropriate read/write/execute permissions to run the installer.
- The operating system account that you use to run the web application server and IBM Unica Marketing components must have read and write access to the relevant directory and subdirectories.
- On UNIX, the user account that performs the IBM Unica product installation must be a member of the same group as the user account that installed the web application server on which it will be deployed. This is because the web application server needs access to the product's file system.

On UNIX, all of the installer files for IBM Unica products must have full execute permissions (for example, `rwxr-xr-x`).

---

## Where to find more information

The instructions in this guide are designed to enable you to successfully perform a basic installation of Marketing Operations. Basic installation is a necessary step, but it is not the end of the installation process. IBM Unica Marketing products typically require additional configuration steps to prepare them for use in achieving your business objectives.

We define a basic installation as follows.

- All components of the product are installed.
- A system user is configured, with administrator-level access to the Marketing Operations system tables.

You can find information about advanced configurations as shown in the following table.

Topic	Guide
Customizing Unica reporting schemas and sample reports	<i>The Marketing Platform Administrator's Guide and Marketing Operations Administrator's Guide</i>
Configuring use of non-ASCII data or non-US locales	<i>Marketing Operations Administrator's Guide</i>
Configuring use of multiple languages and locales	<i>Marketing Operations Administrator's Guide</i>
Integrating with LDAP and web access control systems	<i>Marketing Platform Administrator's Guide</i>
Configuring SSL	<i>Marketing Platform Administrator's Guide</i>

---

## **If you are upgrading**

You should always read and understand the installation process as a whole before performing an installation. In addition, if you are upgrading, you should read and understand the section on preparing to upgrade and the upgrade section for each IBM Unica Marketing product.

---

## Chapter 3. Preparing the IBM Unica Marketing Operations data source

Before you can install IBM Unica Marketing Operations, you must set up the database and the JDBC connection for the Marketing Operations system tables.

Print the “Marketing Operations data source information checklist” on page 10 located at the end of this chapter. Then, as you complete each task in this chapter, fill in the information in your checklist. Having this information written down makes it easier for you to provide the database connection information when you run the IBM Unica installer later in the installation process.

---

### Step: Set up the Marketing Operations database

1. Work with a database administrator to create the required database for Marketing Operations.
2. Have the database administrator create an account for you to specify for a system user later in the installation process.  
This account must have CREATE, SELECT, INSERT, UPDATE, DELETE, and DROP rights.  
The database must use UTF-8 encoding.  
If you are using SQL Server, ensure that TCP/IP is enabled.  
If you are using DB2®, ensure that the buffer pool for the table space is at least 32K.
3. Print and complete the “Marketing Operations data source information checklist” on page 10. You use this information later in the installation process.

---

### Step: Configure the web application server for your JDBC driver

Use the following procedure to obtain the correct JDBC driver for your installation of Marketing Operations, and to configure your web application server to use it.

**Note:** If you are installing Marketing Operations on the same machine where you installed Marketing Platform, you have already completed this task. Continue to “Step: Create the JDBC connections in the web application server” on page 8

1. Obtain the latest Type 4 JDBC drivers and any required associated files (for example, Oracle requires several associated files) for the database you plan to use.  
You should always use the latest vendor-provided Type 4 driver.
  - If the driver does not exist on the machine where Marketing Operations will be installed, obtain it and copy it to any location on the Marketing Operations machine.
  - If you obtain the driver from a machine where the database client is installed, verify that the version is the latest supplied by the database vendor. See your IBM Unica consultant for a list of supported JDBC drivers.

The following list provides the driver file name or names for database types supported for IBM Unica Marketing system tables.

Database type	File(s)
Oracle 9g and 10g	ojdbc14.jar
Oracle 11	ojdbc5.jar
DB2	db2jcc.jar db2jcc_license_cu.jar - not present in V9.5
SQL Server	You must use version 1.2 of the SQL Server driver sqljdbc.jar

2. Include the full path to the driver in the CLASSPATH of the web application server where you plan to deploy Marketing Operations, as follows.
  - For all supported versions of WebLogic, add the jar files to the CLASSPATH variable in DOMAIN\_DIR\bin\setDomainEnv.cmd. Yours must be the first entry in the CLASSPATH values, to ensure that the web application server uses the correct driver. For example, if you are using SQL Server you might set the path as follows.

```
set CLASSPATH=c:\SQLDRIVER\sqljdbc.jar;%PRE_CLASSPATH%;
%WEBLOGIC_CLASSPATH%; %POST_CLASSPATH%;%WLP_POST_CLASSPATH%
```
  - For all supported versions of WebSphere, set the CLASSPATH in the Administration Console.

---

## Step: Create the JDBC connections in the web application server

The Marketing Operations web application must be able to communicate with both the Marketing Platform system tables and the Marketing Operations system tables. You create these JDBC connections in the web application server where you plan to deploy Marketing Operations.

**Important:** For the connection to the database holding the Marketing Operations system tables, you must use plands as the JNDI name. This value is the required JNDI name.

**Important:** For the connection to the database holding the Marketing Platform system tables, you must use UnicaPlatformDS as the JNDI name. This is the required JNDI name. If you are deploying Marketing Operations and Marketing Platform in the same JVM, this connection should already exist.

If you expect to have many concurrent users in Marketing Operations, you may need to increase the number of connections in your web server. For best results, set your web server to allow 50 connections.

## Information for JDBC connections

When you create a JDBC connection, you can use this section to help you determine some of the values you must enter. If you are not using the default port setting for your database, change it to the correct value.

This information does not exactly reflect all of the information required by the web application servers. Where this section does not provide explicit instructions, you may accept the default values. Consult the application server documentation if you need more comprehensive help.

## WebLogic

Use these values if your application server is WebLogic.

### SQLServer

- Driver: Microsoft's MS SQL Server Driver (Type 4) Versions: 2005
- Default port: 1433
- Driver class: com.microsoft.sqlserver.jdbc.SQLServerDriver
- Driver URL: jdbc:sqlserver://  
*your\_db\_host:your\_db\_port;databaseName=your\_db\_name*
- Properties: Add user=*your\_db\_user\_name*

### Oracle 10g and 11

- Driver: Other
- Default port: 1521
- Driver class: oracle.jdbc.OracleDriver
- Driver URL: jdbc:oracle:thin:@*your\_db\_host:your\_db\_port:your\_db\_service\_name*
- Properties: Add user=*your\_db\_user\_name*

### DB2

- Driver: Other
- Default port: 50000
- Driver class: com.ibm.db2.jcc.DB2Driver
- Driver URL: jdbc:db2://*your\_db\_host:your\_db\_port/your\_db\_name*
- Properties: Add user=*your\_db\_user\_name*

## WebSphere

Use these values if your application server is WebSphere.

### SQLServer

- Driver: N/A
- Default port: 1433
- Driver class: com.microsoft.sqlserver.jdbc.SQLServerConnectionPoolDataSource
- Driver URL: N/A

In the **Database Type** field, select **Other**.

After you create the JDBC Provider and Data Source, go to the Custom Properties for the Data Source, and add and modify properties as follows.

- *serverName=your\_SQL\_server\_name*
- *portNumber =SQL\_Server\_Port\_Number*
- *databaseName=your\_database\_name*
- *enable2Phase = false*

### Oracle 10g and 11

- Driver: Oracle JDBC Driver
- Default port: 1521
- Driver class: oracle.jdbc.OracleDriver

- Driver URL: jdbc:oracle:thin:@*your\_db\_host*:*your\_db\_port*:*your\_db\_service\_name*

**DB2**

- Driver: DB2 Universal JDBC Driver Provider
- Default port: 50000
- Driver class: com.ibm.db2.jcc.DB2Driver
- Driver URL: jdbc:db2://*your\_db\_host*:*your\_db\_port*/*your\_db\_name*

---

**Marketing Operations data source information checklist**

Data source type	
Data source name	
Data source account user name	
Data source account password	
JNDI name	p1ands
Path to the JDBC driver	

---

## Chapter 4. Installing IBM Unica Marketing Operations

After you have prepared the data sources, you are ready to install IBM Unica Marketing Operations. You obtain the installer, obtain the required connection information, and then run the installation wizard. If you are installing Marketing Operations in a cluster, you finish this set of tasks by creating an EAR file.

---

### Copying installation files (DVD only)

If you received your IBM Unica installation files on a DVD, or if you created a DVD from a downloaded ISO image file, you must copy its contents to a writable directory available to the system on which you are installing the IBM Unica products before running the installers.

You cannot run IBM Unica Marketing installers directly from read-only media, such as the installation DVD, an ISO image mounted read-only, or a write-restricted directory or volume.

**Note:** For more information about where to place the installation files, see “How the IBM Unica Marketing installers work.”

---

### How the IBM Unica Marketing installers work

Read this section if you are not familiar with the basic functions of the IBM Unica installer.

#### Single directory requirement for installer files

When you install IBM Unica enterprise products, you use a combination of installers.

- A master installer, which has Unica\_Installer in the file name
- Product-specific installers, which all have the product name as part of their file names

To install IBM Unica Marketing products, you must place the master installer and the product installers in the same directory. When you run the master installer, it detects the product installation files in the directory. You can then select the products you want to install.

When multiple versions of a product installer are present in the directory with the master installer, the master installer always shows the latest version of the product on the IBM Unica Products screen in the installation wizard.

#### Installing patches

You might be planning to install a patch immediately after you perform a new installation of an IBM Unica product. If so, place the patch installer in the directory with the base version and master installer. When you run the installer, you can select both the base version and the patch. The installer then installs both in correct order.

## Choosing product installation directories

You can install to any directory on any network-accessible system. You can specify an installation directory by entering a path or by browsing and selecting it.

You can specify a path relative to the directory from which you are running the installer by typing a period before the path.

If the directory you specify does not exist, the installer creates it, assuming that the user performing the installation has appropriate permissions.

The default top-level directory for IBM Unica installations is named `Unica`. The product installers then install in subdirectories under the `Unica` directory.

## Installation types

The IBM Unica installer performs the following types of installation.

- New installation – When you run the installer and select a directory where an IBM Unica Marketing product has never been installed, the installer automatically performs a new installation.
- Upgrade installation – When you run the installer and select a directory where an earlier version of an IBM Unica Marketing product has previously been installed, the installer automatically performs an upgrade installation. See the [Upgrading](#) chapters for details.
- Reinstallation – When you run the installer and select a directory where the same version of an IBM Unica Marketing product has previously been installed, the installer automatically performs a new installation. This overwrites all of the files in your existing installation directory.

If automatic database table creation is available for the product, and you select it, your data in the system tables is not modified, except for navigation menu items. If you have modified the navigation menu, you should use the Marketing Platform `configTool` utility to export those configuration properties, so you can restore them after you reinstall. If you have not modified the navigation menu, you do not need to do anything, as the installer recreates the default menu items.

You might see some errors because the installer will not be able to create tables in the database, as they already exist. You can safely ignore these errors.

## Installation modes

The IBM Unica installer can run in the following modes.

- Console (command line) mode

In console mode, you enter numbers to select options. If you do not enter a number, but press **Enter**, the default option is selected.

Default options are indicated by one of the following symbols:

– [X]

When this symbol appears, and you want to select an option other than the one it is next to, first enter the number shown next to the symbol to clear that option, followed by a comma and the number you do want to select.

– ->

When this symbol appears, and you want to select an option other than the one it is next to, enter the number you want to select. You do not have to clear the default option explicitly, as you do for the other type.

- Windows GUI or UNIX X Window System mode



- Unattended mode, which allows no user interaction  
Unattended, or silent, mode is used when you must install an IBM Unica product multiple times, for example when you set up a clustered environment. For more information, see “Installing multiple times using unattended mode.”

## Installing multiple times using unattended mode

If you must install IBM Unica Marketing products multiple times, for example when setting up a clustered environment, you might want to run the IBM Unica installer in unattended mode, which requires no user input.

### About the response files

Unattended (also known as silent) mode requires a file or set of files that provides the information that a user would enter in the installer wizard when using GUI or console modes. These are known as response files.

The installer automatically creates these response files when you perform an installation in console mode or Windows GUI or UNIX X Window System modes. Therefore, you would normally run the installer in one of these modes to create the response files before setting up an unattended run.

The response files are named `installer_product.properties`, except for the file for the IBM Unica installer itself, which is named `installer.properties`. The installer creates these files in the directory where the installer is located.

### Backup requirement for response files

You must create a backup version of the response files, because each time you run in unattended mode, the installer overwrites the `.properties` files with an empty version of the files. Therefore, you must replace the empty files with your backed-up version each time you run in unattended mode.

### Effect of unattended mode when you uninstall

When you uninstall a product that was installed using unattended mode, the uninstall is performed in unattended mode (without presenting any dialogs for user interaction).

## Creating EAR files for clustered deployments

IBM Unica supports clustering. The supported web application servers allow you to deploy and manage deployments from a single administration console. To take advantage of these features, you must use EAR files for deployments.

The master installer can create one or more EAR files containing the installed products that you specify. You then deploy the EAR file or files that include the products.

If you deploy more than one EAR file in a domain, the name you give the EAR file must be unique within that domain.

You can use the IBM Unica installer to create a new EAR file of your installed products at any time after your initial installation. See “To create an EAR file after running the installer” on page 16.

As mentioned in the *Marketing Platform Installation Guide*, if you are using WebLogic 9.2, do not include the Marketing Platform in an EAR file. See the WebLogic guidelines *Marketing Platform Installation Guide* for details.

## IBM Site ID

The installer might prompt you to enter your IBM Site ID. Your IBM Site ID can be found on the IBM Welcome letter, Tech Support Welcome letter, Proof of Entitlement letter, or other communications sent when you purchased your software.

IBM might use data provided by the software to better understand how customers use our products and to improve customer support. The data gathered does not include any information that identifies individuals.

If you do not want to have such information collected, after the Marketing Platform is installed, log on to the Marketing Platform as a user with administration privileges. Navigate to the **Settings > Configuration** page, and set the **Disable Page Tagging** property under the **Platform** category to **True**.

---

## Step: Obtain the installation archive

The IBM Unica Marketing product installation files are named according to the version of the product and the operating system with which they are meant to be used, except for UNIX files intended to be run in console mode, which are not operating system-specific. For UNIX, different files are used depending on whether the installation mode is X-windows or console. For example:

**Windows** - GUI and console mode - *ProductN.N.N.N\_win32.exe* is version N.N.N.N and is intended for installation on the Windows 32-bit operating system.

**UNIX** - X-windows mode - *ProductN.N.N.N\_solaris64.bin* is version N.N.N.N and is intended for installation on the Solaris 64-bit operating system.

**UNIX** - console mode - *ProductN.N.N.N.sh* is version N.N.N.N and is intended for installation on all UNIX operating systems.

---

## Step: Obtain required information

The installer prompts you to enter some information about your Marketing Platform system table database and Marketing Operations deployment. Gather this information before you start the installation.

### Database connection information

The installation wizard must be able to communicate with the Marketing Platform system table database, to register menu items, security information, and configuration properties. Each time you run the installer in a new location, you must enter the following database connection information for the **Marketing Platform system table database**.

- Database type.
- Database host name.
- Database port.
- Database name or schema ID.

- User name and password for the database account.

You obtained this information when you created the database or schema and filled out the Marketing Platform database information checklist.

The installer can create the Marketing Operations system tables during installation. If your company policy permits you to use this feature, you must provide the following connection information for the **Marketing Operations system table database** so the installer can automatically configure the database:

- Database type.
- Database host name.
- Database port.
- Database name or schema ID.
- User name and password for the database account.

You obtained this information when you created the database or schema and filled out the Marketing Operations database information checklist.

## Marketing Operations deployment information

Obtain the following information about your planned Marketing Operations deployment.

- Protocol: HTTP or HTTPS if SSL is implemented in the web application server.
- Host: The name of the machine on which Marketing Operations will be deployed.
- Port: The port on which the web application server listens.
- Domain name: The company domain of each machine where IBM Unica products are installed. For example, `mycompany.com`. All IBM Unica products must be installed in the same company domain, and you must enter the domain name in all lower-case letters. If there is a mis-match in domain name entries, you may encounter problems when you attempt to use Marketing Operations features or navigate among products. You can change the domain name after the products are deployed by logging in and changing values of the relevant configuration properties in the product navigation categories on the **Settings > Configuration** page.

---

## Step: Run the IBM Unica installer

Before you run the IBM Unica installer, verify that you have met the following prerequisites.

- You downloaded the IBM Unica installer and products you plan to install, and you put both the IBM Unica installer and the product installers in the same directory.
- You have available the information you gathered as described in “Step: Obtain required information” on page 14.

See the other topics in this section for details about the installer, or if you need help entering information in the wizard.

Run the IBM Unica installer as described here, and follow the instructions in the wizard.

Do not run the product installer directly. IBM Unica does not support installations performed in this way.

- **GUI or X-windows mode**

Run the Unica\_Installer file. On UNIX, use the .bin file.

- **Console mode**

Open a command prompt and from the directory where you downloaded the IBM Unica software, run the Unica\_Installer executable file as follows.

On Windows, run the Unica\_installer executable file with `-i console`. For example:

```
Unica_Installer_N.N.N.N_OS -i console
```

On UNIX, run the Unica\_installer.sh file with no switch.

- **Unattended mode**

Open a command prompt and from the directory where you downloaded the IBM Unica software, run the Unica\_Installer executable file with `-i silent`. On UNIX, use the .bin file. For example, to specify a response file located in the same directory as the installer:

```
Unica_Installer_N.N.N.N_OS -i silent
```

To specify a response file in a different directory, use `-f filepath/filename`. Use a fully qualified path. For example:

```
Unica_Installer_N.N.N.N_OS -i silent -f filepath/filename
```

For more information about unattended mode, see “Installing multiple times using unattended mode” on page 13.

---

## To create an EAR file after running the installer

To create an EAR file (typically for use in a cluster installation), you run the installer in console mode, from the command line. For Marketing Operations cluster installations, typically you create an EAR that includes the unica.war, the dashboard.war, and the plan.war. Then you deploy the EAR on each of the machines in your cluster.

1. Put the WAR files in a single directory.
2. If this is the first time you are running the installer in console mode, make a backup copy of the installer's `.properties` file for each of your installed products.

These files are located in the same directory where you have placed the IBM Unica product installers. They are named `installer_product.properties`, except for the file for the IBM Unica installer itself, which is named `installer.properties`.

This backup step is especially important when you run the installer in unattended mode and you need to make more than one EAR. When the installer runs in unattended mode, it clears these files. To create an EAR file, you need the information that the installer writes in the `.properties` files during the initial install.

3. Open a command window and change directories to the directory that contains the installer.
4. Run the installer executable with this option:

```
-DUNICA_GOTO_CREATEEARFILE=TRUE
```

On UNIX-type systems, run the .bin file rather than the .sh file.

The installer wizard runs.

5. Follow the instructions in the wizard.

6. If you need to create additional EAR files, overwrite the `.properties` file or files with the backup(s) you created before you ran the installer in console mode for the first time.



---

## Chapter 5. Configuring IBM Unica Marketing Operations before deployment

Whether you need to perform any of the tasks in this chapter depends on your installation. For example, if your company policy allowed you to use the installer to automatically configure your system tables, you do not need to do so manually.

Review the tasks in this chapter and complete any that are required for your installation before you deploy the IBM Unica Marketing Operations web application

---

### Step: Create and populate the Marketing Operations system tables with the umodbsetup utility, if necessary

The IBM Unica installer can create the Marketing Operations system tables during installation, but if your company policy does not permit you to create database tables in this way, you must manually run the database setup utility, umodbsetup.

The umodbsetup utility does one of the following.

- Option 1: Creates the required system tables in the Marketing Operations database and populates the tables with required default data.
- Option 2: Outputs the database creation and population scripts to a file that you or your DBA can then run in your own database client.

#### Configure environment variables

Before you run the umodbsetup utility, complete the following steps to configure the environment variables properly:

1. From the UNICA\_HOME\MarketingOperations\tools\bin directory, locate and open the setenv file in a text editor.
2. Make the following additions:
3. Save and close the file.
4. From the UNICA\_HOME\MarketingOperations\tools\bin directory, locate and open the the jdbc.properties file.
5. Set values for the following parameters. (See comments in the file for examples.)
  - umo\_driver.classname
  - umo\_data\_source.url
  - umo\_data\_source.login
  - umo\_data\_source.password
6. Save and close the file.

#### Run the database setup utility

From a command prompt or UNIX shell, navigate to the UNICA\_HOME\MarketingOperations\tools\bin directory. Run the umodbsetup utility and provide appropriate input for the parameters required for your situation.

For example, the following command runs a full database installation (rather than an upgrade), sets the locale to en\_US, and sets the logging level to high:

```
./umodbsetup.sh -t Full -L en_US -l high
```

Following is a description of all the possible variables for the utility:

-b	For upgrades only. The base version of the database that you are attempting to upgrade.  By default, the utility can detect the version of the database you are upgrading. However, if an earlier attempt to upgrade the database failed in some way, you use this variable with the -f variable to specify the correct base version.  For example, -f -b 8.2.0
-f	For upgrades only. Instructs the utility to use the base version specified by the -b variable, overriding the base version it may detect in the database. See the description of the -b variable, above.
-h	Provides help for the utility.
-l	The output from the actions that the umodbsetup utility performs are written to the umo-tools.log file located in the UNICA_HOME\MarketingOperations\tools\logs directory. This variable specifies the logging level.  You can set the logging level to high, medium, or low.
-L	Default Locale for Installation. For example, -L de_DE  The valid entries for locales are as follows: pt_BR, zh_CN, en_US, es_ES, de_DE, fr_FR, it_IT, ja_JP, ko_KR
-m	Outputs the scripts to a file in the UNICA_HOME\MarketingOperations\tools\logs directory, which you can then run manually. Use this option if you do not want the umodbsetup tool to run the script because there is a reason why you need to run scripts from your own database client application.
-t	Type of database installation. Valid values are Full and upgrade. For example, -t Full
-v	Verbose.

### Run the database scripts manually, if necessary

If you used the -m variable to output the scripts so you can run them from your own database client application, run the scripts now.

Do not deploy the plan.war file before you create and populate the system tables.

---

## Step: Register Marketing Operations manually, if necessary

If the Marketing Operations installer cannot connect to the Marketing Platform database to register the product, it displays an error message that notifies you of this failure. The installation process will proceed, but in this case you must import the product information into the Marketing Platform system tables manually.



The configTool utility mentioned in this procedure is located in the tools/bin directory under your Marketing Platform installation. For detailed instructions on using the configTool utility, see Appendix B, "The configTool utility," on page 63.

1. Set an environment variable named NAVIGATION\_DIR to the Marketing Operationsconf directory.
2. Run the configTool utility, using the following example commands as guidelines.

This imports configuration properties and menu items. Note that you run the utility as many times as there are files.

```
configTool.bat -v -i -p "Affinium" -f "%NAVIGATION_DIR%\plan_registration.xml"
```

```
configTool.bat -v -i -p "Affinium|suite|uiNavigation|mainMenu" -f "%NAVIGATION_DIR%\plan_navigation_operations.xml"
```

```
configTool.bat -v -i -p "Affinium|suite|uiNavigation|mainMenu" -f "%NAVIGATION_DIR%\plan_navigation_financials.xml"
```

```
configTool.bat -v -i -p "Affinium|suite|uiNavigation|mainMenu|Analytics" -f "%NAVIGATION_DIR%\plan_navigation_analytics.xml"
```

```
configTool.bat -v -i -p "Affinium|suite|uiNavigation|settingsMenu" -f "%NAVIGATION_DIR%\plan_navigation_settings.xml"
```

```
configTool.bat -v -i -p "Affinium|suite|uiNavigation|alerts" -f "%NAVIGATION_DIR%\plan_alerts_registration.xml"
```

---

## Step: Set environment variables (WebLogic/Windows only)

Perform this task only if you are planning to deploy Marketing Operations on a WebLogic web application server installed on a Windows machine.

On the machine where WebLogic is installed, add the following to the value of the Path System environment variable.

- Full path to the bin directory where the Sun JDK is installed.
- Full path to the server\bin directory where WebLogic is installed.



---

## Chapter 6. Deploying IBM Unica Marketing Operations

This chapter provides general guidelines for deploying Marketing Operations on WebSphere and WebLogic. If you created an EAR file after running the installer and your EAR file includes any other IBM Unica products, you must follow all the deployment guidelines detailed in the individual install guides for the products included in the EAR file in addition to those listed in this chapter.

It is assumed that you know how to work with your web application server. Consult your web application server documentation for details about things like how to use the Administration console.

---

### Guidelines for deploying Marketing Operations on WebSphere

**Note:** If you are deploying Marketing Operations on **WebSphere 7.0**, you need to apply PM00452: SHIP SDK APAR IZ63859 AS WAS IFIX to WebSphere, available at <http://www-01.ibm.com/support/docview.wss?rs=180&uid=swg24025051>. Without the patch, JavaScript files and other static resources will not get cached, resulting in errors being returned to the browser.

**Note:** If you are deploying Marketing Operations on **WebSphere 6.1** ensure that your version is **WebSphere 6.1.0.21 or higher**.

Complete the following steps.

1. Deploy the WAR or EAR file as an enterprise application and set the value of the context root to /plan.
2. WebSphere 6.1 to 7.5. Ensure that the JDK source level of the JSP compiler is set to Java 1.5, as follows.
  - a. In the form where you browse to and select the WAR or EAR file, select **Show me all installation options and parameters** so the Select Installation Options wizard runs.
  - b. In step 1 of the Select Installation Options wizard, select **Precompile JavaServer pages files**.
  - c. In step 3 of the Select Installation Options wizard, ensure that the **JDK Source Level** is set to 15.
3. In the server's **Web Container Settings > Session Management** section, enable cookies.
4. Rename the Marketing Operations session cookie from JSESSIONID to UMOSESSIONID.
5. Add the following entries to the Generic JVM arguments property.
  - -Dplan.home=Unica\_home\Marketing\_Operations, where Unica\_home is the path to the top-level IBM Unica directory and Marketing Operations is the path to the directory where you installed Marketing Operations. Typically this is Unica/MarketingOperations.
  - -Dclient.encoding.override=UTF-8
6. If your Marketing Operations system tables are in DB2, go to the data source's Custom Properties. Set the value for **resultSetHoldability** to 1.  
If you do not find a field named **resultSetHoldability**, add this value.

7. For best results, enter 1024 in both the **Initial Heap Size** and **Maximum Heap Size** fields.
8. In **Applications > Enterprise Applications** section, select the EAR file or WAR file that you deployed, then select **Class loading and update detection**.
9. Under **General Properties**, set **Class loader order** to **Classes loaded with local class loader first (parent last)**.
10. Set the class loader policy as follows.
  - If you deployed a WAR file, select **Single class loader for application**.
  - If you deployed an EAR file, select **ClassLoader for each WAR file in application**.
11. Start the deployed application.

## IBM WebSphere Application Server V7.0 requires fixpack 7.0.0.17 or higher

If you plan to use the IBM WebSphere Application Server V7.0 to deploy any IBM Unica Marketing products, you must apply Fix Pack 17 (also referred to as Version 7.0.0.17) or higher to address a security issue. This applies to all WebSphere Application Server 7.0 packages, including the version that is bundled with some IBM Unica Marketing products.

You can obtain Fix Pack 17 or higher here:

<http://www-01.ibm.com/support/docview.wss?rs=180&uid=swg27013594>.

Note that on that page, you must select the correct Fix Pack before you download.

For additional information about supported WebSphere versions for deploying IBM Unica Marketing products, see the *Recommended Software Environments and Minimum System Requirements* document for each product.

---

## Guidelines for deploying Marketing Operations on WebLogic

Before you begin, note the following:

- IBM Unica Marketing products customize the JVM used by WebLogic. You may need to create a WebLogic instance dedicated to IBM Unica Marketing products if you encounter JVM-related errors.
- Do not install more than one Marketing Operations application under the same WebLogic domain.
- Verify that the SDK selected for the WebLogic domain you are using is the Sun SDK by looking in the startup script (`startWebLogic.cmd`) for the `JAVA_VENDOR` variable. It should be set to `JAVA_VENDOR=Sun`. If it is set to `JAVA_VENDOR=BEA`, JRockit has been selected. JRockit is not supported. To change the selected SDK, refer to the WebLogic documentation.

Complete the following steps.

1. AIX® only. If your operating system is AIX, extract the Marketing Operations WAR file, delete the `xercesImpl.jar` file from `WEB_INF/lib` directory, and recreate the WAR file.

If the installer combined products in an EAR file, you must first extract that file to obtain the WAR file, and you must recreate the EAR file.

2. If you are configuring WebLogic to use the IIS plug-in, review the WebLogic documentation to determine whether you have additional requirements.
3. From the bin directory under your WebLogic domain directory, locate and open the setDomainEnv script in a text editor.  
Scroll to the JAVA\_OPTIONS property, and add the following entries. Use a space to separate entries.
  - `-Dplan.home=Unica_home\Marketing_Operations`  
Where *Unica\_home* is the path to the top-level IBM Unica directory and *Marketing\_Operations* is the path to the directory where you installed Marketing Operations. Typically this directory is Unica/MarketingOperations.
  - `-Dfile.encoding=UTF-8`
4. If deploying in a production environment, set the JVM memory heap size parameters to 1024 by adding the following line to the setDomainEnv script:  
Set `MEM_ARGS=-Xms1024m -Xmx1024m -XX:MaxPermSize=256m`
5. Save and close the file.
6. Restart WebLogic.
7. Deploy Marketing Operations as a web application module.
8. Start the deployed web application.



---

## Chapter 7. Configuring IBM Unica Marketing Operations after deployment

After you deploy and start the Marketing Operations application, you can log in and verify the installation. This chapter describes some basic configuration steps—configuring the system user and a test user, setting up email and markup—but there are additional system setup tasks in the *Marketing Operations Administrator's Guide*.

In addition, if you are using the IBM Unica Marketing reporting feature, you must perform the tasks described in Chapter 8, "Installing reports," on page 31.

---

### Step: Verify your installation

1. Access the IBM Unica Marketing URL using Internet Explorer.  
If you entered a domain when you installed, the URL is the following, where *host* is the machine where the Marketing Platform is installed, *domain.com* is the domain in which the host machine resides, and *port* is the port number on which the web application server listens.  
`http://host.domain.com:port/unica`
2. Log in using the default administrator login, which is `asm_admin`. You should have already changed this user's password when you verified your Platform installation.  
The first time you log in, the default value of this user's password is `password`. You are asked to change the password. You can enter the existing password, but you should choose a new one.  
The default home page is the Dashboard, which is a blank page until dashboards are set up. If you see a "404 page not found" message, it means that the Dashboard's WAR file has not been deployed properly. See the *Marketing Platform Installation Guide* for instructions about deploying the Dashboard WAR file.
3. Select **Settings > Configuration** and verify that Marketing Operations appears in the list on the left. Then expand the Marketing Operations section and verify that the **umoConfiguration** category appears in the list.
4. Optional. Make this page your "home" page until you configure the dashboard. That way you will not see a blank page each time you log in.

---

### Step: Give the `asm_admin` user access to Marketing Operations

While the default admin user `asm_admin` has access to the Marketing Operations configuration properties automatically, there are no default users with access to the Marketing Operations application until you configure them.

1. Create a group. For example, `Default-MarketOps-Group`.
2. Add the `PlanAdmin` and `PlanUser` roles to the group.
3. Add the `asm_admin` user to the group.
4. Restart the application server.
5. Log back in as `asm_admin`.
6. Verify that you have access to the Marketing Operations options on the **Operations** menu by selecting **Operations > Plans**.

---

## Step: Configure the markup option, if necessary

Marketing Operations provides markup tools for making comments on attachments. When Marketing Operations users send approvals for review, approvers can place their comments directly in the electronic file, where they can be viewed by other users.

Marketing Operations provides two types of markup tools.

- Adobe Acrobat markup: This markup tool requires the installation of Adobe Acrobat on each client machine. Users can apply all Acrobat commenting features, and then save the edited PDF in Marketing Operations.
- Native Marketing Operations markup: Native markup does not require Acrobat to be installed on client machines. The native markup option provides various markup functions that can be applied to files in PDF, HTML, JPG, PNG, GIF, and BMP format. Users can mark up whole websites if a URL is supplied. The comments can then be saved in Marketing Operations. Native markup is the default option.

The markup option is a global setting. (You cannot enable different markup options for different groups of users.)

### Optional. Configure the Adobe markup option

After you deploy the Marketing Operations application, the system is configured to use the native markup option by default. If you want to use the Adobe option, select **Settings > Configuration > Marketing Operations > umoConfiguration > markup**.

Then configure the markup properties with the following values:

- markupServerType—Set to "SOAP"
- markupServerURL—Set to the URL for the computer hosting the Marketing Operations server, including the number of the port where the web application server listens. The URL must contain the fully qualified host name. It should include the path shown here, with your values substituted for *plan\_server* and *port*.  
`http://plan_server:port/plan/services/collabService?WSDL`
- useCustomMarkup—Set to "True"

---

## Step: Configure the email settings

Marketing Operations workflows rely heavily on notification emails so it is a good idea to identify your SMTP server during installation.

1. Select **Settings > Configuration > Marketing Operations > umoConfiguration > email**.
2. Click **Edit Settings**.
3. Set the value of the `notifyEmailMonitorJavaMailHost` property to the machine name or IP address of your organization's SMTP server.
4. Specify a valid email address for the `notifyDefaultSenderEmailAddress` property. The system uses this address to send emails when there is no valid email address available to send a notification email to.
5. Save your changes.



---

## Step: Configure the integration with Campaign, if necessary

Marketing Operations optionally integrates with IBM Unica Campaign. When Marketing Operations and Campaign are integrated, you can use the marketing resource management features in Marketing Operations to create, plan, and approve campaigns.

When Campaign integration is enabled, you also have the option to enable offer integration so that you can perform offer lifecycle management tasks in Marketing Operations.

To enable your integration with Campaign, log in to Marketing Operations and set the following properties on the **Settings > Configuration** page:

- **Unica > Platform:**
  - IBM Unica Marketing Operations - Campaign integration (MO\_UC\_integration must be enabled)
  - IBM Unica Marketing Operations - Offer integration (optional, if Campaign integration is enabled)
- **Unica > Campaign > partitions > partition[n] > server > internal:**
  - MO\_UC\_integration (Set this option to Yes if you plan to enable any of the following three optional settings)
  - MO\_UC\_BottomUpTargetCells
  - Legacy\_campaigns
  - IBM Unica Marketing Operations - Offer integration
- **Unica > Marketing Operations > umoConfiguration > campaignIntegration:**
  - defaultCampaignPartition
  - webServiceTimeoutInMilliseconds

### Enable the advanced search feature

If you used IBM Unica Marketing Platform to set the required integration flags *before* you installed Marketing Operations, you must manually enable the advanced search feature.

To do so, in Marketing Operations:

1. Click **Settings > Marketing Operations Configuration**.
2. Click **Marketing Operations Upgrade**.
3. Check the **Upgrade Advance Search** check box. Clear all of the other check boxes.
4. Click **Upgrade**.
5. Log out and restart the Marketing Operations server.

For more information, see the *IBM Unica Marketing Operations and Campaign Integration Guide*.



---

## Chapter 8. Installing reports

For its reporting feature, Marketing Operations integrates with IBM Cognos 8 BI, a separate business intelligence application. Reporting relies on the following components:

- An installation of IBM Cognos 8 BI 8.4
- A set of IBM Unica Marketing components that integrate the IBM Unica system with the IBM Cognos 8 installation
- The example reports for the Marketing Operations application, built with IBM Cognos Report Studio

The Marketing Platform provides the IBM Unica side of the reporting integration. To finish installing reporting, you run the IBM Unica , Marketing Platform, and Marketing Operations report package installers on the IBM Cognos system.

This chapter describes how to install and set up reporting for Marketing Operations. For information about the individual components and how they interact with each other, see the *IBM Unica Marketing Platform Administrator's Guide*.

---

### Install reporting components

Installing and configuring IBM Unica product report packages is a multi-step process. Perform the tasks in this section to perform the installation.

#### Step: Set up a user with the ReportsSystem role, if necessary

Configure a user with access to the **Settings > Configuration** and **Settings > Report SQL Generator** pages so you can log in as this user when you need to configure the reporting properties.

The easiest way to do this is to assign the **ReportSystem** role to the **platform\_admin** user. This role is under **Report > PartitionN** on the User Roles and Permissions page.

See "To assign a role to or remove a role from a user" for general information on performing this task.

#### To assign a role to or remove a role from a user

1. Click **Settings > Users**.

The Users page displays.

2. Click the name of the user account that you want to work with.

The user detail page displays a list of the user's attributes, roles, groups, and data sources.

3. Click **Edit Roles**.

The Edit Roles page displays. Roles that are not assigned to the user are shown in the **Available Roles** box on the left. Roles that are currently assigned to the group are shown in the **Roles** box on the right.

4. Click a role name in the Available Roles box to select it.

The selected role name is highlighted.

5. Click **Add** or **Remove** to move the role name from one box to the other..

6. Click **Save Changes** to save your changes.  
A window displays the message, *Save Successful*.
7. Click **OK**.  
The user details display in the right pane, with your changes shown in the **Roles** list.

## Step: Determine which authentication mode to configure

The IBM Unica Authentication Provider is one of the components that integrates the IBM Cognos 8 BI system with IBM Unica Marketing. This component enables the IBM Cognos 8 BI applications to use IBM authentication to communicate with the IBM Unica Marketing system as though it were another IBM Unica application in the suite.

There are three authentication options: anonymous, authenticated, and authenticated per user.

- **Anonymous** means authentication is disabled. You use this mode to test your configuration without the added complication of authentication settings.
- **Authenticated** means that the communications between the IBM Unica system and the IBM Cognos system are secured at the machine level. You configure a single system user and give it with the appropriate access rights. By convention, this user is named "cognos\_admin."
- **Authenticated per user** means that the system evaluates individual user credentials.

Determine which authentication mode you need to configure. For a complete description of these options, see "Reporting and security" in the *IBM Unica Marketing Platform Administrator's Guide*.

## Optional step: Obtain email server information

If you want report results to be sent through email, obtain the following information.

- Host name or IP address of your SMTP server
- User name and password for the account on that server
- Email address for the default sender email

---

## Install and test IBM Cognos 8 BI

If your license agreement with IBM Unica grants you an IBM Cognos 8 BI license, you can download the IBM Cognos 8 BI 8.4 installation media from IBM Unica's Customer Central web site.

## IBM Cognos 8 BI, IBM Unica reporting, and domains

Before you begin, determine whether you are installing IBM Cognos 8 BI in the same domain as the IBM Unica Marketing suite. As a best practice, you are strongly encouraged to install IBM Cognos and the IBM Unica Marketing system in the same domain. If you do not, you must configure both IBM Cognos and IBM Unica Marketing to use SSL.

**Note:** After you install IBM Cognos 8, be sure to use Cognos Configuration to configure the Cognos URLs appropriately. On a Windows system, the default values for these URLs use the machine name "localhost." You must replace the "localhost" placeholder with the fully qualified host name, including domain.

## IBM Cognos 8 BI applications

IBM Cognos 8 BI is a collection of several applications, servers, and services, organized in a multi-tiered architecture. When you use IBM Cognos BI with your IBM Unica Marketing suite, you use the following subset of the Cognos 8 BI applications:

- IBM Cognos 8 BI Server, which provides storage for reports and folders (plus the queries and metadata models), the Content Manager, and so on.
- IBM Cognos Connection, a web application that you use to import, configure, and schedule the reports. This application also provides access to the following additional components:
  - Cognos Viewer - used for displaying reports. This is the module that displays the reports in your IBM Unica Marketing applications.
  - Report Studio - used for customizing reports and creating new ones. Note that when you purchase IBM Cognos 8 BI from IBM Unica , you are typically granted a license for one report author only.
  - Cognos Administration - used for configuring data sources and so on.
- IBM Cognos Framework Manager - the metadata modeling tool that you use to configure and customize the Cognos data model that supports the IBM Cognos 8 BI reports for your IBM Unica application.
- IBM Cognos Configuration - the configuration tool that you use to configure individual Cognos 8 BI components.

## IBM Cognos 8 BI installation options and Cognos documentation

Before you install IBM Cognos 8 BI, use the *IBM Cognos 8 BI Architecture and Deployment Guide* to learn about the various components, the installation options, and the configuration approaches recommended by IBM Cognos.

The IBM Cognos documentation uses two general categories to describe installations: installing in a distributed environment vs. installing all the components on one computer. For best results, do not install all components on one computer unless it is for a proof of concept or is a demonstration environment.

Installing the subset of IBM Cognos 8 BI applications that IBM Unica reporting uses requires that you use two IBM Cognos installers. One provides the IBM Cognos 8 BI server, the Content Manager, Cognos Configuration, and the Web-based user interfaces. You use a separate installer to install Framework Manager, the metadata modeling tool, because it must be installed on a Windows machine.

If you are installing all components on one computer you can use the *IBM Cognos 8 Quick Start Installation and Configuration Guide*. If you are installing in a distributed environment, use the full installation guide, *IBM Cognos 8 BI Installation and Configuration Guide*.

## IBM Cognos 8 BI web applications and the web server

IBM Unica does not provide the web server that hosts Cognos Connection and the other IBM Cognos 8 BI web applications. For Windows, the IBM Cognos documentation assumes that you are using Microsoft's IIS (Internet Information Services) but you can also use Apache HTTP.

If you use the Apache HTTP server, take care to set up the web aliases for the Cognos web applications in the `VirtualHost` configuration directive of the Apache `httpd.conf` file correctly: be sure to order the most specific alias first (the script alias) and set directory permissions for each alias.

### Example `httpd.conf` code snippet

The following example is from an Apache installation on a Windows system and the Apache server is running on the default port 80.

```
<VirtualHost *:80>
  ScriptAlias /cognos8/cgi-bin "C:/cognos/cgi-bin"
    <Directory "C:/cognos/cgi-bin">
      Order allow,deny
      Allow from all
    </Directory>
  Alias /cognos8 "C:/cognos/webcontent"
    <Directory "C:/cognos/webcontent">
      Order allow,deny
      Allow from all
    </Directory>
</VirtualHost>
```

**Note:** This `httpd.conf` file snippet is an example, only. Be sure to configure your web aliases appropriately for your systems.

## IBM Cognos 8 BI and locale

If you plan to install a localized version of your IBM Unica application report package (other than English), be sure to set the product locale to match the language of the application report package.

On the system running the Cognos Content Manager, open Configuration Manager, select **Actions > Edit Global Configuration**, and configure the locale for the IBM Cognos 8 BI system. For more information, see the *IBM Cognos Configuration User Guide*, available from the Help menu in Configuration Manager.

## Test the IBM Cognos 8 BI installation

Test your IBM Cognos installation using the following guidelines.

- Stop and restart the Cognos 8 BI server and check the `cogserver.log` file for errors. The file is located in the `logs` directory of your Cognos installation.
- Verify that database tables exist in the Cognos content store. There should be approximately 134 tables.

If you have a distributed Cognos environment with components installed on different machines, for example Cognos 8 BI server on a UNIX system and Framework Manager installed on a Windows machine, do the following.

- Verify that you can communicate with the internal and external dispatcher and the Content Manager from the machine where the Gateway is installed. To test components that do not have a user interface, enter the URI of the component in a browser's address field. A Cognos page should appear in the browser.
- Open Framework Manager and start to create a new project. This test ensures that you can log in. Check the log file again for errors.

---

## Install IBM Unica integration components and report models on the Cognos system

To integrate the IBM Unica Marketing suite with Cognos, you need the following installers.

- The IBM Unica master installer—You always run this installer to launch the other installers
- The Marketing Platform installer—You install the Cognos integration component from this installer
- The reports pack installer or installers for the products for which you want to implement reporting—You install the reports archive containing the models and sample reports from this installer

After you perform the installation, you perform the following configuration steps, as described in the remainder of this section.

- Configure IBM Unica and Cognos reporting properties in the Marketing Platform interface
- Import the report into Cognos Connection
- Configure Cognos to use IBM Unica authentication

### Installation checklist: IBM Cognos integration

The following list provides a high level overview of how to install and configure the IBM Unica components and reports on the IBM Cognos system. Each step is described in detail later in this section.

1. “Step: Obtain the JDBC driver for the Marketing Platform system tables.”
2. “Step: Install the reporting models and integration component on the IBM Cognos system” on page 36.
3. “Step: Create the IBM Cognos data sources for the IBM Unica application databases” on page 36.
4. “Optional step: Set up email notification” on page 37.
5. “Step: Configure the IBM Cognos application's firewall” on page 38.
6. “Step: Import the reports folder in Cognos Connection” on page 38.
7. “Step: Configure and publish the data model, if necessary” on page 39.
8. “Step: Enable internal links in the reports” on page 40.
9. “Step: Verify the data source names and publish” on page 40.
10. “Step: Configure the reporting properties in IBM Unica Marketing” on page 41.
11. “Step: Test your configuration without authentication enabled” on page 41.
12. “Configure IBM Cognos to use IBM Unica authentication” on page 42.
13. “Step: Test your configuration with authentication configured” on page 45.

### Step: Obtain the JDBC driver for the Marketing Platform system tables

Obtain the JDBC drivers and any required associated files that you used to configure the JDBC data source for the Marketing Platform's system tables when you set up the IBM Unica Marketing system. In a task later in this chapter, you configure Cognos to use IBM Unica authentication. Cognos needs the JDBC driver so it can obtain user information from the Marketing Platform system tables when it uses IBM Unica authentication.

Copy the JDBC driver to the machine where the Cognos Content Manager is installed, to the webapps\p2pd\WEB-INF\AAA\lib directory under your Cognos installation.

## Step: Install the reporting models and integration component on the IBM Cognos system

If yours is a distributed Cognos installation, determine which machine is running the Cognos Content Manager so you can run the IBM Unica installer on this machine.

1. Stop the IBM Cognos service.
2. On the machine where the Cognos Content Manager is installed, place the following IBM Unica installers in a single directory.
  - IBM Unica master installer
  - Marketing Platform
  - The reports pack installer or installers for the products for which you want to implement reporting
3. Run the IBM Unica master installer, and select the Marketing Platform and Reports packages you want to install.
4. Following the prompts, enter the connection information for the Marketing Platform system table database.
5. When the Marketing Platform installer launches and the **Platform Installation Components** window appears, select the **Reports for IBM 8 Cognos BI** option and clear the other options
6. When the Marketing Platform installer prompts for the path to the JDBC driver, enter the fully qualified path for the JDBC driver you copied to the Cognos system during the task “Step: Obtain the JDBC driver for the Marketing Platform system tables” on page 35.
7. When the Marketing Platform installer prompts for the location of the IBM Cognos installation, enter or browse to the top level of the IBM Cognos installation directory. Note that the default value provided in this field is a static value that is not based on the actual file structure of your IBM Cognos system.
8. When the report pack installer or installers displays installation options, select the **IBM Cognos Package for Product**, and clear the option for the reporting schemas.
 

This option copies the reports archive to the Cognos machine. You import this archive later.
9. Restart the IBM Cognos server.

## Step: Create the IBM Cognos data sources for the IBM Unica application databases

The IBM Cognos applications need their own data sources that identify the IBM Unica application databases – that is, the source of the data for the reports. The IBM Cognos data models provided in the IBM Unica reports packages are configured to use the following data source names:

*Table 1. Cognos data sources*

IBM Unica application	Cognos data source name(s)
Campaign	CampaignDS



Table 1. Cognos data sources (continued)

IBM Unica application	Cognos data source name(s)
eMessage	eMessageTrackDS
Interact	InteractDTDS for the design time database InteractRTDS for the runtime database InteractLearningDS for the learning database
Marketing Operations	MarketingOperationsDS
Leads	LeadsDS for the data mart tables

Use the following guidelines to create Cognos data sources for the IBM application databases:

- Use the Administration section of Cognos Connection.
- Use the default data source names that are shown in the Cognos data sources table. That way you can avoid altering the data model.
- The database type you select must match that of the IBM application database. Use the Cognos documentation and help topics to determine how to fill out database-specific fields.
- Be sure that you identify the IBM Unica application database and not the Cognos content store.
- When you configure the **Signon** section, select the **Password** and **Create a Signon that the Everyone group can use** options.
- In the **Signon** section, specify the user credentials for the IBM Unica application database user.
- Consult the Cognos data sources table and ensure that you create all the data sources required by the data model for the reports you are configuring. For example, the reporting data for Interact is located in three databases so you must create separate Cognos data sources for each one.
- If the Campaign system has more than one partition, create separate data sources for each partition. For example, if Campaign is configured for multiple partitions, create a separate Campaign data source for each partition.
- Verify that you have configured each data source correctly by using the **Test Connection** feature.

If you have any questions about configuring Cognos data sources, see the *IBM Cognos 8 Administration and Security Guide*, "Chapter 6: Data Sources and Connections" and the Cognos online help.

## Optional step: Set up email notification

When an IBM Cognos report is displayed in the IBM Unica Marketing interface, the Cognos Viewer toolbar in the window includes an option for sending the report as an attachment in an email. If you want to enable IBM Cognos to send IBM Unica reports as email attachments, configure notification in Cognos Configuration.

Use the following guidelines to set up email notification for the IBM Unica application reports:

- In Cognos Configuration, select **Data Access > Notification**.

- Specify the SMTP mail server using the host name or the IP address plus the port using the format **host:port** or **IPAddress:port**. For example, serverX:25 or 192.168.1.101:25. (The default SMTP port is usually 25.)
- To set the user name and password of the account, click in the **Value** column and click the pencil icon to open the **Value** dialog box.
- Specify the default sender using the pattern user@company.com.

If you have any questions about configuring email notification, see the Cognos Connection online help.

**Note:** When a user selects the email option from the Cognos Viewer toolbar, the email form that appears includes the option to insert a link to the report. When you acquire your IBM Cognos license from IBM Unica, this option is not supported. Users can send the reports as email attachments only.

## Step: Configure the IBM Cognos application's firewall

To configure the IBM Cognos firewall, you specify the IBM Unica system as a valid domain or host and disable validation.

1. In Cognos Configuration, select **Security > IBM Cognos Application Firewall**.
2. Set **Enable CAF validation** to false.
3. In the valid domains or hosts property, enter the fully qualified machine host name, including the domain and the port, for the system where the Marketing Platform is running.

**Important:** If you have a distributed IBM Unica Marketing environment, you must do this for every machine on which an IBM Unica product that renders Cognos reports is installed (for example, the Marketing Platform, which has dashboards; Campaign; and Marketing Operations).

For example:


serverXYZ.mycompany.com:7001

4. Save the configuration.
5. Restart the IBM Cognos service.

## Step: Import the reports folder in Cognos Connection

The IBM Unica application reports are in the zip file the report package installer copied to the IBM Cognos machine. Use the guidelines in this procedure to import the reports zip file into Cognos Connection.

1. Navigate to the Cognos8 directory under your report package installation on the IBM Cognos machine.
2. Copy the reports archive .zip file (for example Unica Reports for Campaign.zip) to the directory where your Cognos deployment archives are saved. In a distributed IBM Cognos environment, this is a location on the system running the Content Manager.  
The default location is the deployment directory under your IBM Cognos installation and it is specified in the Cognos Configuration tool installed with the Cognos Content Manager. For example: cognos\deployment.
3. Locate the Cognos8\ProductNameModel subdirectory under your report package installation on the Cognos machine.
4. Copy the entire subdirectory to any place on the system running Cognos Framework Manager that Framework Manager has access to.

5. Open Cognos Connection.
6. From the **Welcome** page, click **Administer Cognos Content**.  
If your **Welcome** page is turned off, turn it back on in the Cognos Connection user preferences.
7. Click the **Configuration** tab.
8. Select **Content Administration**.
9. Click **New Import** on the toolbar .
10. Follow these guidelines as you step through the **New Import Wizard**:
  - a. Select the reports archive that you copied in the previous procedure.
  - b. In the Public folders content list, select **all** the options, including the package itself (the blue folder).
  - c. If you do not want users to access the package and its entries yet, select **Disable after import**. You do this when you want to test the reports before you make them available to the IBM Unica application users.

## Step: Configure and publish the data model, if necessary

In “Step: Create the IBM Cognos data sources for the IBM Unica application databases” on page 36, you set up the IBM Unica system tables as a Cognos data source. If the data source login you used is not the owner of the IBM Unica application system tables, perform the step described here. If the data source login you used **does** own the IBM Unica application system tables, then you can skip this step.

1. Locate the Model directory under the reports package installation. Copy all of the files in this Model directory to anywhere under your Cognos Framework Manager installation directory. These files constitute the application-specific data model.
2. In Framework Manager, open the project file. The project file has a .cpf extension and the file name includes the IBM application name (for example, *ProductNameModel.cpf*).
3. Open the application’s data model and do the following.
  - a. In the Project Viewer, expand Data Sources.
  - b. Click the Application’s data source.
  - c. Update the data source as described in the following table.

Database	Fields
SQL Server	<ul style="list-style-type: none"> <li>• Catalog: Enter the IBM Unica application’s database name.</li> <li>• Schema: Enter the IBM Unica application’s database schema name. For example, dbo</li> </ul>
Oracle	<ul style="list-style-type: none"> <li>• Schema: Enter the IBM Unica application’s database schema name.</li> </ul>
DB2	<ul style="list-style-type: none"> <li>• Schema: Enter the IBM Unica application’s database schema name.</li> </ul>

4. Save and republish the package.  
If you need basic instructions on publishing a package in IBM Cognos, see the *Cognos Framework Manager User Guide*.

## Step: Enable internal links in the reports

The IBM Unica application reports have standard links. To enable these links to work properly, you must configure the Cognos firewall as described in “Step: Configure the IBM Cognos application's firewall” on page 38, and you must configure the redirect URL in the Cognos data model (the .cpf file) for the IBM Unica application reports, as follows.

1. From Cognos Framework Manager, browse to the *productNameModel* subdirectory you copied into the Framework Manager directory structure and select the .cpf file. For example, CampaignModel.cpf.
2. Select **Parameter Maps > Environment**.
3. Right click **Environment** and select **Edit Definition**.
4. In the **Redirect URL** section, select the **Value** field. Edit the server name and port number so they are correct for the IBM Marketing system, leaving the rest of the URL intact. The host name should include the domain name.

For example, for Campaign:

```
http://serverX.ABCompany.com:7001/Campaign/  
redirectToSummary.do?external=true&
```

For example, for Marketing Operations:

```
http://serverX.ABCompany.com:7001/plan/callback.jsp?
```

5. Save the model and publish the package:
  - a. From the navigation tree, expand the **Packages** node of the model.
  - b. Right click the package instance and select **Publish Package**.

## Step: Verify the data source names and publish

When you publish the model from Framework Manager to the Cognos content store, the name specified as the data source for the reports in the model must match the name of the data source you created in Cognos Connection. If you used the default data source names as described in “Step: Create the IBM Cognos data sources for the IBM Unica application databases” on page 36, the data source names match. If they do not, you must change the name of the data source in the model.

1. In Cognos Connection, determine the name(s) of the data source(s) you created.
2. In Framework Manager, select the **Open a Project** option.
3. Browse to the *productNameModel* subdirectory you copied into the Framework Manager directory structure and select the .cpf file. For example, CampaignModel.cpf.
4. Expand the **Data Sources** entry and examine the name(s) of the data sources. Do they match what you named them in Cognos Connection?
  - a. If they match, you are finished with this procedure.
  - b. If they do not match, select the data source instance and edit the name in the **Properties** section. Save your changes.
5. Publish the package to the Cognos content store

## Step: Configure the reporting properties in IBM Unica Marketing

There are several sets of properties for configuring reporting in IBM Unica Marketing. Some specify parameter values for the reporting components in the Marketing Platform and some specify URLs and other parameters for the IBM Cognos 8 BI system.

1. Log in to IBM Unica Marketing as the platform\_admin user or another user with the ReportsSystem role.

2. Select **Settings > Configuration > Reports > Integration > Cognos 8**

3. Set the value of the **Enabled** property to True.

4. Set the value of the **Domain** property to the name of the company domain on which the IBM Cognos system is running.

For example, xyzCompany.com.

Note that if your company uses subdomains, the value in this field should include the company domain and the subdomain.

5. Set the value of the **Portal URL** property, to the URL of the Cognos Connection portal. Use a fully qualified host name, including the domain and any subdomains (specified in the **Domain** property).

For example: http://MyCognosServer.xyzCompany.com/cognos8/cgi-bin/cognos.cgi

You can find this URL in the Cognos Configuration utility under **Local Configuration > Environment**.

6. In the **Dispatch URL** field, specify the URL of the primary Cognos Content Manager dispatcher. Use a fully qualified host name, including the domain and any subdomains (specified in the **Domain** property).

For example: http://MyCognosServer.xyzCompany.com:9300/p2pd/servlet/dispatch

You can find this URL in the Cognos Configuration utility under **Local Configuration > Environment**.

7. Leave **Authentication mode** set to anonymous for now.

8. Save the settings.

## Step: Test your configuration without authentication enabled

After the reports are installed and configured but before you enable authentication, test the setup by running some reports.

1. Verify that IBM Unica Marketing is running and that the IBM Cognos 8 BI service is running.

2. Log in to IBM Unica as a user with application access and create some data. (Otherwise the reports have nothing to show.)

3. Open Cognos Connection.

4. Navigate to the report folders you imported and click the link to a basic report. For example, for Campaign, select **Public Folders > Campaign > Campaign > Campaign Summary**.

If the report fails, verify that you configured the Cognos data source for the IBM Unica application database correctly. See “Step: Create the IBM Cognos data sources for the IBM Unica application databases” on page 36.

5. Click a link in the report.

If the internal links from the reports do not work, the redirect URL is not configured correctly. See “Step: Enable internal links in the reports” on page 40.

6. Log in to the IBM Unica application as a user with application access and navigate to the **Analysis** page.

When you specify the URL for the IBM Unica application, be sure to use a fully qualified host name with your company domain (and subdomain, if appropriate). For example:

```
http://serverX.ABCompany.com:7001/unica
```

7. Click the link to the same report that you tested in Cognos.

If you cannot view the report, it is likely that the IBM Cognos firewall is not configured correctly. See “Step: Configure the IBM Cognos application's firewall” on page 38.

8. Click a link in the report.

If the internal links from the reports do not work, the redirect URL is not configured correctly. See “Step: Enable internal links in the reports” on page 40.

9. Open an individual item, click the **Analysis** tab, and verify that the report is correct.

---

## Configure IBM Cognos to use IBM Unica authentication

The IBM Unica Authentication Provider enables the Cognos applications to use IBM Unica authentication to communicate with the IBM Unica Marketing system as though it were another IBM Unica application in the suite.

Before you begin the procedures in this section, be sure that you know which authentication mode you plan to configure ("authenticated" or "authenticated per user). If you need more information, see “Step: Determine which authentication mode to configure” on page 32.

### Step: Create the reporting system user, if necessary

**Note:** If you are setting the authentication mode to "authenticated per user" skip this procedure and continue to “Step: Configure the Cognos authentication properties in IBM Unica Marketing” on page 43.

When you create the reports system user, you create the user and add data source credentials to the user that holds login information for IBM Cognos 8 BI. In this way, you configure two sets of logins for the same user:

- One for the IBM Unica system: the user name and password specified for the reports system user (cognos\_admin)
- One for IBM Cognos 8 BI: the user name and password specified as data source credentials for the reports system user

1. Log in to IBM Unica Marketing as the platform\_admin user.
2. Select **Settings > Users**.
3. Create an IBM Unica user with the following attributes:
  - a. User name: cognos\_admin
  - b. Password: admin
4. Create a new data source for the user with the following attributes:
  - a. Data Source: Cognos
  - b. Data Source Logon: cognos\_admin

Ensure that the user name in the data source exactly matches the user name of the IBM Unica user you created in step 3.

- c. Data Source Password: admin
5. Add the Reports System role to the user.
6. If IBM Unica Marketing is configured to expire user passwords, log out and then log back in as the reporting system user (cognos\_admin). This step ensures that you interact with the IBM Unica security "change password" challenge and reset the password before you log in to IBM Cognos as this user in a later task.

## Step: Configure the Cognos authentication properties in IBM Unica Marketing

1. Log in to IBM Unica Marketing as the platform\_admin user.
2. Select **Settings > Configuration**.
3. Expand **Reports > Integrations > Cognos 8**.
4. Set the value of the **Authentication Mode** property by selecting either **authenticated** or **authenticatedPerUser**, as appropriate for your system.
5. **For "authenticated" only.** Verify that the values in the **Authentication user name** and **Authentication datasource name** fields match those of the user and data source you created in the previous task, "Step: Create the reporting system user, if necessary" on page 42.
6. If the IBM Cognos installation and the IBM Unica installation are not in the same domain, change the value in the **Enable form authentication** property to true, which means that IBM Unica security should use form-based authentication in place of cookies.

**Important:** When the **Enable form authentication** property is set to true, the login name and password appended to the Cognos URL appear as clear text unless IBM Unica Marketing and IBM Cognos are configured to use SSL communication. Even with SSL configured, the user name and password appear as clear text in the HTML source code when you "view source" in a displayed report. For this reason, you should install IBM Cognos and IBM Unica Marketing in the same domain.

7. Save the new settings.
8. **For "authenticatedPeruser" only.** Assign the ReportUser role to the default asm\_admin user. You do this because to test reports, you need a user with access to the IBM Unica application and with access to the report data. The platform\_admin user does not have access to the IBM Unica application features.

## Step: Configure IBM Cognos to use the IBM Unica Authentication Provider

In this task, you use the Cognos Configuration and Cognos Connection applications to configure the IBM Cognos 8 BI 8.4 applications to use the IBM Unica Authentication Provider.

1. On the machine running the Cognos Content Manager, open Cognos Configuration
2. Select **Local Configuration > Security > Authentication**.
3. Right-click **Authentication** and select **New resource > Namespace**.
4. Complete the fields as follows, and then click OK:

- a. **Name:** Unica
  - b. **Type:** Custom Java Provider.
5. On the **Resource Properties** page, complete the fields as follows and then save your changes:
    - a. **NamespaceID:** Unica
    - b. **Java class name:** com.unica.report.adapter.UnicaAuthenticationProvider
  6. Stop and restart the IBM Cognos 8 BI service.  
 On a Windows system, sometimes the Cognos interface indicates that the service is stopped when it is not. To ensure that the service has really stopped, use the Windows Administrative tools to stop the service.
  7. Under **Local Configuration > Security > Authentication**, right-click **Unica** and select **Test**.  
 If Cognos Connection displays an error, examine the cogserver.log file, located in the logs directory of your Cognos installation to determine the problem.
  8. Log in to Cognos Connection as follows to verify that the IBM Unica Authentication provider is configured correctly:
    - If you set the authentication mode to "authenticated," log in as the cognos\_admin (report system) user.
    - If you set the authentication mode to "authenticated per user," log in as the asm\_admin user.
 If IBM Cognos displays the error "The 3rd party provider returned an unrecoverable exception," expand the error message. If it states "invalid credentials," you made an error entering your user credentials. Try again. However, if it states "password expired," IBM Unica Marketing expired the password. Log in to IBM Unica application as the reporting system user and reset the password. Then try logging in to Cognos Connection again.  
 If you still cannot log in to Cognos Connection, examine the cogserver.log file, located in the logs directory of your Cognos installation, to determine the problem.
  9. When you can successfully log in to Cognos Connection, open Cognos Configuration again.
  10. Select **Local Configuration > Security > Authentication > Cognos**.
  11. Disable anonymous access to IBM Cognos 8 BI by setting **Allow anonymous access?** to false.
  12. Save your changes.
  13. Stop and restart the IBM Cognos service.  
 If the IBM Cognos service cannot communicate successfully with the authentication provider, it cannot start. If the IBM Cognos service fails to start, verify your configuration by retracing the steps in this procedure.
  14. **Distributed systems only.** If your IBM Cognos system has backup Content Managers configured for failover support, repeat this procedure on all the servers with Content Manager installed.

At this point, anyone logging in to an application on the Cognos system must be authenticated by IBM Unica Marketing. Additionally, the authentication namespace "Unica" now appears in the IBM Cognos user interface for logon and security administration tasks.



## Step: Test your configuration with authentication configured

After configuring IBM Cognos to use IBM Unica authentication, test the system again.

1. Verify that IBM Unica Marketing is running and that the IBM Cognos service is running.
2. Open Cognos Connection.
3. Navigate to the report folders you imported and click the link to a basic report. For example, for Campaign, select **Public Folders > Campaign > Campaign > Campaign Summary**.

If the report fails, verify that you configured the IBM Cognos data source for the IBM Unica application database correctly. See “Step: Create the IBM Cognos data sources for the IBM Unica application databases” on page 36.

4. Click a link in the report.

If the internal links from the reports do not work, the redirect URL is not configured correctly. See “Step: Enable internal links in the reports” on page 40.

5. Log in to IBM Unica Marketing and navigate to the **Analysis** page.

When you specify the URL for the IBM Unica application, be sure to use a fully qualified host name with your company domain (and subdomain, if appropriate). For example:

`http://serverX.ABCompany.com:7001/unica`

6. Click the link to the same report that you tested in IBM Cognos.

If you see error messages about security, it is likely that the IBM Unica Authentication Provider is not configured correctly. See “Configure IBM Cognos to use IBM Unica authentication” on page 42.

If you are prompted to enter credentials for authentication, it is likely that the domain name is missing from one of your URLs. Log in to IBM Unica Marketing as a user with admin privileges. Then select **Settings > Configuration** and ensure that the URLs in the following properties include the domain name and any appropriate subdomain name.

- **Reports > Integration > Cognos > Portal URL and Dispatch URL**
- Any URL properties for the IBM Unica applications, for example: **Campaign > navigation > serverURL**

7. Click a link in the report.

If you are prompted to enter credentials for authentication, it is likely that the domain name is missing from one of the URLs.

8. Open an individual item, click the **Analysis** tab, and verify that the report is correct.

If you see error messages about security, it is likely that the IBM Unica Application Provider is not configured correctly.

---

## Next steps for reporting

At this point, reporting is working properly and the example reports are in their default state.

- If you configured the system to use the “authenticated per user” mode, ensure that the appropriate IBM Unica users can run the reports from the IBM Unica applications. The easiest way to do this is to assign the default ReportsUser role to the appropriate user groups or users.
- For general information about the Framework Manager data models and Report Studio reports, see the chapter named “Configuring Reporting” in the *IBM Unica*

*Marketing Platform Administrator's Guide*. For information about configuring and customizing the Marketing Operations reports, see the chapter on reports in the *IBM Unica Marketing Operations Administration Guide*.

- To use the Cognos dashboard reports in your dashboards, see the chapter on Dashboards in the *IBM Unica Marketing Platform Administrator's Guide*.

---

## Chapter 9. Installing IBM Unica Marketing Operations in a cluster

To install IBM Unica Marketing Operations in a cluster, you follow the instructions from chapters 2 through 7 and supplement those instructions with the information from this chapter.

When you install Marketing Operations in a cluster, there are many ways to configure the installation. However, the basic process is this:

1. Run the installers on one system - typically the administration server (or whatever the equivalent is for your application server type).
2. Create and share a file directory to hold the upload files for all the Marketing Operations installations.
3. Create the EAR file, and then deploy it on each machine in the cluster.
4. Configure each system to share the same Marketing Platform system tables and the same Marketing Operations system tables.
5. Configure each system to use the shared file directory.
6. Determine which machine in the cluster should send notifications. Then suppress the notification process on all the other machines.

---

### Installing on a cluster in WebLogic

If you are installing Marketing Operations on a cluster in WebLogic, use the following changes and additions when completing the tasks in chapters 2 through 7.

#### Preparing to Install

Before you begin, you must create a WebLogic domain for the cluster. For help with this step, see the WebLogic documentation.

#### Preparing the data sources

The data source chapter instructs you to create a database for Marketing Operations and then configure a JDBC data source for it in your application server. When you complete these tasks for a cluster, note the following additional instructions:

- You must configure the web application servers to use the correct JDBC driver on all machines in the cluster.
- Create the data source for the Marketing Platform system tables (UnicaPlatformDS) on both the administration server and the cluster members.
- When you create the data source for the Marketing Operations system tables (plands), deploy it to the cluster, and not to the administration server. Select **All servers in the cluster**.

#### Installing the products

When you follow the instructions for running the installer, be sure that you install Marketing Platform and Marketing Operations once on the machine that you have designated as the administration server for the cluster. You do not need to install

the software on each cluster member. Instead, you install it once (on the administration server), create the EAR, and then deploy the EAR file on each cluster member.

## Additional pre-deployment steps

Before you deploy Marketing Operations, complete the following tasks in addition to the ones specified in the pre-deployment configuration chapter:

- Share the top-level directory in which Marketing Operations is installed. For example, say that if Marketing Operations is installed in the following directory: C:\UMOC\cluster\Unica\MarketingOperations. In this case, you would share the entire UMOC\cluster directory.
- Create and share a folder on the administration server to contain the upload files for Marketing Operations. This folder is known as the Shared\_UMO\_Artifacts folder. All cluster members must have full control (read, write, change, and delete) of this folder. Placing this folder below the IBM Unica home directory in the local file system hierarchy is optional.

## Deploying the applications on WebLogic

In addition to the instructions in the deployment chapter, note the following additions and one exception.

### 1. How to set the Source accessibility option

When you deploy the EAR on the administration server, set the **Source accessibility** option to **Use the defaults defined by the deployment's targets**.

### 2. Additional instructions for setting the JAVA\_OPTIONS

Remember to configure the JAVA\_OPTIONS property in the setenv file on **each machine** in the cluster.

The path you specify in the plan.home property must point to the **shared installation directory**.

There are two additional parameters to set for clusters:

- -DPLAN\_CONFIG\_GUID=Plan
- On the machines that should not send notifications, set the "suppress notifications" parameter as follows: -Dplan.suppressNotification=true  
Set this property on every node except one - the one you want to send notifications.

### 3. How to set the MEM\_ARGS

The **memory setting is different** for clusters than it is for a non-clustered installation. Use the following:

```
-Xms32m -Xmx256m -XX:MaxPermSize=512m
```

## Additional post-deployment steps

If you are using a plug-in for load balancing, you must do the following:

- Log in, select **Settings > Configuration**, and configure the following URL parameters so that all references to the Marketing Operations server use the proxy host and port.
  - Marketing Operations | navigation | serverURL
  - Marketing Operations | umoConfiguration | markup | markupServerURL
  - Marketing Operations | umoConfiguration | notifications | notifyPlanBaseURL
- Edit the web.xml file for the proxy server and add the following tag to override the cookie name:

```
<init-param>
  <param-name>CookieName</param_name>
  <param-value>UMOSESSIONID</param-value>
</init-param>
```

---

## Installing on a cluster in WebSphere

If you are installing Marketing Operations on a cluster in WebSphere, use the following changes and additions when completing the tasks in chapters 2 through 7.

### Preparing the data sources

The data source chapter instructs you to create a database for Marketing Operations and then configure a JDBC data source for it in your application server. When you complete these tasks for a cluster on WebSphere, note the following additional instructions:

- The Marketing Operations database must be on a machine that is accessible to all machines in the cluster, but it does not need to be on a machine in the cluster.
- When configuring the JDBC provider, specify the cluster as the scope.

### Installing the products

When you follow the instructions for running the installer, be sure that you install Marketing Platform and Marketing Operations once, on a machine that is accessible to all machines in the Marketing Operations cluster.

You do not need to install the software on each cluster member. Instead, you install it once, create the EAR, and then deploy the EAR file on each cluster member.

### Additional pre-deployment steps

Before you deploy Marketing Operations, complete the following tasks in addition to the ones specified in the pre-deployment configuration chapter:

- Share the top-level directory in which Marketing Operations is installed. For example, say that Marketing Operations is installed in C:\UMOC\cluster\Unica\MarketingOperations. In this case, you would share the entire UMOC\cluster directory.
- Create and share a folder on the administration server to contain the upload files for Marketing Operations. This folder is known as the Shared\_UMO\_Artifacts folder. All cluster members must have full control (read, write, change, and delete) of this folder. Placing this folder below the IBM Unica home directory in the local file system hierarchy is optional.

## Additional deployment steps

In addition to the instructions in the deployment chapter, note the following additions

### 1. Mapping modules to servers

When you set the options in the **Select Installation Options** wizard for WebSphere, select the cluster and the web server when mapping modules to servers.

### 2. Additional instructions for the Generic JVM property

Remember to configure the Generic JVM property on **each machine** in the cluster.

The path you specify in the `plan.home` and other properties must point to the **shared installation directory**.

There are four additional parameters to set for clusters:

- `-DPLAN_CONFIG_GUID=Plan`
- `-Dplan.log.config=\\umoMachine\SharedUnicaHome\MarketingOperations\conf\plan_log4j_client.xml`
- `-Dplan.local.log.dir=local_log_dir` (where *local\_log\_dir* is the writeable folder on this physical machine where Marketing Operations creates logs)
- On the machines that should not send notifications, set the "suppress notifications" parameter as follows: `-Dplan.suppressNotification=true`  
Set this property on every node except one - the one you want to send notifications.

## Configuring Unica products after deployment

Remember to rename the session cookie to `UMOSESSIONID` for every server in the cluster.

If you are using a plug-in for load balancing, you must log in, select **Settings > Configuration**, and configure the following URL parameters so that all references to the Marketing Operations server use the proxy host and port.

- Marketing Operations | navigation | serverURL
- Marketing Operations | umoConfiguration | markup | markupServerURL
- Marketing Operations | umoConfiguration | notifications | notifyPlanBaseURL

---

## Configure the shared folder properties

Before you deployed the Marketing Operations application, you created a folder known as the `Shared_UMO_Artifacts` folder. Now you need to set the values of the properties that specify the folder for various upload files to point to that location.

1. Log in and select **Settings > Configuration**.
2. Select **Marketing Operations > umoConfiguration > templates**.
3. Click **Edit Settings** and then update the value for the `templatesDir` property to point to a subfolder in the `Shared_UMO_Artifacts` folder.
4. Save your changes
5. Select **Marketing Operations > umoConfiguration > attachmentFolders**.

6. Click **Edit Settings** and then update the values for all the properties in this category to point to subfolders in the Shared\_UMO\_Artifacts folder.
7. Save your changes.

---

## Configuring Ehcache

Ehcache is an open source java distributed cache for general purpose caching, Java EE and light-weight containers. To avoid having to re-start the Marketing Operations server after making changes to templates when your installation is in a cluster, perform the appropriate procedure in this section to edit the `plan_ehcache.xml` file. Select the procedure based on whether you are using RMI or multicast for cache replication.

**Important:** If your installation is upgraded from a previous version, some or all of the sections in the `plan_ehcache.xml` file may not be present. In that case, you must add the sections shown and then edit them as described below.

### To configure ehcache with RMI

Navigate to the `UNICA_HOME\MarketingOperations\conf` directory and open the `plan_ehcache.xml` file in a text editor. Then make the following edits:

- Un-comment the following section of the file.

You must customize the items shown in bold (machineA, machineB, and port) to reflect your environment. Provide a pipe-separated list of all machines in the cluster, using fully qualified host names.

```
<!--
<cacheManagerPeerProviderFactory
class="net.sf.ehcache.distribution.RMICacheManagerPeerProviderFactory"
properties="peerDiscovery=manual,
rmiUrls=//<b>machineA:40000</b>/planApplicationCache|//<b>machineB</b>:
40000/planApplicationCache"/>

<cacheManagerPeerListenerFactory
class="net.sf.ehcache.distribution.RMICacheManagerPeerListenerFactory"
properties="port=<b>40000</b>, socketTimeoutMillis=20000"/>
-->
```

- Un-comment the following section of the file.

```
<!--
<cacheEventListenerFactory
class="net.sf.ehcache.distribution.RMICacheReplicatorFactory"
properties="replicateAsynchronously=true, replicatePuts=true,
replicateUpdates=true, replicateUpdatesViaCopy=true,
replicateRemovals=true"/>
<cacheEventListenerFactory
class="com.unicacorp.uap.common.cache.PlanCacheEventListenerFactory
"net.sf.ehcache.distribution.RMIBootstrapCacheLoaderFactory" />
-->
```

- If the following lines are present in the file, remove them.

```
<bootstrapCacheLoaderFactory class=net.sf.ehcache.distribution.
RMIBootstrapCacheLoaderFactory"/>
```

### To configure ehcache with multicast

Navigate to the `UNICA_HOME\MarketingOperations\conf` directory and open the `plan_ehcache.xml` file in a text editor. Then make the following edits:

- Un-comment the following section of the file.

You must customize the items shown in bold (multicastGroupAddress and multicastGroupPort) to reflect the multicast group and port in your environment.

```
<!--<cacheManagerPeerProviderFactory
class="net.sf.ehcache.distribution.RMICacheManagerPeerProviderFactory"
properties="peerDiscovery=automatic, multicastGroupAddress=230.0.0.1,
multicastGroupPort=4446, timeToLive=32"/>

<cacheManagerPeerListenerFactory
class="net.sf.ehcache.distribution.RMICacheManagerPeerListenerFactory"/>
-->
```

- Un-comment the following section of the file.

```
<!--
<cacheEventListenerFactory
class="net.sf.ehcache.distribution.RMICacheReplicatorFactory"
properties="replicateAsynchronously=true, replicatePuts=true,
replicateUpdates=true, replicateUpdatesViaCopy=true,
replicateRemovals=true"/>
<cacheEventListenerFactory
class="com.unicacorp.uap.common.cache.PlanCacheEventListenerFactory" />
-->
```

- Also, if the following lines are present in the file, remove them.

```
<bootstrapCacheLoaderFactory
class="net.sf.ehcache.distribution.RMIBootstrapCacheLoaderFactory"/>
```



---

## Chapter 10. Upgrading IBM Unica Marketing Operations

Before you upgrade from any version of Affinium Plan or Marketing Operations, be sure to read all of the topics in this section to ensure a successful upgrade process.

---

### Upgrade prerequisites for all IBM Unica Marketing products

There are many prerequisites you must meet before upgrading IBM Unica Marketing products.

To upgrade any IBM Unica Marketing product, you must meet all of the prerequisites listed under "Prerequisites" on page 4 in the "Preparing to Install" chapter.

In addition, you must meet the prerequisites listed in this section.

#### **User account requirement (UNIX only)**

On UNIX, the same user account that installed the product must perform the upgrade.

#### **32-bit to 64-bit version upgrades**

If you are moving from a 32-bit to a 64-bit version of an IBM Unica Marketing product, ensure that the following conditions are met.

- The database drivers for your product data sources are also 64-bit
- All relevant library paths (for example, startup or environment scripts) correctly reference the 64-bit versions of your database drivers

#### **Knowledge requirements**

These instructions assume that the person performing the upgrade has an understanding of the following.

- The basic function of the IBM Unica installer, as described in "How the IBM Unica Marketing installers work" on page 11
- General IBM Unica Marketing product functionality and components, including the structure of the file system
- The installation and configuration process for the source product version and for the new version
- Maintaining configuration properties in your source and target systems
- The installation and configuration process for reports, if you are using these reports

---

## About upgrading with existing campaign projects or requests

If you are upgrading a Marketing Operations system that is integrated with Campaign and you have existing campaign projects for which you have not created the corresponding linked campaigns, create the linked campaigns before you upgrade to Marketing Operations. Likewise, if you have existing project requests for campaign projects, accept or reject the requests before you upgrade to Marketing Operations.

If you do not link them before you upgrade, then when you attempt to create the campaigns for these projects or accept these requests after the system is upgraded, the campaigns will not be linked properly to the Marketing Operations projects.

**Note:** Upgrading from Plan 7.5.x to Marketing Operations 8.x disables any existing campaign templates. You cannot use these templates to create new projects after upgrading.

---

## Marketing Operations upgrade scenarios

Follow these guidelines for upgrading to Marketing Operations 8.5.0.

Source version	Upgrade path
Any 7.5.0 line or earlier version of Affinium Plan.	An upgrade from these versions directly to Marketing Operations is not supported. Perform the following steps. <ol style="list-style-type: none"><li>1. Obtain the 7.5.2 Affinium Plan software and upgrade to that version, following the instructions in the <i>Affinium Plan 7.5.2 Installation Guide</i>.</li><li>2. Upgrade your 7.5.2 installation of Affinium Plan to Marketing Operations, as described in this guide.</li></ol>
Affinium Plan version 7.5.1 and 7.5.2, and Marketing Operations 8.0.0, 8.1.0, 8.1.1., and 8.2.0	Upgrade your installation to version 8.5.0 as described in this guide.

---

## To upgrade Marketing Operations

Note that older versions of Marketing Operations were named Affinium Plan. All versions are now referred to as Marketing Operations in this guide.

To upgrade Marketing Operations, you back up your existing installation, ensure that the Platform is upgraded and running, run the installer, restore any trigger procedures, deploy the upgraded applications, and then run some post-deployment processes.

### Step: Back up the system before you begin the upgrade

Before you begin your upgrade process, complete the steps in this task to ensure that you have properly backed up everything in your current installation.

1. **Version 7.5.x only.** If you are upgrading from a 7.5.x version, make a copy of the icons and templates subfolders of your images folder.

Do not undeploy your existing version before you complete this task.

- On WebLogic, this directory is located under the WebLogic staging directory or at *Affinium\_Home/Affinium/Plan/unwar/images*, where *Affinium\_Home* is the top-level directory where you installed Affinium Plan.
  - On WebSphere, this directory is located under the WebSphere deployed directory or at *../installedApps/<node>/plan.ear/plan.war/images*
2. Undeploy your existing version of Marketing Operations.
  3. Back up all files and directories in your existing installation folder.

**Note:** If you have modified the sample trigger procedures or the *procedure\_plugins.xml* file, you must restore files from the backup after upgrading, to avoid losing trigger procedures. The files you must restore are in the */devkits/integration/examples/src/procedure* folder.

4. Back up the database that holds your Marketing Operations system tables.

## Step: Verify that the Marketing Platform has been upgraded

You must upgrade and deploy the Marketing Platform before you upgrade Marketing Operations.

Verify that the Marketing Platform was successfully upgraded and deployed before you continue.

## Step: Run the installer and update the configuration properties

Before you run the installer, ensure that you have the appropriate database connection information for both the Marketing Platform database and the Marketing Operations database.

1. Run the IBM Unica installer and specify your existing installation directory as the installation directory to use. For more information, see “Step: Run the IBM Unica installer” on page 15.

The installer detects that you have an earlier version installed and runs in upgrade mode.

2. Follow the instructions in the installation wizard. Note the following.
  - If you are upgrading from version 7.5.x or older, the installer must move the images associated with your templates to a new directory (*MarketOps\_HOME\conf\images*). The installer knows the default location of this directory (the "unwar" directory) but the person who installed your existing version may have used a different name for the directory. If you know your installation uses the default location, click the **Restore Default Folder** option. Otherwise, click the **Choose** button and navigate to the location of the unwar directory.
  - Starting with version 8.5, the installer can upgrade the database automatically. If your company policy does not permit you to use this feature, select the **Manual database setup** option and then run the scripts manually after installing the software and before deploying the web application.
3. When the installer finishes, log in to the upgraded Marketing Platform application. Select **Settings > Configuration**. Review the properties in the Marketing Operations categories and set or change any parameters that are new for the current version of Marketing Operations.

## Step: Upgrade your database manually, if necessary

The IBM Unica installer can upgrade the Marketing Operations database during the upgrade, but if your company policy does not permit this, you must use the database setup utility, `umodbsetup`, to upgrade the tables manually.

The `umodbsetup` utility does one of the following.

- Option 1: Upgrades the system tables in the Marketing Operations database and populates the tables with required default data.
- Option 2: Outputs the database upgrade and population scripts to a file that you or your DBA can then run in your own database client.

### Configure environment variables

Before you run the `umodbsetup`, complete the following steps to configure the environment variables properly:

1. From the `UNICA_HOME\MarketingOperations\tools\bin` directory, locate and open the `setenv` file in a text editor.
2. Make the following additions:
3. Save and close the file.
4. From the `UNICA_HOME\MarketingOperations\tools\bin` directory, locate and open the `jdbc.properties` file.
5. Set values for the following parameters. (See comments in the file for examples.)
  - `umo_driver.classname`
  - `umo_data_source.url`
  - `umo_data_source.login`
  - `umo_data_source.password`
6. Save and close the file.

### Run the database setup utility

From a command prompt or UNIX shell, navigate to the `UNICA_HOME\MarketingOperations\tools\bin` directory. Run the `umodbsetup` utility and provide appropriate input for the parameters required for your situation.

For example, the following command runs an upgrade, sets the locale to `en_US`, and sets the logging level to `medium`:

```
./umodbsetup.sh -t upgrade -L en_US -l medium
```

Following is a description of all the possible variables for the utility:

-b	<p>For upgrades only. The base version of the database that you are attempting to upgrade.</p> <p>By default, the utility detects the version of the database you are upgrading. However, if an earlier attempt to upgrade the database failed in some way, the version may have been updated even though the upgrade failed. When you have corrected the problem and run the utility again, you use this variable with the -f variable to specify the correct base version.</p> <p>For example, -f -b 8.2.0</p>
-f	<p>For upgrades only. Instructs the utility to use the base version specified by the -b variable, overriding the base version it may detect in the database. See the description of the -b variable, above.</p>
-h	<p>Provides help for the utility.</p>
-l	<p>The output from the actions that the umodbsetup utility performs are written to the umo-tools.log file located in the UNICA_HOME\MarketingOperations\tools\logs directory. This variable specifies the logging level.</p> <p>You can set the logging level to high, medium, or low.</p>
-L	<p>Default Locale for Installation. For example, -L de_DE</p> <p>The valid entries for locales are as follows: pt_BR, zh_CN, en_US, es_ES, de_DE, fr_FR, it_IT, ja_JP, ko_KR</p>
-m	<p>Outputs the scripts to a file in the UNICA_HOME\MarketingOperations\tools\logs directory, which you can then run manually. Use this option if you do not want the umodbsetup tool to run the script because there is a reason why you need to run scripts from your own database client application.</p>
-t	<p>Type of database installation. Valid values are Full and upgrade. For example, -t Full</p>
-v	<p>Verbose.</p>

## Run the database scripts manually, if necessary

If you used the -m variable to output the scripts so you can run them from your own database client application, run the scripts now.

Do not deploy the plan.war file before you upgrade and populate the system tables.

## Step: Deploy the upgraded web application and run the upgrade processes

1. Deploy Marketing Operations in your web application server as described in Chapter 6, “Deploying IBM Unica Marketing Operations,” on page 23.
2. Restart the application server.
3. When the application is running, log in and verify that the upgrade worked properly. Select **Setting > Configuration** and verify that Marketing Operations appears in the list on the left. Then expand the Marketing Operations section and verify that the **umoConfiguration** category appears in the list.

4. Select **Settings > Marketing Operations Settings**.
5. Scroll to the bottom of the page and then click **Marketing Operations Upgrade** to display the list of process that upgrades things like forms, alerts, and metrics.
6. Run each of the upgrade processes.  
Click **Help** for descriptions of each process and details about how they work.
7. Do one of the following:
  - If you are upgrading from version 8.2, you are finished with this procedure. Continue to “Step: Restore trigger procedures, if necessary.”
  - If you are upgrading from any version earlier than 8.2, continue with step 8 of this procedure.
8. To upgrade your markup items, do the following.
  - a. Determine the value specified for the approvalUploadDir parameter on the **Settings > Configuration > Marketing Operations > umoConfiguration > attachmentFolders** page.
  - b. Navigate to the tools\admin\markup directory under your Marketing Operations installation.
  - c. Run the markup\_redo\_pdf\_to\_jpg script and specify the full path to the folder specified in the approvalUploadDir parameter. The script ensures that attachments display properly.
  - d. For existing plans, programs, projects, and marketing objects that had markup enabled on attachments, tell the owners that they must enable markup again. (For attachments added after the upgrade, markup is enabled by default.)

## Step: Restore trigger procedures, if necessary

If you were using triggers, complete the steps in this task to restore them.

1. Restore the procedures and the procedure\_plugins.xml file from the backup you made earlier. Put them in the default location for the files:  
UNICA\_HOME\MarketingOperations\devkits\integration\examples\src\procedure.
2. If necessary, rebuild the integration services procedures using the build file located in the UNICA\_HOME\MarketingOperations\devkits\integration\examples\build directory under your Marketing Operations installation.
3. Update the following parameters on the **Settings > Configuration > Marketing Operations > umoConfiguration > attachmentFolders** page. Set the values to point to the directories you created in the previous step.
  - Set graphicalRefUploadDir to UNICA\_HOME\MarketingOperations\graphicalrefimages
  - Set templateImageDir to UNICA\_HOME\MarketingOperations\images
  - Set recentDataDir to UNICA\_HOME\MarketingOperations\recentdata
  - Set workingAreaDir to UNICA\_HOME\MarketingOperations\umotemp

## Step: Upgrade reporting

In IBM Unica Marketing version 8.x, reporting is one of the components provided by the Marketing Platform. That is, IBM Unica reporting is no longer provided in a separate web application as it was in Affinium Reports 7.5.x. When you upgraded to Marketing Platform version 8.x, the installer also upgraded the reporting feature.

- If you are upgrading from 7.5.x to 8.5.0, follow the appropriate procedures in the "Upgrading Reporting" chapter in the *IBM Unica Marketing Platform 8.5 Installation Guide* to upgrade reporting for your system.
- If you are upgrading from 8.0.x or 8.1.x to 8.5.0, use the procedure in the "Upgrading Reporting" chapter in the *IBM Unica Marketing Platform 8.5 Installation Guide* to install the new data model and reports.
- If you are upgrading from version 8.2.x, you are finished with your upgrade.

---

## Upgrading Marketing Operations in a clustered environment

Use the following guidelines when you upgrade multiple instances of Marketing Operations (or Affinium Plan) in a clustered environment.

- Undeploy all of the instances of Marketing Operations (or Affinium Plan).
- Follow the directions in this chapter to upgrade.
- Use your web application server's automatic deployment features to deploy the EAR file in your cluster.





---

## Appendix A. Uninstalling IBM Unica products

You might need to uninstall an IBM Unica product if you are doing the following.

- Retiring a system.
- Removing an IBM Unica product from your system.
- Freeing up space on a system.

When you install IBM Unica Marketing products, an uninstaller is included in the `Uninstall_Product` directory, where *Product* is the name of your IBM Unica product. On Windows, an entry is also added to the **Add or Remove Programs** list in the Control Panel.

Running the IBM Unica uninstaller ensures that all configuration files, installer registry information, and user data are removed from the system. If you manually remove the files in your installation directory instead of running the uninstaller, the result might be an incomplete installation if you later reinstall an IBM Unica product in the same location.

---

### To uninstall IBM Unica products

Follow these instructions to properly remove IBM Unica products from your system.

**Note:** On UNIX, the same user account that installed IBM Unica Marketing must run the uninstaller.

1. Undeploy the IBM Unica Marketing product web application from WebSphere or WebLogic.
2. Shut down WebSphere or WebLogic.
3. Stop any running processes that are related to the product you are uninstalling. For example, stopping the Campaign or Optimize Listener services before uninstalling those products.
4. Run the IBM Unica Marketing uninstaller and follow the directions in the wizard.

The uninstaller is located in the `Uninstall_Product` directory, where *Product* is the name of your IBM Unica Marketing product.

When you uninstall a product that was installed using unattended mode, the uninstall is performed in unattended mode (without presenting any dialogs for user interaction).



---

## Appendix B. The configTool utility

The properties and values on the Configuration page are stored in the Marketing Platform system tables. The configTool utility imports and exports configuration settings to and from the Marketing Platform system tables.

### When to use configTool

You might want to use configTool for the following reasons.

- To import partition and data source templates supplied with Campaign, which you can then modify and/or duplicate using the Configuration page.
- To register (import configuration properties for) IBM Unica Marketing products, if the product installer is unable to add the properties to the database automatically.
- To export an XML version of configuration settings for backup or to import into a different installation of IBM Unica Marketing.
- To delete categories that do not have the **Delete Category** link. You do this by using configTool to export your configuration, then manually deleting the XML that creates the category, and using configTool to import the edited XML.

**Important:** This utility modifies the `usm_configuration` and `usm_configuration_values` tables in the Marketing Platform system table database, which contain the configuration properties and their values. For best results, either create backup copies of these tables, or export your existing configurations using configTool and back up the resulting file so you have a way to restore your configuration if you make an error when using configTool to import.

### Valid product names

The configTool utility uses product names as parameters with the commands that register and unregister products, as described later in this section. With the 8.0.0 release of IBM Unica Marketing, many product names changed. However, the names recognized by configTool did not change. The valid product names for use with configTool are listed below, along with the current names of the products.

Product name	Name used in configTool
Marketing Platform	Manager
Campaign	Campaign
Distributed Marketing	Collaborate
eMessage	emessage
Interact	interact
Optimize	Optimize
Marketing Operations	Plan
CustomerInsight	Insight
NetInsight	NetInsight
PredictiveInsight	Model
Leads	Leads

## Syntax

```
configTool -d -p "elementPath" [-o]
```

```
configTool -i -p "parent ElementPath" -f importFile [-o]
```

```
configTool -x -p "elementPath" -f exportFile
```

```
configTool -r productName -f registrationFile [-o]
```

```
configTool -u productName
```

## Commands

### **-d -p "*elementPath*"**

Delete configuration properties and their settings, specifying a path in the configuration property hierarchy.

The element path must use the internal names of categories and properties, which you can obtain by going to the Configuration page, selecting the wanted category or property, and looking at the path displayed in parentheses in the right pane. Delimit a path in the configuration property hierarchy using the | character, and surround the path with double quotes.

Note the following.

- Only categories and properties within an application may be deleted using this command, not whole applications. Use the -u command to unregister a whole application.
- To delete categories that do not have the **Delete Category** link on the Configuration page, use the -o option.

### **-i -p "*parentElementPath*" -f *importFile***

Import configuration properties and their settings from a specified XML file.

To import, you specify a path to the parent element under which you want to import your categories. The configTool utility imports properties *under* the category you specify in the path.

You can add categories at any level below the top level, but you cannot add a category at same level as the top category.

The parent element path must use the internal names of categories and properties, which you can obtain by going to the Configuration page, selecting the desired category or property, and looking at the path displayed in parentheses in the right pane. Delimit a path in the configuration property hierarchy using the | character, and surround the path with double quotes.

You can specify an import file location relative to the tools/bin directory or you can specify a full directory path. If you specify a relative path or no path, configTool first looks for the file relative to the tools/bin directory.

By default, this command does not overwrite an existing category, but you can use the -o option to force an overwrite.

**-x -p "elementPath" -f exportFile**

Export configuration properties and their settings to an XML file with a specified name.

You can export all configuration properties or limit the export to a specific category by specifying a path in the configuration property hierarchy.

The element path must use the internal names of categories and properties, which you can obtain by going to the Configuration page, selecting the wanted category or property, and looking at the path displayed in parenthesis in the right pane. Delimit a path in the configuration property hierarchy using the | character, and surround the path with double quotes.

You can specify an export file location relative to the current directory or you can specify a full directory path. If the file specification does not contain a separator (/ on Unix, / or \ on Windows), configTool writes the file to the tools/bin directory under your Marketing Platform installation. If you do not provide the xml extension, configTool adds it.

**-r productName -f registrationFile**

Register the application. The registration file location may be relative to the tools/bin directory or may be a full path. By default, this command does not overwrite an existing configuration, but you can use the -o option to force an overwrite. The *productName* parameter must be one of those listed above.

Note the following.

- When you use the -r option, the registration file must have <application> as the first tag in the XML.  
Other files may be provided with your product that you can use to insert configuration properties into the Marketing Platform database. For these files, use the -i option. Only the file that has the <application> tag as the first tag can be used with the -r option.
- The registration file for the Marketing Platform is named Manager\_config.xml, and the first tag is <Suite>. To register this file on a new installation, use the populateDb utility, or rerun the Marketing Platform installer as described in the *IBM Unica Marketing Platform Installation Guide*.
- After the initial installation, to reregister products other than the Marketing Platform, use configTool with the -r option and -o to overwrite the existing properties.

**-u productName**

Unregister an application specified by *productName* . You do not have to include a path to the product category; the product name is sufficient. The *productName* parameter must be one of those listed above. This removes all properties and configuration settings for the product.

## Options

**-o**

When used with -i or -r, overwrites an existing category or product registration (node).

When used with `-d` allows you to delete a category (node) that does not have the **Delete Category** link on the Configuration page.

## Examples

- Import configuration settings from a file named `Product_config.xml` located in the `conf` directory under the Marketing Platform installation.  
`configTool -i -p "Affinium" -f Product_config.xml`
- Import one of the supplied Campaign data source templates into the default Campaign partition, `partition1`. The example assumes that you placed the Oracle data source template, `OracleTemplate.xml`, in the `tools/bin` directory under the Marketing Platform installation.  
`configTool -i -p "Affinium|Campaign|partitions|partition1|dataSources" -f OracleTemplate.xml`
- Export all configuration settings to a file named `myConfig.xml` located in the `D:\backups` directory.  
`configTool -x -f D:\backups\myConfig.xml`
- Export an existing Campaign partition (complete with data source entries), save it to a file named `partitionTemplate.xml`, and store it in the default `tools/bin` directory under the Marketing Platform installation.  
`configTool -x -p "Affinium|Campaign|partitions|partition1" -f partitionTemplate.xml`
- Manually register an application named `productName`, using a file named `app_config.xml` located in the default `tools/bin` directory under the Marketing Platform installation, and force it to overwrite an existing registration of this application.  
`configTool -r product Name -f app_config.xml -o`
- Unregister an application named `productName`.  
`configTool -u productName`

---

## Appendix C. Marketing Operations configuration properties

This section describes the IBM Unica Marketing Operations configuration properties on the Configuration page.

**Note:** Properties in the **Marketing Operations > about** category are for internal use only; you should not edit these values.

---

### Marketing Operations

#### **supportedLocales**

##### **Description**

Specifies the locales available in your installation of IBM Unica Marketing Operations. List only the locales that you are actually using. Each locale you list uses memory on the server. The amount of memory used depends on the size and number of templates.

If you add locales after the initial installation or upgrade, you must run the upgrade servlets again. See upgrade documentation for details.

If you change this value, you must stop and restart your Marketing Operations deployment before the change takes effect.

##### **Default value**

en\_US

#### **defaultLocale**

##### **Description**

Specifies the supported locale in which you want IBM Unica Marketing Operations to display for all users, unless explicitly overridden for specific users by Marketing Operations administrators.

If you change this value, you must stop and restart your Marketing Operations deployment before the change takes effect.

##### **Default value**

en\_US

---

### Marketing Operations | Navigation

#### **welcomePageURI**

##### **Description**

The Uniform Resource Identifier of the IBM Unica Marketing Operations index page. This value is used internally by IBM Unica Marketing applications. You should not change this value.

##### **Default value**

affiniumPlan.jsp?cat=projectlist

#### **projectDetailpageURI**

##### **Description**

The Uniform Resource Identifier of the IBM Unica Marketing Operations detail page. This value is used internally by IBM Unica Marketing applications. You should not change this value.

**Default value**

blank

**seedName**

**Description**

Used internally by IBM Unica Marketing applications. You should not change this value.

**Default value**

Plan

**type**

**Description**

Used internally by IBM Unica Marketing applications. You should not change this value.

**Default value**

Plan

**httpPort**

**Description**

The port number used by the application server for connections to the IBM Unica Marketing Operations application.

**Default value**

7001

**httpsPort**

**Description**

The port number used by the application server for secure connections to the IBM Unica Marketing Operations application.

**Default value**

7001

**serverURL**

**Description**

The URL of the IBM Unica Marketing Operations installation.

**Default value**

`http://servername:port/plan`

**logoutURL**

**Description**

Used internally. You should not change this value.



IBM Unica Marketing Platform uses this value to call the logout handler of each registered application if the user clicks the logout link in suite.

**Default value**

`/uapsysservlet?cat=sysmodules&func=logout`

**displayName**

**Description**

Used internally.

**Default value**

Plan

---

## Marketing Operations | About

The **Marketing Operations>About** configuration properties list information about your IBM Unica Marketing Operations installation. You cannot edit these properties.

**displayName**

**Description**

The display name of the product.

**Default value**

IBM Unica Marketing Operations

**releaseNumber**

**Description**

The currently installed release.

**Default value**

8.5.0.x.x

**copyright**

**Description**

The copyright year.

**Default value**

2011

**os**

**Description**

The operating system on which IBM Unica Marketing Operations is installed.

**Default value**

**java**

**Description**

The current version of java.

**Default value**

### **support**

**Description**

Read documentation and contact support at <https://customercentral.unica.com>.

**Default value**

<https://customercentral.unica.com>

### **appServer**

**Description**

**Default value**

blank

### **otherString**

**Description**

**Default value**

blank

---

## **Marketing Operations | umoConfiguration**

### **serverType**

**Description**

Application Server Type. Used for Calendar Export.

**Default value**

WEBLOGIC

**Valid Values**

WEBLOGIC or WEBSHERE

### **userManagerSyncTime**

**Description**

Time in milliseconds to between scheduled synchronizations with IBM Unica Marketing Platform.

**Default value**

10800000 milliseconds (3 hours)

### **firstMonthInFiscalYear**

**Description**

Set to the month that you would like your account fiscal year to begin. The Summary tab for the account contains a view-only table which lists budget information by month for the account's fiscal years. The first month in this table is determined by this parameter.

January is represented by 0. To have your fiscal year to begin in April, set firstMonthInFiscalYear to 3.

**Default value**

0

**Valid Values**

integers 0 to 11

**maximumItemsToBeRetainedInRecentVisits****Description**

The maximum number of items to save in recent list.

**Default value**

10

**maxLimitForTitleString****Description**

The maximum number of characters that can display in a page title. If titles are longer than the specified number, IBM Unica Marketing Operations clips them.

**Default value**

40

**maximumLimitForBulkUploadItems****Description**

The maximum number of attachments you can upload at the same time.

**Default value**

5

**workingDaysCalculation****Description**

Controls how IBM Unica Marketing Operations calculates durations.

**Default value**

all

**Valid Values**

- Business days only : includes working days only. Does not include weekends and days off.
- Business days + Weekends : includes working days and weekends. Does not include days off.
- Business days + Days off : includes all working days and days off. Does not include weekends.
- all : includes all days in the calendar.

**validateAllWizardSteps****Description**

When creating a program, project, or request using the wizard, IBM Unica Marketing Operations automatically validates that the required fields on

the current page have values. This parameter controls whether Marketing Operations validates the required fields on all pages (tabs) when a user clicks **Finish**.

**Default value**

true

**Valid Values**

- true : Marketing Operations checks the required fields on pages that the user did not visit (except workflow, tracking, and attachments). If a required fields is blank, the wizard opens that page and displays an error message.
- false : Marketing Operations does not check validate required fields on pages the user did not visit.

**enableRevisionHistoryPrompt**

**Description**

Ensures that users are prompted to add change comments when saving a project/request or approval.

**Default value**

false

**Valid Values**

true | false

**useForecastDatesInTaskCalendar**

**Description**

Specifies the type of dates used when displaying tasks in calendar view.

**Default value**

false

**Valid Values**

- true : displays tasks using the forecast/actual dates.
- false : displays tasks using the target dates.

**copyRequestProjectCode**

**Description**

Controls whether you want to carry the Project Code (PID) over from a request to a project. If you set this parameter to false, the project and the request use different codes.

**Default value**

true

**Valid Values**

true | false

**projectTemplateMonthlyView**

**Description**

Controls whether the monthly view is allowed in a project template's workflow.

**Default value**

false

**Valid Values**

true | false

**disableAssignmentForUnassignedReviewers**

**Description**

Specifies how work is assigned by role for approvals. The parameter `disableAssignmentForUnassignedReviewers`, controls the behavior of "Assign work by Role..." for assignment of approvers in workflow approvals based on the per People tab.

**Default value**

false

**Valid Values**

- true : unassigned reviewers in the People tab are not added to the approval as new steps.
  - Append option: The existing, owner-assigned approvers without an assigned role do not change. New approver steps are not added even if the People tab has reviewers with the role "unassigned."
  - Replace option: The existing owner assigned approvers without a role are replaced with a blank. New approver steps would not be added even if the people tab has reviewers with the role "unassigned."
- false : unassigned reviewers are added to the approval.
  - Append option: All reviewers without a role are appended to the approval as reviewers if the approval has owner assigned steps without defined roles.
  - Replace Option: The existing approvers of approvals are replaced with the unassigned approvers in the People tab.

**enableApplicationLevelCaching**

**Description**

Indicates whether application-level caching is enabled or not. For best results, consider turning off application level caching when installing IBM Unica Marketing Operations in a clustered environment on which multicasting of caching messages is not enabled.

**Default value**

true

**Valid Values**

true | false

**customAccessLevelEnabled**

**Description**

Determines whether you use custom access levels (project roles) in IBM Unica Marketing Operations.

**Default value**

true

**Valid Values**

- true : user access to projects and requests is evaluated according to Object Access Levels and Custom Access Levels (project roles), and tab security is enabled for custom tabs.
- false : user access to projects and requests is evaluated only according to Object Access Levels (object implicit roles), and tab security is turned off for custom tabs.

**enableUniqueldsAcrossTemplatizableObjects****Description**

Determines whether you use unique internal id's across objects created from templates such as programs, projects, plans, and invoices.

**Default value**

true

**Valid Values**

- true enables unique internal id's across all objects created from templates. This way you can use the same table for two different object types to simplify cross object reporting.
- false disables unique internal id's across all objects created from templates.

**FMEnabled****Description**

Enables and disables the Financial Management Module, which determines whether the Accounts, Invoices, and Budget tabs appear in the product.

**Default value**

false

**Valid Values**

true | false

**FMProjVendorEnabled****Description**

Parameter used to show/hide vendor column for project line items.

**Default value**

false

**Valid Values**

true | false

**FMPrgmVendorEnabled****Description**

Parameter used to show/hide vendor column for program line items.

**Default value**

false

**Valid Values**

true | false

---

## Marketing Operations | umoConfiguration | templates

### **templatesDir**

**Description**

Set to the directory that you want to contain all your project template definitions, which are stored in XML files.

Use a fully-qualified path.

**Default value**

templates

### **assetTemplatesFile**

**Description**

The XML file that defines the templates for assets. This file must be located in the directory specified by the `templatesDir` property.

**Default value**

asset\_templates.xml

### **planTemplatesFile**

**Description**

The XML file that defines the templates for plans. This file must be located in the directory specified by the `templatesDir` property.

**Default value**

plan\_templates.xml

### **programTemplatesFile**

**Description**

The XML file that defines the templates for programs. This file must be located in the directory specified by the `templatesDir` property.

**Default value**

program\_templates.xml

### **projectTemplatesFile**

**Description**

The XML file that defines the templates for projects. This file must be located in the directory specified by the `templatesDir` property.

**Default value**

project\_templates.xml

### **invoiceTemplatesFile**

**Description**

The XML file that defines the templates for invoices. This file must be located in the directory specified by the `templatesDir` property.

**Default value**

`invoice_templates.xml`

**componentTemplatesFile**

**Description**

The XML file that defines the templates for marketing objects templates. This file must be located in the directory specified by the `templatesDir` property.

**Default value**

`component_templates.xml`

**metricsTemplateFile**

**Description**

The XML file that defines the templates for metrics. This file must be located in the directory specified by the `templatesDir` property.

**Default value**

`metric_definition.xml`

**teamTemplatesFile**

**Description**

The XML file that defines the templates for teams. This file must be located in the directory specified by the `templatesDir` property.

**Default value**

`team_templates.xml`

**offerTemplatesFile**

**Description**

The XML file that defines the templates for offers. This file must be located in the directory specified by the `templatesDir` property.

**Default value**

`uap_sys_default_offer_comp_type_templates.xml`

---

## Marketing Operations | `umoConfiguration` | `attachmentFolders`

**uploadDir**

**Description**

The upload directory where attachments for projects are stored.

**Default value**

`projectattachments`



## **planUploadDir**

### **Description**

The upload directory where attachments for plans are stored.

### **Default value**

planattachments

## **programUploadDir**

### **Description**

The upload directory where attachments for programs are stored.

### **Default value**

programattachments

## **componentUploadDir**

### **Description**

The upload directory where attachments for marketing objects are stored.

### **Default value**

componentattachments

## **taskUploadDir**

### **Description**

The upload directory where attachments for tasks are stored.

### **Default value**

taskattachments

## **approvalUploadDir**

### **Description**

The upload directory where approval items are stored.

### **Default value**

approvalitems

## **assetUploadDir**

### **Description**

The upload directory where assets are stored.

### **Default value**

assets

## **accountUploadDir**

### **Description**

The upload directory where attachments for accounts are stored.

### **Default value**

accountattachments

## **invoiceUploadDir**

### **Description**

The upload directory where attachments for invoices are stored.

### **Default value**

invoiceattachments

## **graphicalRefUploadDir**

### **Description**

The upload directory where attribute images are stored.

### **Default value**

graphicalrefimages

## **templateImageDir**

### **Description**

The upload directory where template images are stored.

### **Default value**

images

## **recentDataDir**

### **Description**

The temporary directory that stores the recent data (serialized) for each user.

### **Default value**

recentdata

## **workingAreaDir**

### **Description**

The temporary directory that stores CSV files that are uploaded during grid imports.

### **Default value**

umotemp

## **managedListDir**

### **Description**

The upload directory where managed list definitions are stored.

### **Default value**

managedList

---

## **Marketing Operations | umoConfiguration | email**

### **notifyEMailMonitorJavaMailHost**

#### **Description**

Optional string that specifies either the DNS host name of the email notifications mail server or its dot-formatted IP address; set to the machine name or IP address of your organization's SMTP server.

This parameter is necessary if you have not provided IBM Unica Marketing Operations with an existing JavaMail session that uses the session parameter above and the delegate is marked "Complete."

**Default value**

[CHANGE-ME]

**notifyDefaultSenderEmailAddress**

**Description**

Set to a valid email address. The system uses this address to send emails when there is no valid email address available to send the notification emails.

**Default value**

[CHANGE-ME]

**notifySenderAddressOverride**

**Description**

Use this parameter to specify a standard value for the REPLY-TO and FROM email addresses for notifications. By default, these addresses are populated with the email address of the event owner.

**Default value**

blank

---

## Marketing Operations | umoConfiguration | markup

IBM Unica Marketing Operations provides markup tools for making comments on attachments. You can use either Adobe Acrobat markup or native Marketing Operations markup. Use the properties in this category to configure which option to use.

**markupServerType**

**Description**

Determines which markup option to use.

**Default value**

MCM

**Valid Values**

- SOAP enables users to edit and view markups in PDF documents. Adobe Acrobat Standard or Professional are required for markups. If specified, users cannot view markups made in a web browser with the native Marketing Operations method.

If you specify SOAP, you must also configure the markupServerURL and useCustomMarkup parameters.

- MCM enables the native Marketing Operations markup method that allows users to edit and view markups in a web browser. If specified, users cannot edit or view markups that made previously in PDF using Adobe Acrobat.
- If blank, the markup function is disabled and the **View/Add Markup** link does not appear.

## markupServerURL

### Description

Dependent on markupServerType = SOAP.

Set to the URL for the computer hosting the markup server, including the number of the port where the web application server will be listening. The URL must contain the fully qualified host name.

### Default value

http://[SERVER]:[PORT]/plan/services/collabService?wsdl

## useCustomMarkup

### Description

Determines whether Windows users can send and receive markup comments using the **Acrobat Send Receive Comments** button.

### Default value

True

### Valid Values

- true : Windows users can use only the **Acrobat Send Receive Comments** button to send and receive markup comments. The sdkSOAPCollabSample.js file must be available in the javascripts folder of the client-side Acrobat installation.  
Dependent on markupServerType = SOAP.
- false : Windows users can use only the Marketing Operations custom **Send Comments** button to send and receive markup comments. They cannot use the Acrobat button and must configure Acrobat to enable the IBM Unica Marketing Operations **Comments** toolbar. For details, see description of PDF reviewing in the *IBM Unica Marketing Operations User's Guide*.

## instantMarkupFileConversion

### Description

If true, IBM Unica Marketing Operations converts PDF attachments to images as soon as they are uploaded, rather than doing this conversion the first time a user opens the item for markup.

### Default value

false

### Valid Values

true | false

---

## Marketing Operations | umoConfigurations | grid

### **gridmaxrow**

#### **Description**

An optional integer to define the maximum number of rows to be retrieved in grids. The default, -1, retrieves all rows.

#### **Default value**

-1

### **reloadRuleFile**

#### **Description**

An optional boolean parameter indicating whether the grid validation plug-in needs to be reloaded or not.

#### **Default value**

true

#### **Valid Values**

true | false

### **gridDataValidationClass**

#### **Description**

An optional parameter to specify custom grid data validation class. If not specified, the default, built in plug-in is used for grid data validation.

#### **Default value**

blank

### **tvcdatalmportFieldDelimiterCSV**

#### **Description**

Delimiter to be used to parse data while importing in a grid. Default is comma (,).

#### **Default value**

, (comma)

### **maximumFileSizeToImportCSVFile**

#### **Description**

Represents the maximum file size in MB that can be uploaded while importing comma-separated data for TVC.

#### **Default value**

0 (unlimited)

### **maximumRowsToBeDisplayedPerPageInGridView**

#### **Description**

Integer parameter specifying number of rows to be displayed per page in grid view.

**Default value**

100

**Valid Values**

positive integers

**griddatxsd****Description**

Name of Grid Data XSD file.

**Default value**

griddataschema.xsd

**gridpluginxsd****Description**

Name of Grid plug-ins XSD file.

**Default value**

gridplugin.xsd

**gridrulesxsd****Description**

Name of Grid Rules XSD file.

**Default value**

gridrules.xsd

---

**Marketing Operations | umoConfiguration | workflow****hideDetailedDateTime****Description**

Optional show/hide parameter for detailed date time in the tasks page.

**Default value**

false

**Valid Values**

true | false

**daysInPastRecentTask****Description**

This parameter determines for how long tasks should be considered "recent." If the task is "active," and started less than X days ago or the task's Target End Date is between today and X days in the past, the task displays as a recent task.

**Default value**

14

**Valid Values**

positive integers

### **daysInFutureUpcomingTasks**

#### **Description**

This parameter determines how many days in the future to look for upcoming tasks. If the task starts in the next daysInFutureUpcomingTasks or does not end before the current date, it is an upcoming task.

#### **Default value**

14

#### **Valid Values**

positive integers

### **beginningOfDay**

#### **Description**

Begin hour of the working day. This parameter is used to calculate the datetimes in workflow using fractional durations.

#### **Default value**

9 (9 AM)

#### **Valid Values**

integers 0 to 12

### **numberOfHoursPerDay**

#### **Description**

Number of hours per day. This parameter is used to calculate the datetimes in workflow using fractional durations.

#### **Default value**

8

#### **Valid Values**

integers 1 to 24

### **mileStoneRowBGColor**

#### **Description**

Defines the background color for workflow tasks. To specify the value, insert the # character before the six-character Hex code for the color. For example, #0099CC.

#### **Default value**

#DDDDDD

---

## **Marketing Operations | umoConfiguration | integrationServices**

### **enableIntegrationServices**

#### **Description**

Enables and disables the Integration Services module that can be used by third party users to access IBM Unica Marketing Operations functionality using web services and triggers.

**Default value**

false

**Valid Values**

true | false

### **integrationProcedureDefinitionPath**

**Description**

Optional full file path to the custom procedure definition XML file.

**Default value**

[PLAN\_HOME]/devkits/integration/examples/src/procedure/procedure-plugins.xml

### **integrationProcedureClasspathURL**

**Description**

URL to the classpath for custom procedures.

**Default value**

file://[PLAN\_HOME]/devkits/integration/examples/classes/

---

## **Marketing Operations | umoConfiguration | campaignIntegration**

### **defaultCampaignPartition**

**Description**

When IBM Unica Marketing Operations is integrated with IBM Unica Campaign, this parameter specifies the default Campaign partition if the campaign-partition-id is not defined in the project template.

**Default value**

partition1

### **webServiceTimeoutInMilliseconds**

**Description**

Added for Web Service integration API calls. This parameter is used as a timeout for web services API calls.

**Default value**

1800000 milliseconds (30 minutes)

---

## **Marketing Operations | umoConfiguration | reports**

### **reportsAnalysisSectionHome**

**Description**

Indicates the home directory for the Analysis Section reports.

**Default value**



/content/folder[@name='Affinium Plan']

### **reportsAnalysisTabHome**

#### **Description**

Indicates the home directory for the Analysis Tab reports.

#### **Default value**

/content/folder[@name='Affinium Plan - Object Specific Reports']

### **cacheListOfReports**

#### **Description**

This parameter enables/disables caching of list of reports on object instance's analysis page.

#### **Default value**

false

#### **Valid Values**

true | false

---

## **Marketing Operations | umoConfiguration | invoiceRollup**

### **invoiceRollupMode**

#### **Description**

Specifies how rollups occur. Acceptable values are the following.

#### **Default value**

immediate

#### **Valid Values**

- immediate: rollups occur every time an invoice is marked PAID
- schedule: rollups occur on a scheduled basis

If this parameter is set to schedule, the system uses the following parameters to determine when rollups occur.

- invoiceRollupScheduledStartTime
- invoiceRollupScheduledPollPeriod

### **invoiceRollupScheduledStartTime**

#### **Description**

If invoiceRollupMode is schedule, this parameter specifies the poll period in seconds for rollup to occur.

If invoiceRollupMode is immediate, this parameter is not used.

#### **Default value**

3600 (1 hour)

### **invoiceRollupScheduledPollPeriod**

#### **Description**

If invoiceRollupMode is schedule, this parameter is used as follows.

- If this parameter contains a value (for example, 11:00 pm), that value is the start time for the schedule to start.
- If this parameter is undefined, the rollup schedule starts when the server starts.

If `invoiceRollupMode` is `immediate`, this parameter is not used.

**Default value**

---

## Marketing Operations | umoConfiguration | database

### **fileName**

#### **Description**

Path to file for loading datasources using JNDI lookup.

#### **Default value**

`plan_datasources.xml`

### **sqlServerSchemaName**

#### **Description**

Specifies the database schema to use. This parameter only applies if you are using SQL Server for your IBM Unica Marketing Operations database.

#### **Default value**

`dbo`

### **thresholdForUseOfSubSelects**

#### **Description**

Specifies the number of records beyond which a subquery should be used in the IN clause of SQL (for listing pages) instead of the actual entity IDs in the IN clause. Setting this parameter improves performance for IBM Unica Marketing Operations installations that have a lot of application data. As a best practice, do not change this value unless you encounter performance issues. If the parameter is missing or commented out, the database behaves as if the threshold was set to a very large value.

#### **Default value**

`3000`

### **commonDataAccessLayerFetchSize**

#### **Description**

This parameter specifies resultset fetch size for certain performance sensitive, critical queries.

#### **Default value**

`0`

### **commonDataAccessLayerMaxResultSetSize**

#### **Description**

This parameter specifies maximum resultset size for certain performance sensitive, critical queries.

**Default value**

-1

**useDBSortForAllList****Description**

This parameter is used when configuring ALL IBM Unica Marketing Operations List Handlers. Use USE\_DB\_SORT\_FOR\_[MODULE]\_LIST to override particular list's paging behavior.

**Default value**

true

**Valid Values**

- true : get one page of list data from database at a time.
- false : cache all list data.

**useDBSortForPlanList****Description**

This parameter is used to configure the Plan List Handler.

**Default value**

true

**Valid Values**

- true : get one page of list data from database at a time.
- false : cache all list data.

**useDBSortForProjectList****Description**

This parameter is used to configure the Project List Handler.

**Default value**

true

**Valid Values**

- true : get one page of list data from database at a time.
- false : cache all list data.

**useDBSortForTaskList****Description**

This parameter is used to configure the Task List Handler.

**Default value**

true

**Valid Values**

- true : get one page of list data from database at a time.
- false : cache all list data.

## **useDBSortForProgramList**

### **Description**

This parameter is used to configure the Program List Handler.

### **Default value**

true

### **Valid Values**

- true : get one page of list data from database at a time.
- false : cache all list data.

## **useDBSortForApprovalList**

### **Description**

This parameter is used to configure the Approval List Handler.

### **Default value**

true

### **Valid Values**

- true : get one page of list data from database at a time.
- false : cache all list data.

## **useDBSortForInvoiceList**

### **Description**

This parameter is used to configure the Invoice List Handler.

### **Default value**

true

### **Valid Values**

- true : get one page of list data from database at a time.
- false : cache all list data.

## **useDBSortForAlerts**

### **Description**

This parameter is used to configure the Alerts List Handler.

### **Default value**

true

### **Valid Values**

- true : get one page of list data from database at a time.
- false : cache all list data.

---

## **Marketing Operations | umoConfiguration | listingPages**

### **listItemsPerPage**

#### **Description**

Specifies how many items (rows) are displayed in one list page. This value should be greater than 0.

**Default value**

10

**listPageGroupSize****Description**

Specifies the size of visible page numbers in the list navigator in the list page. For example, pages 1-5 is a page group. This value should be greater than 0.

**Default value**

5

**maximumItemsToBeDisplayedInCalendar****Description**

The maximum number of objects (plans, programs, projects, or tasks) the system displays on calendars. Use this parameter to restrict a user's view of calendars to a specific number of objects. The number 0 indicates that there is no restriction.

**Default value**

0

**listDisplayShowAll****Description**

Display "Show All" link on listing pages.

**Default value**

false

**Valid Values**

true | false

---

**Marketing Operations | umoConfiguration | objectCodeLocking****enablePersistentObjectLock****Description**

enablePersistentObjectLock must be set to true if IBM Unica Marketing Operations is deployed in a clustered environment. The object lock information will be persistent in database.

**Default value**

false

**Valid Values**

true | false

**lockProjectCode****Description**

Determines whether users can edit the Project Code or PID on the **Project Summary Edit** tab.

**Default value**

true

**Valid Values**

- true: enables locking
- false: disables locking

**lockProgramCode****Description**

Determines whether users can edit the Program Code or PID on the **Program Summary Edit** tab.

**Default value**

true

**Valid Values**

- true: enables locking
- false: disables locking

**lockPlanCode****Description**

Determines whether users can edit the Plan Code or PID on the **Plan Summary Edit** tab.

**Default value**

true

**Valid Values**

- true: enables locking
- false: disables locking

**lockMarketingObjectCode****Description**

Determines whether users can edit the Marketing Object Code or PID on the **Marketing Object Summary Edit** tab.

**Default value**

true

**Valid Values**

- true: enables locking
- false: disables locking

**lockAssetCode****Description**

Determines whether users can edit the Asset Code or PID on the **Asset Summary Edit** tab.

**Default value**

true

**Valid Values**

- true: enables locking
- false: disables locking

---

## Marketing Operations | umoConfiguration | thumbnailGeneration

### **trueTypeFontDir**

#### **Description**

Specifies the directory where the True Type fonts are located. This parameter is required for thumbnail generation on non-Windows platforms using Aspose. For Windows installations, this parameter is optional.

#### **Default value**

blank

### **coreThreadPoolSize**

#### **Description**

Specifies the number of persistent threads kept in the thread pool for thumbnail generator threads.

#### **Default value**

5

### **maxThreadPoolSize**

#### **Description**

Specifies the maximum number of threads allowed in the thread pool for thumbnail generator threads.

#### **Default value**

10

### **threadKeepAliveTime**

#### **Description**

Parameter to configure the keep-alive time for thumbnail generator threads.

#### **Default value**

60

### **threadQueueSize**

#### **Description**

Parameter to configure the thread queue size for thumbnail generator threads.

#### **Default value**

20

---

## Marketing Operations | umoConfiguration | notifications

### **notifyPlanBaseURL**

#### **Description**

The URL for your IBM Unica Marketing Operations deployment, including the host name and port number. Marketing Operations includes this URL in notifications that contain links to other information in Marketing Operations .

**Note:** Do not use "localhost" as a server name unless your mail client and IBM Unica Marketing Operations server are running on same machine.

**Default value**

`http://[SERVER]:[PORT]/plan/affiniumpplan.jsp`

**notifyDelegateClassName**

**Description**

The fully-qualified Java class name of the delegate implementation to be instantiated by the service. This class must implement the `com.unicapcorp.afc.service.IServiceImpl` interface. Will default to a local implementation if not specified.

**Default value**

blank

**notifyIsDelegateComplete**

**Description**

Optional boolean string indicating if the delegate implementation is complete. Defaults to "true" if not specified.

**Default value**

true

**Valid Values**

true | false

**notifyEventMonitorStartTime**

**Description**

Specifies when the Notify Monitor should begin processing for the first time after the IBM Unica Marketing Operations product is started. Format the value according to the short version of the `java.text.DateFormat` class for the current locale. For example, in US English locale, a valid string might be 11:45 PM.

**Default value**

Immediately after Marketing Operations is started.

**notifyEventMonitorPollPeriod**

**Description**

Defines the approximate time, in seconds, for the event monitor to sleep between polls. Events will be accumulated in the event queue between polling periods; shorter times will process notifications sooner, but may impose more system overhead. If you erase the default and leave the value blank, the poll period defaults to some short period of time, usually under a minute.



**Default value**

5

**notifyEventMonitorRemoveSize****Description**

Specifies the number of events to remove from queue in one shot. The event monitor will continue removing events from the event queue in increments specified by this value until none are left.

**Note:** Setting this value to something other than 1 may increase event processing performance, but risks losing events if the service host goes down before all the removed events can be processed.

**Default value**

10

**alertCountRefreshPeriodInSeconds****Description**

Specifies, in seconds, the system-wide alert count refresh period for the alerts count. This count appears near the top of the navigation bar after a user logs in.

**Note:** Changing the refresh period to poll faster may have performance implications in a multi-user environment.

**Default value**

180 (3 minutes)

---

**Marketing Operations | umoConfiguration | notifications | email****notifyEMailMonitorStartTime****Description**

Specifies when the Email Monitor should begin processing for the first time after the IBM Unica Marketing Operations product is started. Format the value according to the short version of the `java.text.DateFormat` class for the current locale. For example, in US English locale, a valid string might be 11:59 PM.

**Default value**

Immediately after IBM Unica Marketing Operations is started.

**notifyEMailMonitorPollPeriod****Description**

Defines the approximate time, in seconds, for the email monitor to sleep between polls.

**Note:** As with events, emails will accumulate in the queue between polling periods; shorter polling times will send emails sooner, but may increase system overhead.

**Default value**

**notifyEMailMonitorJavaMailSession****Description**

JNDI name of an existing, initialized JavaMail Session to use for email notifications. If not specified and the delegate is marked Complete, then the JavaMail host parameter must be supplied so IBM Unica Marketing Operations can create a session.

**Default value**

blank

**notifyEMailMonitorJavaMailProtocol****Description**

Specifies the mail server transport protocol to use for email notifications.

**Default value**

smtp

**notifyEMailMonitorRemoveSize****Description**

Specifies the number of emails to remove from queue at one time. The email monitor will continue incrementally removing emails from the email queue until none remain.

**Note:** Setting a value other than 1 may increase email processing performance, but you risk losing emails if the service host goes down before all the removed emails are processed.

**Default value**

10

**notifyEMailMonitorMaximumResends****Description**

Specifies the maximum number of times the system attempts to send an email message that failed in the first attempt to send it. When a send fails, the email is put back on the queue unless it has already reached the maximum attempts allowed by this parameter.

For example, if the email monitor is set to poll every 60 seconds, then setting maximumResend to 60 will cause the email monitor to retry every minute, once in each poll, for up to an hour. A value of 1440 (24x60) will cause retry every minute for up to 24 hours.

**Default value**

1440

**showUserNameInEmailNotificationTitle****Description**

Specifies whether the IBM Unica Marketing Operations notification and alert systems includes the user name in the **From** field of email notifications.

**Note:** This setting is applicable only to emails sent by the notification and alert systems in IBM Unica Marketing Operations.

**Default value**

false

**Valid Values**

- true : Marketing Operations appends the user name to the title of the message and displays both in the **From** field of the email
- false : Marketing Operations displays only the message title in the **From** field

### **notifyEMailMonitorJavaMailDebug**

**Description**

Specifies if JavaMail debug mode should be set.

**Default value**

false

**Valid Values**

- true : enables JavaMail debug.
- false : disables debug tracing.

---

## **Marketing Operations | umoConfiguration | notifications | project**

### **notifyProjectAlarmMonitorStartTime**

**Description**

Specifies when the project alarm monitors should begin processing for the first time after the IBM Unica Marketing Operations product is started. Format the value according to the short version of the `java.text.DateFormat` class for the current locale. For example, in US English locale, a valid string might be 11:59 PM. If you erase the default and leave the value blank, this monitor starts immediately after you create it.

**Default value**

10:00 PM

### **notifyProjectAlarmMonitorPollPeriod**

**Description**

Defines the approximate time, in seconds, for the project and program alarm monitors to sleep between polls.

**Default value**

60

### **notifyProjectAlarmMonitorScheduledStartCondition**

**Description**

Defines the number of days before a project's start date that IBM Unica Marketing Operations should start sending start notifications to users.

**Note:** If this value is -1, then Marketing Operations does not send these notifications.

**Default value**

1

**notifyProjectAlarmMonitorScheduledEndCondition**

**Description**

Defines the number of days before a project's end date when IBM Unica Marketing Operations should start sending end notifications to users.

**Note:** If this value is -1, then Marketing Operations does not send these notifications.

**Default value**

3

**notifyProjectAlarmMonitorTaskScheduledStartCondition**

**Description**

Defines the number of days before a task's start date that IBM Unica Marketing Operations should start sending start notifications to users.

**Note:** If this value is -1, then Marketing Operations does not send these notifications.

**Default value**

1

**notifyProjectAlarmMonitorTaskScheduledEndCondition**

**Description**

Defines the number of days before a task's end date when IBM Unica Marketing Operations should start sending end notifications to users.

**Note:** If this value is -1, then Marketing Operations does not send these notifications.

**Default value**

3

**notifyProjectAlarmMonitorTaskLateCondition**

**Description**

Defines the number of days after a task's start date when IBM Unica Marketing Operations should begin notifying users that a task did not start.

**Note:** If this value is -1, then Marketing Operations does not send these notifications.

**Default value**

3

### **notifyProjectAlarmMonitorTaskOverdueCondition**

#### **Description**

Defines the number of days after a task's end date when IBM Unica Marketing Operations should begin notifying users that a task did not finish.

**Note:** If this value is -1, then Marketing Operations does not send these notifications.

#### **Default value**

3

### **notifyProjectAlarmMonitorTaskScheduledMilestoneCondition**

#### **Description**

Defines the number of days after a task milestone's start date when IBM Unica Marketing Operations should start sending notifications.

**Note:** If this value is -1, then Marketing Operations does not send these notifications.

#### **Default value**

1

---

## **Marketing Operations | umoConfiguration | notifications | projectRequest**

### **notifyRequestAlarmMonitorLateCondition**

#### **Description**

Defines the number of days before IBM Unica Marketing Operations should send a notification that the request is late.

**Note:** If this value is -1, then Marketing Operations does not send these notifications.

#### **Default value**

3

### **notifyRequestAlarmMonitorScheduledEndCondition**

#### **Description**

Defines the number of days before a request's end date when IBM Unica Marketing Operations should start sending end notifications to users.

**Note:** If this value is -1, then Marketing Operations does not send these notifications.

#### **Default value**

1

---

## Marketing Operations | umoConfiguration | notifications | program

### notifyProgramAlarmMonitorScheduledStartCondition

#### Description

Defines the number of days before a program's start date when IBM Unica Marketing Operations should start sending notifications to users.

**Note:** If this value is -1, then Marketing Operations does not send these notifications.

#### Default value

1

### notifyProgramAlarmMonitorScheduledEndCondition

#### Description

Defines the number of days before a program's end date when IBM Unica Marketing Operations should start sending end notifications to users.

**Note:** If this value is -1, then Marketing Operations does not send these notifications.

#### Default value

3

---

## Marketing Operations | umoConfiguration | notifications | marketingObject

### notifyComponentAlarmMonitorScheduledStartCondition

#### Description

Specifies the number of days before a marketing object's start date when IBM Unica Marketing Operations should start sending notifications to users.

**Note:** If this value is -1, then Marketing Operations does not send these notifications.

#### Default value

1

### notifyComponentAlarmMonitorScheduledEndCondition

#### Description

Specifies the number of days before a marketing object's end date when IBM Unica Marketing Operations should start sending end notifications to users.

**Note:** If this value is -1, then Marketing Operations does not send these notifications.

#### Default value

3

---

## Marketing Operations | umoConfiguration | notifications | approval

### notifyApprovalAlarmMonitorStartTime

#### Description

Specifies when the approval alarm monitor should begin processing for the first time after the IBM Unica Marketing Operations product is started. Format the value according to the short version of the `java.text.DateFormat` class for the current locale. For example, in US English locale, a valid string might be 11:59 PM. If you delete the default and leave this value blank, the monitor starts immediately after it is created.

**Note:** For best results, configure the alarm monitors to start during off-peak hours and stagger their start times to spread out the data processing load.

#### Default value

9:00 PM

### notifyApprovalAlarmMonitorPollPeriod

#### Description

Specifies the approximate time, in seconds, for the approval alarm monitor to sleep between polls.

#### Default value

60

### notifyApprovalAlarmMonitorLateCondition

#### Description

Specifies the number of days after an approval's start date when IBM Unica Marketing Operations should begin notifying users that the approval is late.

**Note:** If this value is -1, then Marketing Operations does not send these notifications.

#### Default value

3

### notifyApprovalAlarmMonitorScheduledEndCondition

#### Description

Specifies the number of days before an approval's end date when IBM Unica Marketing Operations should begin sending end notifications to users.

**Note:** If this value is -1, then Marketing Operations does not send these notifications.

#### Default value

3

---

## Marketing Operations | umoConfiguration | notifications | asset

### notifyAssetAlarmMonitorStartTime

#### Description

Specifies when the Asset Alarm Monitor should begin processing for the first time after the IBM Unica Marketing Operations product is started. Format the value according to the short version of the `java.text.DateFormat` class for the current locale. For example, in US English locale, a valid string might be 11:59 PM. If you delete the default and leave this value blank, the monitor starts immediately after it is created.

**Note:** For best results, configure the alarm monitors to start during off-peak hours and stagger their start times to spread out the data processing load.

#### Default value

11:00 PM

### notifyAssetAlarmMonitorPollPeriod

#### Description

Specifies the time, in seconds, for the asset alarm monitor to sleep between polls.

#### Default value

60

### notifyAssetAlarmMonitorExpirationCondition

#### Description

Specifies the number of days before an asset is going to expire when IBM Unica Marketing Operations should notify users that the asset is about to expire.

**Note:** If this value is -1, Marketing Operations does not check for expiration.

#### Default value

3

---

## Marketing Operations | umoConfiguration | notifications | invoice

### notifyInvoiceAlarmMonitorStartTime

#### Description

Specifies when the invoice alarm monitor should begin processing for the first time after the IBM Unica Marketing Operations product is started. Format the value according to the short version of the `java.text.DateFormat` class for the current locale. For example, in US English locale, a valid string might be 11:59 PM. If you delete the default and leave the value blank, the monitor starts immediately after you create it.



**Note:** For best results, configure the alarm monitors to start during off-peak hours and to stagger their start times to spread out the data processing load.

**Default value**

9:00 PM

**notifyInvoiceAlarmMonitorDueCondition**

**Description**

Specifies the number of days when IBM Unica Marketing Operations should start notifying users that an invoice is becoming due.

**Note:** If this value is -1, then Marketing Operations does not send these notifications.

**Default value**

5



---

## Notices

This information was developed for products and services offered in the U.S.A.

IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information about the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not grant you any license to these patents. You can send license inquiries, in writing, to:

IBM Director of Licensing  
IBM Corporation  
North Castle Drive  
Armonk, NY 10504-1785  
U.S.A.

For license inquiries regarding double-byte (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

Intellectual Property Licensing  
Legal and Intellectual Property Law  
IBM Japan Ltd.  
1623-14, Shimotsuruma, Yamato-shi  
Kanagawa 242-8502 Japan

The following paragraph does not apply to the United Kingdom or any other country where such provisions are inconsistent with local law: INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some states do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

Any references in this information to non-IBM websites are provided for convenience only and do not in any manner serve as an endorsement of those websites. The materials at those websites are not part of the materials for this IBM product and use of those websites is at your own risk.

IBM may use or distribute any of the information you supply in any way it believes appropriate without incurring any obligation to you.

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

IBM Corporation  
170 Tracer Lane  
Waltham, MA 02451  
U.S.A.

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this document and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Program License Agreement or any equivalent agreement between us.

Any performance data contained herein was determined in a controlled environment. Therefore, the results obtained in other operating environments may vary significantly. Some measurements may have been made on development-level systems and there is no guarantee that these measurements will be the same on generally available systems. Furthermore, some measurements may have been estimated through extrapolation. Actual results may vary. Users of this document should verify the applicable data for their specific environment.

Information concerning non-IBM products was obtained from the suppliers of those products, their published announcements or other publicly available sources. IBM has not tested those products and cannot confirm the accuracy of performance, compatibility or any other claims related to non-IBM products. Questions on the capabilities of non-IBM products should be addressed to the suppliers of those products.

All statements regarding IBM's future direction or intent are subject to change or withdrawal without notice, and represent goals and objectives only.

All IBM prices shown are IBM's suggested retail prices, are current and are subject to change without notice. Dealer prices may vary.

This information contains examples of data and reports used in daily business operations. To illustrate them as completely as possible, the examples include the names of individuals, companies, brands, and products. All of these names are fictitious and any similarity to the names and addresses used by an actual business enterprise is entirely coincidental.

#### COPYRIGHT LICENSE:

This information contains sample application programs in source language, which illustrate programming techniques on various operating platforms. You may copy, modify, and distribute these sample programs in any form without payment to IBM, for the purposes of developing, using, marketing or distributing application programs conforming to the application programming interface for the operating platform for which the sample programs are written. These examples have not

been thoroughly tested under all conditions. IBM, therefore, cannot guarantee or imply reliability, serviceability, or function of these programs. The sample programs are provided "AS IS", without warranty of any kind. IBM shall not be liable for any damages arising out of your use of the sample programs.

If you are viewing this information softcopy, the photographs and color illustrations may not appear.

---

## Trademarks

IBM, the IBM logo, and [ibm.com](http://ibm.com) are trademarks or registered trademarks of International Business Machines Corp., registered in many jurisdictions worldwide. Other product and service names might be trademarks of IBM or other companies. A current list of IBM trademarks is available on the Web at "Copyright and trademark information" at [www.ibm.com/legal/copytrade.shtml](http://www.ibm.com/legal/copytrade.shtml).







Printed in USA