

Cloud Native Unica V12.1.9 Installation and Configuration Guide



Contents

Chapter 1. Pre-installation configurations.....	3
Avoiding timeout issues.....	3
Application server setup.....	4
Configuring application servers for Cloud Native Unica.....	5
Database setup.....	6
Listener Database client setup.....	9
Setting up the Cloud Native environment.....	10
Cloud Native Unica setup on SSL.....	12
Chapter 2. Installation and verifying the installation.....	13
Installation.....	13
Verifying the chart.....	13
Log files.....	13
Campaign Log Files.....	14
Chapter 3. Post installation configurations.....	15
Configurations for Campaign.....	15
Configuring multi-partitions for Campaign.....	15
Configurations for Director.....	16
Configurations for Interact.....	16
Configurations for Platform.....	17
Chapter 4. Migration of on-premises applications to Cloud Native Unica.....	20
Migration prerequisites.....	20
common-configMap configurations.....	20
JVM option configurations.....	21
Performing the migration.....	21
Configuring Unica Campaign post migration.....	22
Configuring Unica Interact post migration.....	22
Configuring Unica Platform post migration.....	22
Chapter 5. Cloud Native Unica upgrade.....	23
Custom listener scripts and Cloud Native Unica container OS upgrade.....	23
Chapter 6. Installing Apache Superset with Unica as a Sub-chart.....	24
Configurations to Customize Superset.....	24
Chapter 7. Installing Standalone Superset.....	29
Configuring Superset for Unica.....	29
Chapter 8. Scaling Unica containers.....	34
Scaling Listener containers.....	34
Load balancing.....	35
Listener integration.....	35
Scaling Interact containers.....	36
Scaling Journey engine containers.....	42
Chapter 9. Using Red Hat OpenShift.....	43
Security Context Constraints for Unica on Red Hat OpenShift.....	43
Chapter 10. Deployment monitoring.....	46
Deploying the dashboard user interface.....	46
Chapter 11. Product utilities.....	47
Chapter 12. Using secret to avoid passwords in plain text.....	48
Chapter 13. Using AWS Secrets and Configuration Provider with Kubernetes Secret Store CSI Driver.....	49
AWS Secret Manager Implementation.....	49
Prerequisite Software for AWS Secret Manager.....	50
Prerequisite Configurations for AWS Secret Manager.....	50
Implementing AWS Secret Manager.....	51
Chapter 14. Enabling Multicast using Weave-Net CNI plugin on AWS EKS cluster.....	55
Chapter 15. Uninstalling the chart.....	56

Chapter 1. Pre-installation configurations

Before installing or upgrading to Cloud Native Unica, you should complete some configurations.

The list of pre-installation or pre-upgrade configurations are as follows:

- Configure the resources for containers. For more information, see *Cloud Native Unica Getting Started Guide*.
- Ensure that you have installed Docker Enterprise version 19.xx.x. For more information, see [Docker documentation](#).
- Ensure that you have installed Kubernetes. For more information, see [Kubernetes documentation](#).
- Verify if:
 - you have configured a Kubernetes cluster.
 - the Kubernetes environment has the appropriate image enforcement policy to allow access to the required repositories.
 - the application server is setup. For more information, see one of the following topics based on the application server that is installed on your system:
 - [Setup for Apache Tomcat on page 4](#)
 - [Setup for Red Hat JBoss Enterprise Application Platform on page 4](#)
 - [Configuring JBoss for Cloud Native Unica on page 5](#)
 - [Setup for Oracle WebLogic on page 4](#)
 - [Configuring WebLogic for Cloud Native Unica on page 5](#)
 - the database is setup. For more information, see one of the following topics based on the application server that is installed on your system:
 - [For Apache Tomcat on page 6](#)
 - [For Red Hat JBoss Enterprise Application Platform on page 7](#)
 - [For Oracle WebLogic on page 8](#)
- Ensure that you have installed Helm. For more information, see [Helm documentation](#).

Avoiding timeout issues

To avoid timeout issues, perform the following steps.

1. Access the path `<chart-location>/unica/`.
2. Open the file `values-local.yaml`.
3. Add the following lines of code in the annotations section within ingress.

```
nginx.ingress.kubernetes.io/proxy-connect-timeout: "30"  
nginx.ingress.kubernetes.io/proxy-read-timeout: "1800"  
nginx.ingress.kubernetes.io/proxy-send-timeout: "1800"  
nginx.ingress.kubernetes.io/proxy-body-size: 50m  
ingress.kubernetes.io/proxy-body-size: 50m
```

4. Save the changes.

Application server setup

Cloud Native Unica supports Apache Tomcat®, Red Hat® JBoss® Enterprise Application Platform (EAP), and Oracle® WebLogic Server application servers.

Setup for Apache Tomcat

You do not have to set up the Apache Tomcat application server as it is embedded in the Cloud Native Unica image.

1. Edit the `setenv.sh` file for the respective product instances script in the `bin` directory under your Tomcat instances directory to add the following Java options:

```
-Dfile.encoding=UTF-8
-Dclient.encoding.override=UTF-8
```

2. If you are deploying on a non-production setup, add:

```
-DENABLE_NON_PROD_MODE=true
```

3. If you are deploying on a production setup, remove the Java option `-DENABLE_NON_PROD_MODE=true`, or set it to `false`.
4. After saving the changes, restart the Apache Tomcat server.

Setup for Red Hat JBoss Enterprise Application Platform

To setup the JBoss application server, place the JBoss EAP ZIP file on the mount location and configure the path in the Helm chart.

1. For JBoss server, edit the `standalone.conf` script in the `JBoss/bin` directory to add the following Java options to

`JAVA_VENDOR:`

```
-Dfile.encoding=UTF-8
-Dclient.encoding.override=UTF-8
-Djboss.as.management.blocking.timeout=3600
```

2. If you are deploying on a non-production setup, add:

```
-DENABLE_NON_PROD_MODE=true
```

3. If you are deploying on a production setup, remove the Java option `-DENABLE_NON_PROD_MODE=true`, or set it to `false`.
4. After saving the changes, restart the JBoss server.

Setup for Oracle WebLogic

Install Oracle WebLogic Server on the shared filesystem.

1. For WebLogic server, edit the `setDomainEnv` script in the `bin` directory, within the WebLogic domain directory, to add the following Java options to `JAVA_VENDOR:`
2. If you are deploying on a non-production setup, add:
3. If you are deploying on a production setup, remove the Java option `-DENABLE_NON_PROD_MODE=true`, or set it to `false`.
4. After saving the changes, restart the WebLogic server.

Configuring application servers for Cloud Native Unica

You must perform additional configurations on JBoss and WebLogic.

Configuring JBoss for Cloud Native Unica

To use JBoss with Cloud Native Unica, complete the following steps:

1. Open the file `common-configMap.yaml`. To locate the file, access the `JBOSSEracle/unica/templates/` location.
2. For the `_JBOSS_ZIP_LOCATION` parameter, provide the folder name, residing within the `HOME` folder, containing the JBoss installation `ZIP` file. For example, `/docker/unica/JBossZip/JBOSS.Zip`.
3. For the `_JBOSS_ZIP_NAME_` parameter, provide the name of the JBoss installer `ZIP` file. For example, `jboss-eap-7.1.0.zip`.
4. For the `_DEST_JBOSS_UNZIP_LOCATION_` parameter, provide the absolute directory location where you want to install JBoss. For example, if you want to install JBoss inside the container, provide the value `/opt`. If you want to install JBoss in a mapped shared folder, provide the value `/docker/unica`.
5. For the `_DEST_UNZIP_FOLDER_` parameter, provide a folder name that contains the unzipped contents of the JBoss installer `ZIP` file. For example, if the `ZIP` file is `jboss-eap-7.1.0.zip` and the folder within the `ZIP` file is `JBoss710`, provide the value `JBoss710`.

Results

Completing the earlier mentioned configuration will automatically install JBoss and the required Unica component.

Configuring WebLogic for Cloud Native Unica

Your system should have WebLogic installed to use it with Cloud Native Unica. Cloud Native Unica uses the utilities from WebLogic to create a domain for the required Unica component.

About this task

To use WebLogic with Cloud Native Unica, complete the following steps:

1. For the `JAVA_HOME_WEBLOGIC` parameter, WebLogic requires Oracle JDK. The value of this setting is the `HOME` location of the JDK used for the existing WebLogic installation. For example, `/docker/unica/jdk18_oracle`.
2. For the `WLS_HOME_DIR` parameter, provide the home directory of the WebLogic server installation. For example, `/docker/unica/oracle_products/middleware/wlse`.

3. For the **WLS_DOMAIN_LOCATION** parameter, provide the fully qualified path of the directory under which the domains for the products will be created. For example, `/docker/unica/wlsdomains`.



CAUTION: The creation of a new pod creates a directory for the domain of that Pod. If you discard a pod, the directory is not deleted automatically. You should delete such directories as they consume a lot of disk space.

Database setup

You need to set up the database before you begin installation.

You can setup the database in one of the following ways.

- Use your database Docker image
- Connect to an external database system

In case of Managed Kubernetes Clusters on Cloud, the system data and the customer data must reside on Cloud.

If your database resides in an external system, the configuration of the following parameters, in Unica Helm chart, is mandatory.

- Database Users
- Tablespace Users
- Operating System Users

The database can reside within Kubernetes cluster. If the database resides within the Kubernetes cluster, use any available database image, and edit the Unica Helm chart. Ensure that user creation is complete before the Cloud Native solution starts.

For Apache Tomcat

To use Tomcat, within the cluster or with an external database, complete the following steps:

1. Download Cloud Native Unica images and Helm Chart.
2. Create `Databases` and `Users` and enter those details in the Unica Helm Chart.

If you set the Database as a sub-chart in Unica chart, you can completely automate data import using Shell scripts. For import, data should be available on the Database container mount point. You can also place the data after the container starts. Ensure that Database configuration and user creation activity is completed before running the Unica chart.

For auto-installation of database client on listener pod or container, complete the following steps:



Note: The commands and filenames are mentioned specific to Oracle database. Provide appropriate values based on the the database you use.

1. Place the Oracle client installer, named `linuxamd64_12102_client.zip`, inside the `/tmp` folder.
2. To extract the installer file, run the `unzip` command.

A new folder, named `client` is created in the location `/tmp`.

3. Run the following command:

```
cp /tmp/client/response/client_install.rsp /tmp/oracle_client.rsp
```

4. Access the `oracle_client.rsp` file and make the following changes in the file:

```
UNIX_GROUP_NAME=oinstall
INVENTORY_LOCATION=/home/oracle/oraInventory
ORACLE_HOME=/home/oracle/app/oracle/product/12.1.0/client_1
ORACLE_BASE=/home/oracle/app/oracle
oracle.install.client.installType=Administrator
```

5. Run the following commands:

```
cd /tmp
mkdir linuxamd64_12102_client
mv client linuxamd64_12102_client
tar -cvf Oracle_client.tar linuxamd64_12102_client oracle_client.rsp
gzip Oracle_client.tar
mv Oracle_client.tar.gz oracle_client.rsp /docker/unica
```

6. In the `/docker/unica/` location, create a file named `oracle.sh` and add the following content in the file:

```
yum install -y libaio
/tmp/Oracle_client_install/linuxamd64_12102_client/client/runInstaller
-silent -ignoreSysPrereqs -responseFile /tmp/Oracle_client_install/oracle_client.rsp
```

For Red Hat JBoss Enterprise Application Platform

To use JBoss, within the cluster or within an external database, complete the following steps.

1. Download Cloud Native Unica images and Helm Chart.
2. Add the installable `JBoss` and `JDBC Drivers` to the mount location.
3. Create `Databases` and `Users` and enter those details in the Unica Helm Chart.

If you set the Database as a sub-chart in Unica chart, you can completely automate data import using Shell scripts. For import, data should be available on the Database container mount point. You can also place the data after the container starts. Ensure that Database configuration and user creation activity is completed before running the Unica chart.

For auto-installation of database client on listener pod or container, complete the following steps:



Note: The commands and filenames are mentioned specific to Oracle database. Provide appropriate values based on the the database you use.

1. Place the Oracle client installer, named `linuxamd64_12102_client.zip`, inside the `/tmp` folder.
2. To extract the installer file, run the `unzip` command.

A new folder, named `client` is created in the location `/tmp`.

3. Run the following command:

```
cp /tmp/client/response/client_install.rsp /tmp/oracle_client.rsp
```

4. Access the `oracle_client.rsp` file and make the following changes in the file:

```
UNIX_GROUP_NAME=oinstall
INVENTORY_LOCATION=/home/oracle/oraInventory
ORACLE_HOME=/home/oracle/app/oracle/product/12.1.0/client_1
ORACLE_BASE=/home/oracle/app/oracle
oracle.install.client.installType=Administrator
```

5. Run the following commands:

```
cd /tmp
mkdir linuxamd64_12102_client
mv client linuxamd64_12102_client
tar -cvf Oracle_client.tar linuxamd64_12102_client oracle_client.rsp
gzip Oracle_client.tar
mv Oracle_client.tar.gz oracle_client.rsp /docker/unica
```

6. In the `/docker/unica/` location, create a file named `oracle.sh` and add the following content in the file:

```
yum install -y libaio
/tmp/Oracle_client_install/linuxamd64_12102_client/client/runInstaller
-silent -ignoreSysPrereqs -responseFile /tmp/Oracle_client_install/oracle_client.rsp
```

For Oracle WebLogic

To use WebLogic, within the cluster or within an external database, complete the following steps:

1. Download Cloud Native Unica images and Helm Chart.
2. Create `Databases` and `Users` and enter those details in the Unica Helm Chart.

If you set the Database as a sub-chart in Unica chart, you can completely automate data import using Shell scripts. For import, data should be available on the Database container mount point. You can also place the data after the container starts. Ensure that Database configuration and user creation activity is completed before running the Unica chart.

For auto-installation of database client on listener pod or container, complete the following steps:



Note: The commands and filenames are mentioned specific to Oracle database. Provide appropriate values based on the the database you use.

1. Place the Oracle client installer, named `linuxamd64_12102_client.zip`, inside the `/tmp` folder.
2. To extract the installer file, run the `unzip` command.

A new folder, named `client` is created in the location `/tmp`.

3. Run the following command:

```
cp /tmp/client/response/client_install.rsp /tmp/oracle_client.rsp
```

4. Access the `oracle_client.rsp` file and make the following changes in the file:

```
UNIX_GROUP_NAME=oinstall
INVENTORY_LOCATION=/home/oracle/oraInventory
ORACLE_HOME=/home/oracle/app/oracle/product/12.1.0/client_1
ORACLE_BASE=/home/oracle/app/oracle
oracle.install.client.installType=Administrator
```

5. Run the following commands:

```
cd /tmp
mkdir linuxamd64_12102_client
mv client linuxamd64_12102_client
tar -cvf Oracle_client.tar linuxamd64_12102_client oracle_client.rsp
gzip Oracle_client.tar
mv Oracle_client.tar.gz oracle_client.rsp /docker/unica
```

6. In the `/docker/unica/` location, create a file named `oracle.sh` and add the following content in the file:

```
yum install -y libaio
/tmp/Oracle_client_install/linuxamd64_12102_client/client/runInstaller
-silent -ignoreSysPrereqs -responseFile /tmp/Oracle_client_install/oracle_client.rsp
```

Listener Database client setup

To establish an ODBC connection to the database, the Campaign listener requires a database client.

About this task

If you do not have a database client, you must install it. For a seamless installation of the database client, perform the following steps:

1. Place the database client installer at the mount location (NFS).
2. Configure the location of the database client installer in the `campaign-configMap.yaml` file. For more information, see *Cloud Native Unica Implementation Guide* for the respective Application Server,

Setting up the Cloud Native environment

You must set up the Cloud Native environment before implementing Cloud Native Unica. The chart that you download uses Helm as a package manager for Kubernetes. The chart is a preconfigured application resource and it deploys Unica suite on a specified Kubernetes cluster. Extract the chart ZIP file to a location in the cloud VM, where you plan to deploy Unica. For reference purposes, this chart contains a placeholder for the database. Unica does not own the database and is not responsible for database management. If required, set a containerized database (the charts and subcharts folders are for reference) as a subchart to the Cloud Native Unica chart. You can use scripts to automate the restoration of database on a container.

Before you begin

The prerequisites for running a Helm chart are as follows:

- Download the required Docker images from Flex Net Operations (FNO).
- To import the downloaded Docker images for all the products, run the following command:

```
docker load -i product_image_name.tar
```

- To verify if all products images are loaded and available for use, run the following command:

```
docker images
```

- To tag the images appropriately, run the following command:

```
docker tag SOURCE_IMAGE[:TAG] TARGET_IMAGE[:TAG]
```

- To push the images to the docker registry, run the following command:

```
docker push TARGET_IMAGE[:TAG]
```

- Open the `values.yaml` file, which is placed inside the Unica folder, and edit:
 - the Docker images name in the `repository` section
 - the tag numbers in the `tag` section

See the following code snippet for reference:

```
image:
  repository:
    init: TARGET_IMAGE
    platform: TARGET_IMAGE
  tag:
    init: TAG
    platform: TAG
```

- Configure the database in one of the following ways:
 - **Database within Kubernetes cluster** - Set the database as a subchart to Unica helm chart. Unica will not own or manage the database chart.
 - **Pointing to an external database** - Configure the database to reside on the same subnet as the worker nodes to ensure good performance.

About this task

To set up Cloud Native Unica environment, complete the following steps:

1. Update chart configurations:

- a. Update or customize database and application server details in the `configMap` files for each products. For more information on `configMap` files, see the *Cloud Native Unica Implementation Guide* for your respective application server. An example for updating or customizing the `campaign-configMap.yaml` is as follows:

```
CAMPAIGN_DATABASE_HOST: "{{ .Release.Name }}-unica-suite-database"
CAMPAIGN_DATABASE_PORT: "1521"
CAMPAIGN_DATABASE_NAME: "xe"
CAMPAIGN_DATABASE_USERNAME: "campuser"
CAMPAIGN_DATABASE_PASSWORD: "unica"
CAMPAIGN_DS_INITIAL_SIZE: "1"
CAMPAIGN_DS_MIN_IDLE: "1"
CAMPAIGN_DS_MAX_IDLE: "15"
CAMPAIGN_DS_MAX_TOTAL: "80"
CAMPAIGN_DS_STATEMENT_CACHE_SIZE: "300"
```

For more information on configurations related to `values.yaml` file, see see the *Cloud Native Unica Implementation Guide* for your respective application server.

2. Update persistence volume:

- a. Based on the persistent volume of your choice, update the following files:

```
- unica/extra-configs/local-pv.yaml
- unica/templates/pvc.yaml
```

3. Perform an upgrade:

- a. You can use one of the following methods to upgrade:
 - Upgrade from On-premises to Cloud Native (for example, Unica version 9.1.2 to Cloud Native version 12.1.0)
 - Upgrade from earlier Cloud Native version to a new version (for example, Cloud Native version 12.0 to Cloud Native version 12.1)
- b. Before the upgrade, ensure that you have backed up the file system and the Database.
- c. Place the file system on the mount point and configure the **BASE_FOLDER** parameter in the `common-configMap.yaml` file to point to the file system location.
- d. Also, update the database details in the `common-configMap.yaml` file. For example, refer the following code snippet:

```
DATABASE_EXPORT_DIR: "/DBBACKUP/"
BASE_FOLDER: "OLDINSTALL/IBMUnica_86"
SOURCE_SCHEMA: "camp86"
TARGET_SCHEMA: "camp86"
SOURCE_SCHEMA_RT: "camp86"
TARGET_SCHEMA_RT: "camp86"
SOURCE_SCHEMA_PROD: "intpr86"
TARGET_SCHEMA_PROD: "intpr86"
SOURCE_SCHEMA_LRN: "intlr86"
TARGET_SCHEMA_LRN: "intlr86"
```

```
SOURCE_SCHEMA_RUN: "intrt86"  
TARGET_SCHEMA_RUN: "intrt86"
```

- e. In case of managed Kubernetes clusters, change the value of the **storageClassNames** parameter in the `values.yaml` file.



Note: Active MQ Image or Chart, provided by Unica, is for reference purposes only. Unica does not own or is not responsible for Active MQ Deployments.

Cloud Native Unica setup on SSL

You can configure SSL on Cloud Native Unica setup at the ingress level.

A provision exists to create a secret with a CERT file. For additional details, see *nginx-ingress documentation for TLS configuration*.

Chapter 2. Installation and verifying the installation

The following topics provide information related to installation and verification of installation.

- [Installation on page 13](#)
- [Verifying the chart on page 13](#)
- [Log files on page 13](#)

Installation

You can install Unica using Helm charts. Override the following Helm chart values using `--set name=value`.

Before you begin

- Ensure that `configMaps` in the helm chart are correctly configured.
- Verify all the configurations and ensure that the mount location does not have any Unica-related installation files.

1. `kubectl apply -f ./omnix-unica/extra-configs/local-pv.yaml`
2. `helm install --name nginx stable/nginx-ingress -f ./omnix-unica/extra-configs/nginx-conf.yaml`
3. `helm install --name unica -f ./omnix-unica/values-local.yaml omnix-unica --set service.hostname=kubernetes.nonprod.hclpnp.com --set service.applicationDomain='nonprod.hclpnp.com' --set ingress.enabled=true`

What to do next

After installation, add the installation related parameters in the `common-configMap.yaml` file for version 12.1.4.

Verifying the chart

About this task

Follow the instructions after the completion of Helm installation for chart verification. The chart generates an output for all the resources it creates.

1. To confirm if a chart has generated output for all the resources, run the following command:

```
helm ls
```

2. To view the installed helm release, run the following command:

```
helm status unica
```

3. To view the Unica Kubernetes pods, run the following command:

```
kubectl get pods
```

Log files

Confirm if the required containers are up and running. Upon confirmation, check the logs for all the running services.

- **Installation log files:**

The installation log files are placed in the logs folder at the mount point. For example, `$HOME_DIR/logs`.

- **Product log files:**

Log files are persisted out of the containers at the mount location. The log files for the products are placed in their respective install location folders. For example, if the product is Campaign and the mount location is `/docker/unica`, the Campaign log files will be available within the `/docker/unica/Campaign/logs/` location.

Campaign Log Files

To enable the `ETL`, `Engage`, and `UBX` logs within the Campaign logs folder, provide the absolute path in the `$CAMPAIGN_HOME/conf/campaign_log4j.xml` file.

Example

```
log4j.appender.ETL.File=/docker/unica/Campaign/logs/ETL.log
log4j.appender.ENGAGE_ETL.File=/docker/unica/Campaign/logs/EngageETL.log
log4j.appender.UBX.File=/docker/unica/Campaign/logs/UBX.log
```

Chapter 3. Post installation configurations

The following topics contain details about post installation configurations related to the products of Unica.

- [Configurations for Campaign on page 15](#)
- [Configurations for Director on page 16](#)
- [Configurations for Interact on page 16](#)
- [Configurations for Platform on page 17](#)

Configurations for Campaign

To add user database in Campaign, complete the following steps:

1. Connect to the Listener pod.
2. Add the user database.
3. In the application, navigate to **Campaign > Configuration**.
4. Add an entry for Datasources.

Configuring multi-partitions for Campaign

For Unica Campaign, you can configure the application within the partitions where you have configured an instance of Campaign.

Application users, within each partition, can access the Campaign functions, data, and customer tables that are configured for Campaign in the same partition.

Multiple partitions are useful for setting up a strong security between groups of users, because each partition has its own set of Campaign system tables.

You must not create multiple partitions if groups of users have to share data with each other.

Each partition has its own set of configuration settings. You can customize Campaign for each group of users. However, all partitions share the same installation binaries.

With the same binaries for all partitions, you can minimize the installation and upgrade efforts for multiple partitions.

The utility to create multi-partition is available in the `$HOME_DIR/Platform/tools/bin` location.

Provide values for the following parameters in the Campaign chart:

- **PARTITIONS** - Name of the partition you want to configure. In case of multiple partitions specify partition name separated by a semi-colon. For example `partition2;partition3`.
- **SOURCE_PARTITION** - The name of the source partition to be replicated.
- **DEST_PARTITION** - The name of the destination partition to be created.
- **PARTITION_USER** - Specifies the user name of the admin user for the replicated partition. The name must be unique within the instance of Unica Platform.

- **PARTITION_GROUP** - Specifies the name of the Platform admin group that the utility creates. The name must be unique within the instance of Unica Platform.
- **CAMPAIGN_PARTITION2_DATABASE_HOST** - Host system details of the system hosting the Campaign Partition2 database.
- **CAMPAIGN_PARTITION2_DATABASE_PORT** - Port number of the Campaign Partition2 database.
- **CAMPAIGN_PARTITION2_DATABASE_NAME** - Name of the Campaign Partition2 database.
- **CAMPAIGN_PARTITION2_DATABASE_USERNAME** - Username to access the Campaign Partition2 database.
- **CAMPAIGN_PARTITION2_DATABASE_PASSWORD** - Password to access the Campaign Partition2 database.
- **CAMPAIGN_PARTITION2_DS_INITIAL_SIZE** - The initial size of the Campaign Partition2 datasource connection pool.
- **CAMPAIGN_PARTITION2_DS_MIN_IDLE** - The minimum number of idle connections (not connected to a database) in the Campaign Partition2 datasource connection pool.
- **CAMPAIGN_PARTITION2_DS_MAX_IDLE** - The maximum number of idle connections (not connected to a database) in the Campaign Partition2 datasource connection pool.
- **CAMPAIGN_PARTITION2_DS_MAX_TOTAL** - The maximum number of connections that the Campaign Partition2 datasource can hold. If the number of connection requests exceed the configured value, the connection will be refused.
- **CAMPAIGN_PARTITION2_DS_STATEMENT_CACHE_SIZE** - Maximum number of statements that can be cached in the Campaign Partition2 datasource. Statement caching improves performance by caching executable statements that are used repeatedly.
- **CAMPAIGN_PARTITION2_JNDI_NAME** - JNDI name for Campaign Partition2.
- **CAMPAIGN_PARTITION2_POOL_NAME** - Pool name for Campaign Partition2.

The syntax to generate a partition is:

```
./multiPartition.sh >> output.out
```

After running the utility, restart the Platform and Campaign pod. After restarting the pods, login with `platform_admin`.

You can login with **PARTITION_USER** and the partition name you specify is used as the password for the `admin` user

Configurations for Director

`ActiveMQ` image is for reference or for tests. Unica does not own `ActiveMQ`. You can plug in your own `ActiveMQ` image in the helm chart.

About this task

To configure Director, complete the following step:

Update the `_DIR_HOME_` in the `Campaign/bin/setenv.sh` location with the actual path.

Configurations for Interact

About this task

For Gateway configurations to work, perform the following step.

1. Add the required `JAR` files and the configuration files to the mount location.
2. On JMX console, use the CentOS desktop and the VNC viewer to view the individual pod consoles. Enable port forwarding on different ports.

Configurations for Platform

For Director and Campaign History tab, you should configure the Platform settings.

About this task

To configure Platform settings, complete the following steps:

1. Log in to Unica Platform.
2. Select **Settings > Configuration**.
3. On the left pane, select **Unica Platform > Security > API management > Unica Platform**.
4. On the left pane, select **Authentication** and in the right pane click **Edit settings**. The value for the fields should be:

Field name	Value
API URI	<code>/authentication/login</code>
Block API access	Disabled
Secure API access over HTTPS	Enabled
Require authentication for API access	Disabled

5. On the left pane, select **User** and in the right pane click **Edit settings**. The value for the fields should be:

Field name	Value
API URI	<code>/usr/partitions/*</code>
Block API access	Disabled
Secure API access over HTTPS	Disabled
Require authentication for API access	Enabled

6. On the left pane, select **Policy** and in the right pane click **Edit settings**. The value for the fields should be:

Field name	Value
API URI	<code>/policy/partitions/*</code>
Block API access	Disabled
Secure API access over HTTPS	Disabled
Require authentication for API access	Enabled

7. On the left pane, select **Configurations** and in the right pane click **Edit settings**. The value for the fields should be:

Field name	Value
API URI	/datasource/config
Block API access	Disabled
Secure API access over HTTPS	Disabled
Require authentication for API access	Enabled

8. On the left pane, select **Datasource** and in the right pane click **Edit settings**. The value for the fields should be:

Field name	Value
API URI	/datasource
Block API access	Disabled
Secure API access over HTTPS	Disabled
Require authentication for API access	Enabled

9. On the left pane, select **Login** and in the right pane click **Edit settings**. The value for the fields should be:

Field name	Value
API URI	/authentication/v1/login
Block API access	Disabled
Secure API access over HTTPS	Disabled
Require authentication for API access	Disabled

10. On the left pane, select **Unica Campaign > Campaign REST API Filter** and in the right pane click **Edit settings**. The value for the fields should be:

Field name	Value
API URI	/rest/v1/*
Block API access	Disabled
Secure API access over HTTPS	Disabled
Require authentication for API access	Enabled

11. On the left pane, select **Unica Campaign > Campaign REST API V2 Filter** and in the right pane click **Edit settings**. The value for the fields should be:

Field name	Value
API URI	<code>/rest/v2/*</code>
Block API access	Disabled
Secure API access over HTTPS	Disabled
Require authentication for API access	Enabled

Chapter 4. Migration of on-premises applications to Cloud Native Unica

You can migrate an on-premise version of Unica to the Cloud Native version. The Cloud Native version will be deployed on the application server.

Migration prerequisites

The prerequisites for the migration are as follows:

- Take a backup of your existing database.
- Copy the file system of the previous version to the mount location.
- Provide appropriate values the database parameters of all Unica components.
- For Interact, the schema name in the target setup should be the same as the one in the base setup.
- Manually map the tables and restart the Campaign Pod.

`common-configMap` configurations

In the `common-configMap.yaml` file, provide values for the following fields:

Table 1. Configurable Parameters to perform an Upgrade

Parameter Name	Example Value
BASE_FOLDER	"OLDINSTALL/HCLUnica_86"
FROM	"8.6.0"
TO	"12.0.0"
SOURCE_SCHEMA	"CAMP86"
TARGET_SCHEMA	"DBO"
DB_DRIVER_CLASS	com.microsoft.sqlserver.jdbc.SQLServerDriver
AC_VERSION	"12.1.x"
ACI_UNICODE	"No"
CONFIGURE_ON_ERROR_PROMPT	"Yes"
LOCALE	"en_US"
TYPE	UPGRADE
DATABASE_EXPORT_DIR	/DBBACKUP/
ISEXTERNALDB	false
DB_IMPORT_WAIT_TIME	1050

Table 1. Configurable Parameters to perform an Upgrade (continued)

Parameter Name	Example Value
DB_PRE_IMPORT_WAIT_TIME	1050
IS_UNICODE	false
UPGRADE_FROM_TO	11.1+To12.1
LISTENER_HOST_NAME	{{ .Release.Name }}-omnix-unica-listener
SOURCE_SCHEMA_RT	camp86
TARGET_SCHEMA_RT	camp86
DB_DRIVER_CLASS_RT	com.ibm.db2.jcc.DB2Driver
SOURCE_SCHEMA_PROD	intpr86
TARGET_SCHEMA_PROD	intpr86
DB_DRIVER_CLASS_PROD	com.ibm.db2.jcc.DB2Driver
SOURCE_SCHEMA_LRN	intl86
TARGET_SCHEMA_LRN	intl86
DB_DRIVER_CLASS_LRN	com.ibm.db2.jcc.DB2Driver
SOURCE_SCHEMA_RUN	intr86
TARGET_SCHEMA_RUN	intr86
DB_DRIVER_CLASS_RUN	com.ibm.db2.jcc.DB2Driver

JVM option configurations

Add the JVM option `-DFAST_UPGRADE_VERSION=<BASE_VERSION>`. For example: `JAVA_OPTIONS="${JAVA_OPTIONS}`

`-DFAST_UPGRADE_VERSION=8.6.x`.

Performing the migration

The mount location should contain the old version of the Unica file system. Cloud Native containers will manage the database upgrade and the file system updates.

1. To perform the migration, run the following command.


```
helm install --name unica omnix-unica --set service.hostname=<kubernetes.nonprod.hclpnp.com --set service.applicationDomain='nonprod.hclpnp.com' --set ingress.enabled=true
```
2. Access the migration logs from the mount location.

Configuring Unica Campaign post migration

To configure Unica Campaign post migration, complete the following steps:

Update the parameter **internalServerURL** to point to your Campaign pod.

For example, `http://hcl-unica-campaign:9125/Campaign`.

Configuring Unica Interact post migration

To configure Unica Interact post migration, complete the following steps:

1. Back up the current configurations.
2. Navigate to **Affinium > Campaign > partitions > partition1 > Interact > serverGroups**.
3. In Unica configuration, delete the old `serverGroup` and retain only the Interact `serverGroup`.
4. Define Interact as the `serverGroup` for the following configurations:
 - **flowchart** configuration within **Affinium > Campaign > partitions > partition1 > Interact**
 - **simulator** configuration within **Affinium > Campaign > partitions > partition1 > Interact**
5. Update the Interact design schema by replacing the old `serverGroup` name with a new name. Execute the following commands:
 - `update uaci_deployment set servergroupname='interact';`
 - `update uaci_ICTOSVRGROUP set servergroupname='interact';`
 - `update uaci_OfferMappingSG set servergroupname='interact';`

Configuring Unica Platform post migration

To configure Unica Platform post migration, complete the following steps:

1. The Unica Platform application URL will point to the old base environment. Change the navigation URL using the SQL script from the Platform system database.
2. Manually change the URL of the start page, which appears when you log in to Unica Platform, from the `USM_PERSONALIZATION` table.
3. Copy the following properties files from the source environment to the destination environment. Ensure that all the URLs mentioned in the files are also updated to the destination environment.
 - `Platform_Admin_URL.properties`
 - `Platform_Admin_View_Priv.properties`
 - `Platform_Admin_URL.properties`
 - `Platform_Admin_Scheduler_Scripts.properties`
 - `Platform_Admin_Scheduler_API.properties`

Chapter 5. Cloud Native Unica upgrade

To upgrade an earlier version of Cloud Native Unica to a newer version, complete the following steps:

1. Unica support team will roll out the Helm Charts after you specify the offering related details and requirements. Please contact Unica support team to get a Helm chart.
2. Download the required version image and push it to the Docker registry.
3. Update the image URLs in the helm charts.
4. Back up the Database and the file system before you start the upgrade.
5. Run the following helm upgrade command:

```
helm upgrade hcl unica -f ./unica/values-local.yaml --set service.hostname=kubernetes.nonprod.hclpnp.com --set service.applicationDomain='nonprod.hclpnp.com' --set ingress.enabled=true
```

6. Add upgrade related parameters in the `common-configMap.yaml` file when upgrading to version 12.1.6.
7. Edit the helm chart `platform-deployment.yaml`. In the file, replace `args: ["chmod 755 /docker/unica && ./entrypoint.sh"]` with the following entry:

```
args: ["chmod 755 /docker/unica && echo 'find /opt/generate_datasource_snippet.sh -type f -print0 | xargs -0 sed -i \"s/export DB_URL=\\$/#export DB_URL=/g\"' > /docker/unica/centos_patch.sh && chmod 777 /docker/unica/centos_patch.sh && ./entrypoint.sh"]
```

Custom listener scripts and Cloud Native Unica container OS upgrade

Unica container OS upgrade from CentOS 8 to RHEL Universal Base Image (UBI) v8.5 may cause listener pod custom scripts to fail (applies to Cloud Native Unica versions 12.1.2 / 12.1.3).

1. Modify custom scripts as per RHEL UBI OS. Example: Database Client Installation Script on listener pod.
2. Centos8 OS was updated to RHEL UBI 8.5 because of CentOS 8 end of life.
3. Also, RHEL UBI containers are less vulnerable to security threats because of the frequent fixing and release cycle.

Chapter 6. Installing Apache Superset with Unica as a Sub-chart

This topic provides information about installing and configuring Apache Superset as a sub-chart in the Unica Helm chart.

Prerequisites

- Ensure that Helm is installed in the system.
- Ensure that you can access the Helm chart and the `values.yaml` file and have the privileges to modify them.

Directory Structure for Oracle System Database (Optional)

To install Oracle connector for Superset, place the necessary Oracle RPM files in the server and ensure that it has the following structure:

```
<HOME_DIR>/oracle_rpm/  
|____instantclient_21_15.tar  
|____libaio1_0.3.113-4_amd64.deb
```

Known Vulnerabilities and Fixes

Unica supports Superset version 4.0.2 and following are the list of vulnerabilities fix in this version: <https://superset.apache.org/docs/security/cves/>

Images and Tags:

- apachesuperset.docker.scarf.sh/apache/superset:4.0.2
- docker.io/bitnami/postgresql:14.6.0-debian-11-r13
- docker.io/bitnami/redis:7.0.10-debian-11-r4

Configurations to Customize Superset

The customization for the Superset sub-chart is controlled using the following sections in the `values.yaml` file of the parent Unica Helm chart:

1. Add a sub-chart for Unica

```
/Unica-helm-chart-location/unica/charts/superset.
```

/root/ankityamls/TomcatMariaDB_12.1.9/unica/charts/				
Name	Size	Changed	Rights	Owner
..		15-11-2024 15:15:11	rxwxrwx	root
superset		15-11-2024 15:13:57	rxwxrwx	root

2. Enable SS Mode in `commonConfigMap.yaml` of Unica.

```
/<chart-location>/unica/templates/common-configMap.yaml
```

```
MODE: "PLT_CMP_INT_OFFER RTP_SS"
```


3. In the values .yaml file of the Unica Helm chart, add the following variables:

a. **Global Settings** - Sets global variables for the installation paths and claims.

```
global:
  HOME_DIR: "/docker/unica"
  SUPERSETEXISTINGCLAIM: "hcl-unica"
  UPDATE_DASHBOARD_TAG: true
  CLEANUP_DASHBOARD_FOR_REIMPORT: false
  image:
    busybox: "busybox:1.28"
  superset:
    supersetNode:
      connections:
        db_host: '{{ .Release.Name }}-postgresql'
        db_port: "5432"
        db_user: superset
        db_pass: superset
        db_name: superset
        redis_host: '{{ .Release.Name }}-redis-headless'
        redis_port: "6379"
        redis_user: ""
      extraSecretEnv:
        # Generate your own secret key for encryption. Use openssl rand -base64 42 to generate a good key
        SUPERSET_SECRET_KEY: 'oQecTVRqA7ERuAWair6+b6W2MzTt1cLNu61cM/7KnLnrmClkKBoxZxc'
        # configOverrides:
        # secret: |
        # SECRET_KEY = 'oQecTVRqA7ERuAWair6+b6W2MzTt1cLNu61cM/7KnLnrmClkKBoxZxc'
    image:
      repository: apachesuperset.docker.scarf.sh/apache/superset
      tag: 4.0.2
    init:
      adminUser:
        username: superadmin
        password: superadmin
      #HOME_DIR: "/docker/unica"
      # SUPERSETEXISTINGCLAIM: "hcl-unica"
    service:
      port: 8088
    postgresql:
      tag: "14.6.0-debian-11-r13"
      registry: docker.io
      repository: bitnami/postgresql
    # mariadb://campuser:unica*03@hcl-unica-suite-database:3306/campaigndb
    SUPERSET_CUSTOM:
      CAMP_DBSCHAMA: "campaigndb"
      CAMP_SQLALCHEMY_URI: "mariadb://campuser:unica*03@hcl-unica-suite-database:3306/campaigndb"
      PLAN_DBSCHAMA: "plandb"
      PLAN_SQLALCHEMY_URI: "mariadb://mouser:unica*03@hcl-unica-suite-database:3306/plandb"
      INT_DBSCHAMA: "interactdb"
      INT_SQLALCHEMY_URI: "mariadb://intuser:unica*03@hcl-unica-suite-database:3306/interactdb"
      JOURNEY_DBSCHAMA: "journeydb"
      JOURNEY_SQLALCHEMY_URI: "mariadb://journeyuser:unica*03@hcl-unica-suite-database:3306/journeydb"
      RTP_DBSCHAMA: "campaigndb"
      RTP_SQLALCHEMY_URI: "mariadb://campuser:unica*03@hcl-unica-suite-database:3306/campaigndb"
      INTDT_DBSCHAMA: "campaigndb"
      INTDT_SQLALCHEMY_URI: "mariadb://campuser:unica*03@hcl-unica-suite-database:3306/campaigndb"
      SUPERSET_DEFAULT_LOCALE: "en"
```

```
global:
  HOME_DIR: "/docker/unica"
  SUPERSETEXISTINGCLAIM: "hcl-unica"
  UPDATE_DASHBOARD_TAG: true
  CLEANUP_DASHBOARD_FOR_REIMPORT: false
  image:
    busybox: "busybox:1.28"
```

HOME_DIR	Base directory for Unica and Apache Superset and related files.
SUPERSETEXISTINGCLAIM	Provide the Existing Persistent Volume Claim, if any.
UPDATE_DASHBOARD_TAG	If superset dashboard tag need to be updated. Accepted values are either <code>true</code> OR <code>false</code> .

CLEANUP_DASHBOARD_FOR_REIMPORT	Set it to <code>true</code> when dashboards existing dashboards, charts and datasets needs to be deleted, and new dash boards need to be imported. Accepted values are either <code>true</code> or <code>false</code> .
image.busybox	Image version for busybox utilities used by Superset (required for init container).

b. Superset Node Connection Details - Defines database and Redis connection configurations.

```
superset:
  supersetNode:
    connections:
      db_host: '{{ .Release.Name }}-postgresql'
      db_port: "5432"
      db_user: superset
      db_pass: superset
      db_name: superset
      redis_host: '{{ .Release.Name }}-redis-headless'
      redis_port: "6379"
      redis_user: ""
```

db_host	PostgreSQL database hostname.
db_port	Port on which PostgreSQL is accessible.
db_user / db_pass	Credentials for Superset to access PostgreSQL.
redis_host / redis_port	Hostname and port for Redis.

c. Environment Variables and Secret Key - Manages sensitive environment variables such as the secret key.

```
extraSecretEnv:
  SUPERSET_SECRET_KEY: 'oQecTVRqA7ERuAWair6+b6W2MzTTt1cLNu6lcM/7KnLnrmC1kKBuxZxc'
```

SUPERSET_SECRET_KEY	Generate the key using the command : <code>openssl rand -base64 42</code>
----------------------------	---

d. Superset Docker Image - Specifies the Superset Docker image repository and version.

```
image:
  repository: apachesuperset.docker.scarf.sh/apache/superset
  tag: 4.0.2
```

repository	<code>apachesuperset.docker.scarf.sh/apache/superset</code>
-------------------	---

e. Redis and PostgreSQL Images - Specifies additional services' images, like Redis and PostgreSQL.

```
redis:
  image:
    registry:docker.io
    repository:bitnami/redis
```

```

tag:7.0.10-debian-11-r4
postgresql:
  registry:docker.io
  repository:bitnami/postgresql
  tag:"14.6.0-debian-11-r13"

```

Image	
registry	Example value: <code>docker.io</code>
repository	Example value: <code>bitnami/redis</code>
tag	Example value: <code>7.0.10-debian-11-r4</code>
PostgreSQL	
registry	Example value: <code>docker.io</code>
repository	Example value: <code>bitnami/postgresql</code>
tag	Example value: <code>14.6.0-debian-11-r13</code>

- f. **Admin User Initialization** - Creates the initial admin user for Superset. These credentials will be required for superset UI login.

```

init:
  adminUser:
    username: superadmin
    password: superadmin

```

username	Example value: <code>superadmin</code>
password	Example value: <code>superadmin</code>

- g. **Service Port** - Sets the service port for Superset.

```

service:
  port: 8088

```

port	Example value: <code>8088</code>
-------------	----------------------------------

- h. **Superset Custom Database Configurations** - Sets up various schemas and `SQLAlchemy` URIs for Superset connections.

```

SUPERSET_CUSTOM:
  CAMP_DBSCHAMA: ""
  CAMP_SQLALCHEMY_URI: ""
  PLAN_DBSCHAMA: ""
  PLAN_SQLALCHEMY_URI: ""
  SUPERSET_DEFAULT_LOCALE: ""

```

SQLALCHEMY_URI	Configure <code>SQLALCHEMY_URI</code> as follows for the specified Databases:
-----------------------	---

	<ul style="list-style-type: none"> ▪ mariadb:// <code><USERNAME>:<PASSWORD>@<HOSTNAME>: <PORT>/<DBNAME></code> ▪ oracle:// <code><USERNAME>:<PASSWORD>@<HOSTNAME>: <PORT>/<DBNAME></code> ▪ db2+ibm_db:// <code><USERNAME>:<PASSWORD>@<HOSTNAME>: <PORT>/<DBNAME></code> ▪ mssql+pymssql:// <code><USERNAME>:<PASSWORD>@<HOSTNAME>: <PORT>/<DBNAME></code> ▪ postgresql:// <code><USERNAME>:<PASSWORD>@<HOSTNAME>: <PORT>/<DBNAME></code>
--	--



Note: If the password contains any special character, use the hexadecimal value of the special character.

Example: If the password is `Example@123`, for the following link:

`mariadb://<USERNAME>:<PASSWORD>@<HOSTNAME>:<PORT>/<DBNAME>`, replace `<PASSWORD>` with `Example%40123` and not `Example@123`.

Chapter 7. Installing Standalone Superset

This topic provides information about installing and configuring Apache Superset explicitly on on-premises Unica.

Prerequisites

- Ensure Helm is installed on the system.
- Ensure that you can access the Helm chart and the `values.yaml` file and have the privileges to modify them.

Directory Structure if System Database is Oracle

To install Oracle connector for Superset, place the necessary Oracle RPM files in the server and ensure that it has the following structure:

```
<HOME_DIR>/oracle_rpm/  
|_____instantclient_21_15.tar  
|_____libaio1_0.3.113-4_amd64.deb
```

Known Vulnerabilities and Fixes

Unica supports Superset version 4.0.2 and following are the list of vulnerabilities fix in this version: <https://superset.apache.org/docs/security/cves/>

Images and Tags:

- `apachesuperset.docker.scarf.sh/apache/superset:4.0.2`
- `docker.io/bitnami/postgresql:14.6.0-debian-11-r13`
- `docker.io/bitnami/redis:7.0.10-debian-11-r4`

Configuring Superset for Unica

Setting up Directory Structure

About this task

Set up the following directory structure for the enabled products by placing the respective files:


/docker/unica/Superset/				
Name	Size	Changed	Rights	Owner
..		30-11-2024 00:40:22	rwxf-xr-x	root
Campaign		02-12-2024 10:44:25	rwxfwxrwx	root
Deliver		02-12-2024 10:44:25	rwxfwxrwx	root
flags_localization_update		21-11-2024 15:59:46	rwxfwxrwx	root
flags_superset_import		02-12-2024 13:20:23	rwxfwxrwx	root
flags_superset_update		02-12-2024 13:02:19	rwxfwxrwx	root
Interact		02-12-2024 10:44:25	rwxfwxrwx	root
InteractDT		02-12-2024 10:44:25	rwxfwxrwx	root
Journey		02-12-2024 10:44:25	rwxfwxrwx	root
Plan		02-12-2024 10:44:25	rwxfwxrwx	root
postgres		15-11-2024 16:45:03	rwxfwxrwx	root
RTP		02-12-2024 10:44:25	rwxfwxrwx	root
utilities		21-11-2024 15:58:04	rwxfwxrwx	root

1. (Example) For Campaign:

```
<HOME_DIR>/Superset
|___ Campaign
    |___ sp_campaign_update_dashboards_tags.sql
    |___ en
    |___ campaignsupersetreports.zip
```

2. (Example) For Plan:

```
|___ Plan
    |___ sp_plan_update_dashboards_tags.sql
    |___ en
    |___ plansupersetreports.zip
```

 **Note:** The same structure applies for all other products.

3. For Utilities:

/docker/unica/Superset/utilities/				
Name	Size	Changed	Rights	Owner
..		28-11-2024 22:30:41	rwxfwxrwx	root
scripts		21-11-2024 15:58:04	rwxfwxrwx	root
pip_connector_310		21-11-2024 15:58:04	rwxfwxrwx	root

```
<HOME_DIR>/Superset/
|___ utilities
    |___ scripts
        |___ superset-db-cleanup.sql
        |___ dashboard_files_update.py
        |___ superset_localization.py
        |___ update_unica_superset_zips.sh
        |___ import_unica_superset_dashboards.sh
        |___ dashboard-tag-update-postgres.sh
        |___ superset-dashboard-db-cleanup.sh
```

/docker/unica/Superset/utilities/pip_connector_310/				
Name	Size	Changed	Rights	Owner
..		21-11-2024 15:58:04	rw-rw-rw-	root
werkzeug-3.0.4-py3-none-any.whl	223 KB	02-12-2024 10:44:25	rw-rw-rw-	root
urllib3-2.2.3-py3-none-any.whl	124 KB	02-12-2024 10:44:25	rw-rw-rw-	root
tzlocal-5.2-py3-none-any.whl	18 KB	02-12-2024 10:44:25	rw-rw-rw-	root
typing_extensions-4.12.2-py3-none-any.whl	37 KB	02-12-2024 10:44:25	rw-rw-rw-	root
trino-0.330.0-py3-none-any.whl	53 KB	02-12-2024 10:44:25	rw-rw-rw-	root
SQLAlchemy-2.0.36-cp310-cp310-manylinux_2_17_x86_64.manylinux2014_x...	3,003 KB	02-12-2024 10:44:25	rw-rw-rw-	root
six-1.16.0-py2.py3-none-any.whl	11 KB	02-12-2024 10:44:25	rw-rw-rw-	root
requests-2.32.3-py3-none-any.whl	64 KB	02-12-2024 10:44:25	rw-rw-rw-	root
pytz-2024.2-py2.py3-none-any.whl	497 KB	02-12-2024 10:44:25	rw-rw-rw-	root
python_dateutil-2.9.0.post0-py2.py3-none-any.whl	225 KB	02-12-2024 10:44:25	rw-rw-rw-	root
pymssql-2.3.1-cp310-cp310-manylinux_2_28_x86_64.whl	4,494 KB	02-12-2024 10:44:25	rw-rw-rw-	root
MarkupSafe-3.0.1-cp310-cp310-manylinux_2_17_x86_64.manylinux2014_x8...	21 KB	02-12-2024 10:44:25	rw-rw-rw-	root
jinja2-3.1.4-py3-none-any.whl	131 KB	02-12-2024 10:44:25	rw-rw-rw-	root
itsdangerous-2.2.0-py3-none-any.whl	16 KB	02-12-2024 10:44:25	rw-rw-rw-	root
idna-3.10-py3-none-any.whl	69 KB	02-12-2024 10:44:25	rw-rw-rw-	root
ibm_db-3.2.3-cp310-cp310-manylinux_2_17_x86_64.manylinux2014_x86_64....	42,590 KB	02-12-2024 10:44:25	rw-rw-rw-	root
ibm_db_sa-0.4.1-py3-none-any.whl	31 KB	02-12-2024 10:44:25	rw-rw-rw-	root
greenlet-3.1.1-cp310-cp310-manylinux_2_24_x86_64.manylinux_2_28_x86_6...	586 KB	02-12-2024 10:44:25	rw-rw-rw-	root
flask-3.0.3-py3-none-any.whl	100 KB	02-12-2024 10:44:25	rw-rw-rw-	root
Flask_Cors-5.0.0-py2.py3-none-any.whl	15 KB	02-12-2024 10:44:25	rw-rw-rw-	root
cx_Oracle-8.3.0-cp310-cp310-manylinux_2_5_x86_64.manylinux1_x86_64.ma...	872 KB	02-12-2024 10:44:25	rw-rw-rw-	root
click-8.1.7-py3-none-any.whl	96 KB	02-12-2024 10:44:25	rw-rw-rw-	root
charset_normalizer-3.4.0-cp310-cp310-manylinux_2_17_x86_64.manylinux2...	142 KB	02-12-2024 10:44:25	rw-rw-rw-	root
certifi-2024.8.30-py3-none-any.whl	164 KB	02-12-2024 10:44:25	rw-rw-rw-	root
blinker-1.8.2-py3-none-any.whl	10 KB	02-12-2024 10:44:25	rw-rw-rw-	root

```
<HOME_DIR>/Superset/
|__ utilities
|__ pip_connector_310
```

/docker/unica/Superset/utilities/configs/				
Name	Size	Changed	Rights	Owner
..		03-12-2024 16:29:18	rw-rw-rw-	root
f41b692eed5ba18b8e3f.chunk.js	665 KB	06-12-2024 10:08:31	rw-r--r--	root
tail_js_custom_extra.html	2 KB	06-12-2024 10:08:28	rw-r--r--	root
manager.py	94 KB	03-12-2024 16:29:17	rw-rw-rw-	root

```
<HOME_DIR>/Superset/
|__ utilities
|__ configs
```

4. Update the values .yaml file as per your requirement. Refer the following example:

```
global:
  HOME_DIR: "/docker/unica"
  SUPERSETEXISTINGCLAIM: "hcl-unica"
  UPDATE_DASHBOARD_TAG: true
  CLEANUP_DASHBOARD_FOR_REIMPORT: false
image:
  busybox: "busybox:1.28"
# LOCAL_HOME_DIR: "/docker/unica"
```

```

persistence:
  enabled: true
  accessModes:
    - ReadWriteOnce
  size: 10Gi
  storageClass: "productstore"
SUPERSET_CUSTOM:
  CAMP_DBSCHAMA: "campaign_v1219_db2"
  CAMP_SQLALCHEMY_URI: "db2+ibm_db://campaign_v1219_db2:unica*03@10.115.36.97:50001/siya"
  PLAN_DBSCHAMA: "plandb"
  PLAN_SQLALCHEMY_URI: "oracle://delivertp:delivertp@10.115.198.13:1521/orcl"
  INT_DBSCHAMA: "intdb"
  INT_SQLALCHEMY_URI: "oracle://delivertp:delivertp@10.115.198.13:1521/orcl"
  JOURNEY_DBSCHAMA: "journeydb"
  JOURNEY_SQLALCHEMY_URI: "oracle://delivertp:delivertp@10.115.198.13:1521/orcl"
  RTP_DBSCHAMA: "campaign_v1219_db2"
  RTP_SQLALCHEMY_URI: "db2+ibm_db://campaign_v1219_db2:unica*03@10.115.36.97:50001/siya"
  INTDT_DBSCHAMA: "intdtb"
  INTDT_SQLALCHEMY_URI: "oracle://delivertp:delivertp@10.115.198.13:1521/orcl"
  SUPERSET_DEFAULT_LOCALE: "en_US"
nameOverride: "unica-superset"

```



Note: If you are using an external Postgres database, update the Superset Postgres database details parameter.

If you are using external PostgreSQL server, you can disable the inbuilt PostgreSQL installation using following parameters in the `<unica-chart-location>/unica/charts/superset/values.yaml` file:

- `postgresql.enabled: false`

Reimporting Dashboards and Tags

1. Run the cleanup job and perform the helm upgrade.

In the `values.yaml` file, set the `CLEANUP_DASHBOARD_FOR_REIMPORT` to `True`. By default, the value is `False`. This creates a job which deletes the old dashboards, charts, and datasets.

2. Delete the respective product update flag from the location `/unica/Superset/flags_superset_update/`.

/docker/unica/Superset/flags_superset_update/				
Name	Size	Changed	Rights	Owner
..		02-12-2024 13:03:19	rw-rwxrwx	root
update_Campaign.flag	0 KB	02-12-2024 13:02:19	rw-r--r--	root
update_Deliver.flag	0 KB	02-12-2024 13:02:19	rw-r--r--	root
update_INTERACTDT.flag	0 KB	02-12-2024 13:02:19	rw-r--r--	root
update_Journey.flag	0 KB	02-12-2024 13:02:19	rw-r--r--	root
update_Plan.flag	0 KB	02-12-2024 13:02:19	rw-r--r--	root
update_RTP.flag	0 KB	02-12-2024 13:02:19	rw-r--r--	root

3. Delete the respective product import flag from the location `/unica/Superset/flags_superset_import/`.

/docker/unica/Superset/flags_superset_import/				
Name	Size	Changed	Rights	Owner
..		02-12-2024 13:03:19	rwxrwxrwx	root
imported_campaign.flag	0 KB	02-12-2024 13:03:39	rw-r--r--	root
imported_deliver.flag	0 KB	02-12-2024 13:03:56	rw-r--r--	root
imported_journey.flag	0 KB	02-12-2024 13:20:23	rw-r--r--	root
imported_plan.flag	0 KB	02-12-2024 13:20:15	rw-r--r--	root
imported_rtp.flag	0 KB	02-12-2024 13:04:21	rw-r--r--	root

4. Delete the respective product localization flag from the location `/unica/Superset/flags_localization_import/`.

/docker/unica/Superset/flags_localization_update/				
Name	Size	Changed	Rights	Owner
..		02-12-2024 13:03:19	rwxrwxrwx	root

5. Perform the helm upgrade and wait for the cleanup job to complete.
6. Restart the superset pod and wait for superset to be ready.
7. Delete the dashboard tag update job using the following command:

```
kubectl delete job <your-job-name-dashboard-tag-update-postgres>
```

8. Perform the helm upgrade.

Chapter 8. Scaling Unica containers

The following topics provide information on scaling the containers of Unica:

- For details related to scaling Listener containers, see [Scaling Listener containers on page 34](#).
- For details related to scaling Interact containers, see [Scaling Interact containers on page 36](#).
- For details related to scaling Journey engine containers, see [Scaling Journey engine containers on page 42](#).

Horizontal scaling of Unica containers

Scaling a deployment ensures creation and scheduling of new Pods. Scaling increases the number of Pods to the new required state. Kubernetes also supports autoscaling of Pods.

For Multicast, perform the configurations on Kubernetes host to support it. For example, weave supports multicast and can be configured for multicast support.



Note: Autoscaling of Unica containers is not supported.

Scaling Listener containers

Listeners are defined as StatefulSets in Kubernetes. Each Pod in a StatefulSet derives its hostname from the name of the StatefulSet and the ordinal of the Pod.

The Pod domain is managed by the service and it takes the following form:

```
$(service name).$(namespace).svc.cluster.local.
```

For example, the listener pod entry is registered as follows:

```
listener-0.listener.default.svc.cluster.local
```

These can be configured in the Helm chart in the `campaign-configMap.yaml` file.

Like a Deployment, a StatefulSet manages the Pods that are based on identical container specifications. Unlike a Deployment, a StatefulSet maintains a sticky identity for each of their Pods.

The location of Campaign shared home is `$HOME_DIR/Campaign`.

For the scaled instances of StatefulSet, `listener-0`, `listener-1`, `listener-2`,...`listener-n`, each instance has a file system mapped on the mount location. For example, `$HOME_DIR/listener/listener-0`.

Ordered scale up and scale down

1. Ordered and graceful deployment and scaling.

If you want to scale up the Listener pod, run the following command:

```
kubectrl scale StatefulSets listener --replicas=2
```

2. First instance gets deleted in the end.

If you want to scale down the Listener pod, run the following command:

```
kubectl scale StatefulSets listener --replicas=1
```

Listener-Optimize merge

1. Single scalable deployment in Kubernetes.
2. Configuration and license driven `config.xml`.
3. [Listener integration on page 35](#)

Cluster mode

1. To enable scaling, by default, cluster mode must be `TRUE`.

Also perform the following listener-related scaling activities:

- [Load balancing on page 35](#)
- [Listener integration on page 35](#)

Load balancing

For load balancing, there is a single listener that executes commands related to Campaign flowchart and Optimize sessions. In comparison to Campaign flowchart, an Optimize session requires a significantly better hardware configuration, which exceeds the minimum recommendation, for successful execution.

About this task

This newly introduced single listener helps the master listener to decide the node on which it should send the execution of the flowcharts or sessions, considering the `loadBalanceWeight`. We recommend that you avoid executing Optimize sessions on a node, configured to execute Campaign flowcharts. Similarly, we recommend that you avoid setting up a node with a significantly higher configuration of hardware for executing flowcharts. Using the new flag, the master listener can utilize the available resources in an appropriate way.

Choose an appropriate `listenerType` during installation based on the hardware, or configuration, or your requirements.

Listener integration

Prior to Unica 12.0 release, Campaign and Optimize were separate products. Users having both Campaign and Optimize had to run separate listeners. The Campaign listener `unica_aclsnr` to run flowcharts and Optimize listener `unica_acolsnr` to run the Optimize session.

Campaign-Optimize merged scenario

With text-based license for v12, the listener image expects a license file at mount point.

If both listener host name txt (`listener-0.txt` ...) and `opt.instance` file exist, it will create only the Optimize listener.

If listener host name `TXT` contains the first listener, it creates the listener as `LISTENER_TYPE 3`, which means it is for both Campaign and Optimize, otherwise it creates the listener as `LISTENER_TYPE 2` indicating that it is only for Optimize.

If the listener host name `txt`, `listener-0.txt` and so on, exists and the `opt.instance` file does not exist, it creates the listener as `LISTENER_TYPE 3`, which indicates that it is for both Campaign and Optimize.

Listener types

- **CAMPAIGN_ONLY (TYPE 1)** - This listener can handle commands for Campaign or flowchart only.
- **OPTIMIZE_ONLY (TYPE 2)** - This listener can handle commands for Optimize session only.
- **ALL ((TYPE 3)**- This listener can handle commands for Campaign or Flowchart or Optimize session.

The Type option is available in the following locations:

- **Settings > Configuration > Campaign > unicaACLlistener**
- **Settings > Configuration > Campaign > unicaACOLlistener**

Scaling Interact containers

Each existing Interact machine runs a Kubernetes Interact deployment. If you have set the **hostNetwork** to `TRUE`, the existing network, which already supports multicast, can be used as it is without changing any settings. You can also use the existing load balancers over the Kubernetes Interact deployments.

To scale Interact pods for multiple server groups, refactor the helm chart to add services and deployments per server group. Each Server Group should point to a different Platform Instance. For example, if there are three RT server groups, there will be three Platform instances (three services and three deployments for Platform and Interact).

The **CONTEXT_ROOTS** variable, in the `interact_configMap.yaml` file drives:

- the context roots for Interact and Platform.
- PLT and RT database details per server group.

If you want to scale pods for a server group, run the following command:

```
kubectl scale deployment hcl-unica-interact --replicas=2
```

If the Interact POD crashes, or if you manually delete the pod, manually delete an entry from the configuration using the following command:

```
./configTool.sh -d -p 'Affinium|Campaign|partitions|partition1|Interact  
|serverGroups|interactatm|instanceURLs|$1' -o "
```

In the earlier command `$1` refers to the Interact POD name that crashed or was manually deleted.

Monitoring the scaled instances



Note: Ensure that VNC viewer exists on the host machine to monitor instances.

You can perform JMX monitoring for each of the scaled instances using port forwarding.

For POD1, run the following command:

```
kubectl port-forward --address 0.0.0.0 pod/unica-omnix-unica-interact-84d7b47f59-d2rsl 9998:9998 &
```

For POD2, run the following command:

```
kubectl port-forward --address 0.0.0.0 pod/unica-omnix-unica-interact-84d7b47f59-d2rsl 9999:9998 &
```

Additionally, if your application server is WebLogic, the DB hostname should be a fully qualified domain name or else the Kubernetes service name will not work.

Interact Autoscaling

Interact Autoscaling feature ensures optimal performance and resource management with Cloud Native Deployments.

Leveraging the autoscaling capabilities ensures the maintenance of a seamless customer experience, adapting dynamically to varying workloads and resource demands.

With autoscaling, you can automatically scale Interact runtime servers up or down, based on defined situations such as traffic, resource utilization levels and quality of metrics.

Additionally, you can use autoscaling to maintain application availability. Autoscaling responds to changing demand. The metrics that are used to trigger scaling are an aggregation of metrics coming from all of the Interact server instances.

Example:

If have two runtime server instances where one instance is at 60 percent CPU and the other is at 40 percent CPU, the average of both is 50 percent CPU. When the policy is in effect, Autoscaling adjusts the group's desired capacity to go up or down when the threshold is triggered.

Define a scaling policy to track a specific metric using parameters mentioned in the configuration file. The parameters are as follows:

Variables	Example Values	Required For	Description
AUTOSCALE	True		To enable or disable custom autoscale. To enable set it to <code>True</code> . To disable set it to <code>False</code> .
AVERAGEEXECUTIONTIMEINMILLIS_THRESHOLD	1500	AUTOSCALE	JMX threshold for <code>AVERAGEEXECUTIONTIMEINMILLIS</code> .
CPU_HIGH_LIMIT	97	AUTOSCALE	CPU high limit. In case the CPU utilization reaches 97%, it autoscales without checking any other paramater.

Variables	Example Values	Required For	Description
CPU_LOW_LIMIT	15	AUTOSCALE	CPU low limit. In case the CPU utilization reaches 15%, it does not scaledown.
CPU_TARGET_MAX	65	AUTOSCALE	CPU target limit. If CPU utilization reaches 65%, it checks and scales up Interact deployments.
CPU_TARGET_MIN	25	AUTOSCALE	CPU target low limit. if CPU utilization reaches 25%, it checks and scales down Interact deployments.
GETOFFERSAVERAGE_THRESHOLD	0.2	AUTOSCALE	JMX threshold for GETOFFERSAVERAGE.
HOME_PATH	/docker/unica	AUTOSCALE / HYBRIDINTERACT / INTERACTURL	<ul style="list-style-type: none"> • The path to access Unica logs folder to write logs. • To copy, create, and delete temporary files or folders. • To access the config tool.
HYBRIDINTERACT	False		Enables or disables Interact hybrid solution. To enable, set it to True. To disable, set it to False.
INTERACTURL	False		Enables or disables Interact RT registration and deletion. To enable, set it to True. To disable, set it to False.
MEMORY_HIGH_LIMIT	97	AUTOSCALE	Memory high limit. In case the memory utilization reaches 97%, it autoscales without checking any other parameter.

Variables	Example Values	Required For	Description
MEMORY_LOW_LIMIT	15	AUTOSCALE	Memory low limit. In case the memory utilization reaches 15% it does not scaledown.
NameSpace	{{ .Release.Namespace }}	AUTOSCALE / HYBRIDINTERACT / INTERACTURL	Paramtere for specifying the namespace to be monitored. It is required for scaling or Interact hybrid, Interact URL regestraton, and deletion module.
Partition_Name	partition1	INTERACTURL	Parameter required for Interact URL regestraton and deletion module. Since it can monitor only one partition at a time, it monitors only the specified partition.
POD-REG-COUNTER	5	AUTOSCALE	The number of times to check if any new pods are getting started before moving to the cleanup section or the waiting cycle.
POD-REG-COUNTER-DELAY	10	AUTOSCALE	Delay between two checks of POD-REG-COUNTER. If POD-REG-COUNTER is 5 and POD-REG-COUNTER-DELAY is 10 seconds, the total exection time will be minimum 50 seconds.
Qos_Enabled	True	AUTOSCALE	To enable or disable autoscale on quality of service. Valid values are: AVERAGEEXECUTIONTIMEINMILLIS, GETOFFERSAVERAGE.
RAM_TARGET_MAX	65	AUTOSCALE	The Memory target limit. If Memory utilization reaches 65% it checks and scales up Interact deployments.

Variables	Example Values	Required For	Description
RAM_TARGET_MIN	55	AUTOSCALE	Memory target low limit. If Memory utilization reaches 55% it checks and scales down Interact deployments.
REPLICAS	'{interact :[1,3] }'	AUTOSCALE	The count of minimum and maximum replicas required for each Interact deployment.
Resource_Enabled	True	AUTOSCALE	To enable or disable autoscale on resources, RAM, and CPU.
SCALEDOWN_COUNTER_DELAY	10	AUTOSCALE	The delay between two checks for any incoming session before scaling down pods.
SCALEDOWN_COUNTER_int	5	AUTOSCALE	The delay counter for checking any incoming session before scaling down pods.
SCALEDOWN_ENABLED	True	AUTOSCALE	Enabling or Disabling scale down. To enable, set it to True. To disable, set it to False.
SCALEDOWN_HOURS_OF_DAY	1, 2, 3, 4, 5, 6, 7, 8, 9, 10, 11, 12, 13, 14, 15, 16, 17, 18, 19, 20, 21, 22, 23, 24	AUTOSCALE	Value in hours (24 hours) for scale down. If 2 is not set, scale up does not run at 2 AM.
SCALEUP_COUNTER_DELAY	10	AUTOSCALE	Delay between two checks for any incoming session before scaling down pods.
SCALEUP_COUNTER_int	5	AUTOSCALE	Delay counter for checking any incoming session before scaling down pods.
SCALEUP_ENABLED	True	AUTOSCALE	Enabling or Disabling scale up. To enable, set it to True. To disable, set it to False.

Variables	Example Values	Required For	Description
SCALEUP_HOURS_OF_DAY	1, 2, 3, 4, 5, 6, 7, 8, 9, 10, 11, 12, 13, 14, 15, 16, 17, 18, 19, 20, 21, 22, 23, 24	0	Value in hours (24 hours) for scale down. If 2 is not set, scale up does not run at 2 AM.
SCALING_CHECK_INTERVAL	12	AUTOSCALE	Delay between the two checks of scale up and scale down.
SCALING_FREQUENCY	DAILY	AUTOSCALE	The frequency of running autoscale. Valid values are: DAILY, WEEKDAYS, OR WEEKENDS.
SERVER_GROUPS	interact	AUTOSCALE	The server groups to be monitored. If you deploy Interact and InteractATM, the value should be as follows: SERVER_GROUPS: interact, interactatm.
SyncTimePyPod	30	INTERACTURL	The gap between the check of registration and deletion of Interact URL.
Unica_Deployment	{{ .Release.Name }}-{{ incl udeunica.name . }}	AUTOSCALE / HYBRIDINTERACT / INTERACTURL	Name of the release deployment. Example: If your Interact deployment name hcl-unica-interact , the release deployment name is hcl-unica .
Deployment	hcl-unica-interact	HYBRIDINTERACT	Deployment name for Hybrid.
file_Handle	/ docker/unica/logs/file-patt ern	HYBRIDINTERACT	The filename to capture the pod name. If the helper is deleted or recreated, it captures pod name from the file.
CHANNELNAME_list	intractatm	HYBRIDINTERACT	The channel name.
REDIS_CONFIGURED	True	HYBRIDINTERACT	If Redis is configured, set to True. If Redis is not configured, set to False.

Scaling Journey engine containers

In Kubernetes, Journey engine are defined as StatefulSets.

Each Pod in a StatefulSet derives its hostname from:

- the name of the StatefulSet, and
- the ordinal of the Pod.

The service manages the Pod domain and the format is as follows:

```
$(service name).$(namespace).svc.cluster.local
```

Example:

The Journey engine pod is registered in the following format:

```
journey-0.listener.default.svc.cluster.local
```

In the Helm chart, you can configure these pods in the `journey-configMap.yaml` file.

Like a Deployment, a StatefulSet manages the Pods that are based on identical container specifications.

Unlike a Deployment, a StatefulSet maintains a sticky identity for each of their Pods.

The location of Journey Engine shared home is `$HOME_DIR/Journey/Engine`.

For the scaled instances of StatefulSet, `journey-0`, `journey-1`, `journey-2`,...`journey-n`, each instance has a file system mapped on the mount location.

Example:

```
$HOME_DIR/Journey/journey-0
```

In a Journey engine, by default, clustering is enabled. As soon as the engine starts, it creates `journey-0`, which is a copy of the engine folder. As you keep scaling the Journey engine, it creates folders named `journey-0`, `journey-1`, `journey-2`,...`journey-n`.

The logs for each pod will also be generated as `journey-0`, `journey-1`, `journey-2`,...`journey-n`.

Chapter 9. Using Red Hat OpenShift

You can use OpenShift to develop and run containerized applications. OpenShift allows applications, and the data centers that support them, to expand from just a few machines and applications to thousands of machines that serve millions of clients.

About this task

For detailed information related to Red Hat OpenShift Container Platform, see [OpenShift Container Platform documentation](#).

The benefits of using OpenShift Container Platform are as follows:

- OpenShift provides its own curated Helm charts optimized for its ecosystem. Additionally, OpenShift can also use standard Kubernetes Helm charts but may require customizations due to OpenShift-specific security policies and platform features.
- Easy to manage and monitor using the OpenShift console.

To configure the changes required for Unica, complete the following steps:

1. Place the following items on a location that is accessible from the listener pod:

- `unixodbc`
- `libltdl.so.7`
- `libltdl.so.7.30`
- `mariadb driver` (must be installed and then copied to the required location)

Update the same in `campaign-configmap.yaml` file:

```
export ODBCINI=<driver-path>/etc/odbc.ini
export ODBCINST=<driver-path>/etc/odbcinst.ini
export ODBCSYSINI=<driver-path>/odbc1/etc
```



Note: `<driver-path>` is the path where you have copied the driver. For example, `/docker/unica/odbc1`.

2. In the `campaign-configmap.yaml` file, update the namespace for listener domain name.
3. Based on your setup, you can:

Choose from:

- update the `PVC.yaml` file before using it.
- avoid the `PVC.yaml` file.

Security Context Constraints for Unica on Red Hat OpenShift

For any Security Context Constraint (SCC), perform the following steps:

1. If `AllowPrivilegedContainer` is enabled (set to `TRUE`) or not enabled, set it to `FALSE`.
2. Do not assign root access to the users specified in the `deployment.yaml` file.

3. For pods that do not have a `gid` (group ID), perform the following configuration:

```
securityContext:
  runAsUser: 1000610000
```

The configuration ensures that the start user of the pods is `1000610000`. The `1000610000` user cannot switch to the `root` user or change the `root` user password.

4. For the Oracle client, in the listener pod, create a user for a valid group and perform the following configurations:

```
securityContext as :
  securityContext:
    runAsUser: 1000
    runAsGroup: 1001

oracle:x:1000:1000::/home/oracle:/bin/bash
dba:x:1001:oracle
1000=oracle and 1001 = dba group
```

The configuration ensures that the Oracle user also cannot switch to the `root` user or change the `root` user password.

5. For the SCC (`anyuid`), configure the following values:

```
allowHostDirVolumePlugin: false
allowHostIPC: false
allowHostNetwork: false
allowHostPID: false
allowHostPorts: false
allowPrivilegeEscalation: true
allowPrivilegedContainer: false
allowedCapabilities: null
apiVersion: security.openshift.io/v1
defaultAddCapabilities: null
fsGroup:
  type: RunAsAny
groups:
- system:cluster-admins
kind: SecurityContextConstraints
metadata:
  annotations:
    kubernetes.io/description: anyuid provides all features of the restricted SCC
    but allows users to run with any UID and any GID.
    release.openshift.io/create-only: "true"
  creationTimestamp: "2020-08-24T17:55:03Z"
  generation: 6
  name: anyuid
  resourceVersion: "23505934"
  selfLink: /apis/security.openshift.io/v1/securitycontextconstraints/anyuid
  uid: 43877aab-c522-4ca9-9575-e8b212749e29
priority: 10
readOnlyRootFilesystem: false
requiredDropCapabilities:
- MKNOD
runAsUser:
  type: RunAsAny
seLinuxContext:
  type: MustRunAs
supplementalGroups:
  type: RunAsAny
```

```
users:
- system:serviceaccount:unica:default
volumes:
- configMap
- downwardAPI
- emptyDir
- persistentVolumeClaim
- projected
- secret
```

6. For the listener pod, remove all `chmod` or `su`.
7. In the listener `rc.unica_ac`, remove the root user `check` and change it to `oracle`.
8. In the Journey configmap, update the namespace from `default` to `unica`.

Chapter 10. Deployment monitoring

The Kubernetes Dashboard is a web-based user interface to monitor deployments.


Use the Kubernetes Dashboard to:

- deploy containerized applications to a Kubernetes cluster
- troubleshoot your containerized applications
- managing cluster resources

You can also use the Dashboard to get an overview of the applications running on your cluster, as well as for creating or modifying individual Kubernetes resources.

The Dashboard also provides information on the state of Kubernetes resources in your cluster and on any errors that may have occurred.

Figure 1. Kubernetes dashboard



Deploying the dashboard user interface

The Dashboard user interface is not deployed by default.

To deploy the Dashboard user interface, run the following command.

```
kubectl apply -f https://raw.githubusercontent.com/kubernetes/dashboard/v2.0.0-beta4/aio/deploy/recommended.yaml
```

Chapter 11. Product utilities

You can execute all the utilities of the Unica products in their assigned pods.

The following table lists the Unica products and their assigned pods for running the product-specific utilities.

Table 2. Unica products and their assigned pods for running the utilities

Unica Product Name	Pod Name
Unica Campaign	Listener
Unica Platform	Platform
Unica Plan	Plan

Chapter 12. Using secret to avoid passwords in plain text

To use a secret to avoid using passwords in plain text, complete the following steps:

1. On a Linux virtual machine, run the following command:

```
echo -n 'unica*03' | base64
```

Result

You will see the following output: "dW5pY2EqMDM="

2. Create a `YAML` file (example `unicadbSecret.yaml`) and in the `YAML` file add the following parameters:

```
apiVersion: v1
kind: Secret
metadata:
  name: unica-db-token
  type: Opaque
data:
  PLATFORM_DATABASE_PASSWORD: "dW5pY2EqMDM="
```

3. To use the password in Unica Platform, update the Platform deployment, and wherever `envFrom` exists, add the the following code:

```
envFrom:
- secretRef:
  name: unica-db-token
- configMapRef:
```

4. Either comment or delete the parameter `PLATFORM_DATABASE_PASSWORD: unica*03` from the `platform-configMap.yaml` file.

What to do next



Note:

- The same `unicadbSecret.yaml` can be used for multiple Unica product database passwords. Repeat *Step 3* and *Step 4* for each products deployment and their respectiv `configmap.yaml` file. For example, in case of Unica Plan, with `PLAN_DATABASE_PASSWORD: unica*03`, add the following lines of code

```
apiVersion: v1
kind: Secret
metadata:
  name: unica-db-token
  type: Opaque
data:
  PLATFORM_DATABASE_PASSWORD: "dW5pY2EqMDM="
  PLAN_DATABASE_PASSWORD: "dW5pY2EqMDM="
```

In this case, update the Plan deployment and `configmap.yaml` file.

- Limit the secret size to 1 MB. If the secret size is more than 1 MB, split it into multiple tokens.

Chapter 13. Using AWS Secrets and Configuration Provider with Kubernetes Secret Store CSI Driver


AWS Secrets Manager securely retrieves secrets from the AWS Secrets Manager for Amazon Elastic Kubernetes Service (Amazon EKS) Kubernetes pods.

AWS Secrets and Config Provider (ASCP) contains an easy-to-use plugin that provides secrets to applications that operate on Amazon EKS. The plugin supports industry-standard Kubernetes Secrets Store and Container Storage Interface (CSI) driver.

The benefits of ASCP are as follows:

- Provides compatibility for legacy Kubernetes workloads that fetched secrets through the file system or `etcd`.
- Securely store and manage your secrets in Secrets Manager.
- Retrieve secrets, using applications that run on Kubernetes, without writing a custom code.
- Use AWS Identity and Access Management (IAM) and resource policies on your secret to limit and restrict access to specific Kubernetes pods inside a cluster to tightly control secrets accessible by the pods.

AWS Secrets Manager Working Concept with Unica



AWS Secret Manager Implementation

To implement AWS Secret Manager, ensure that the prerequisites are met and the configurations are executed.

For more details, see the following topics:

- [Prerequisite Software for AWS Secret Manager on page 50](#)
- [Prerequisite Configurations for AWS Secret Manager on page 50](#)
- [Implementing AWS Secret Manager on page 51](#)

Prerequisite Software for AWS Secret Manager

The prerequisite software requirement for AWS Secret Manager are as follows:

- An AWS account
- AWS Command Line Interface installed
- `kubectl` installed
- Helm installed
- `eksctl` installed
- An existing EKS cluster

Prerequisite Configurations for AWS Secret Manager

Before implementing AWS Secret Manager, make the following configurations:

- An IAM policy, with permissions to retrieve secrets from Secret Manager.
- Your secret stored in Secrets Manager, for example `platsecret`, `campsecret`, and `plansecret` with keys `PLATFORM_DATABASE_PASSWORD`, `CAMPAIGN_DATABASE_PASSWORD`, and `PLAN_DATABASE_PASSWORD`:
 - keys should match the `configMap` entries
 - encryption key value must be `aws/secretsmanager`
- A `user` or `iamserviceaccount` that can modify your Kubernetes cluster.
- To the Docker registry, push the new set of images.
- To use the new image tags, update the `values.yaml` file.
- In the Helm chart, comment out the following `_PASSWORD` parameters from the `configMap.yaml` files:
 - `CAMPAIGN_DATABASE_PASSWORD`
 - `PLAN_DATABASE_PASSWORD`
 - `PLATFORM_DATABASE_PASSWORD`
- In the `common-configMap.yaml` file, add the following parameter:


```
TOMCAT_FACTORY: "com.unica.manager.tomcat.utils.TomcatDSFactory"
```
- Create secrets for the following Unica products with the corresponding names:

Unica Product	Secret name
Unica Campaign	<code>campsecret</code>
Unica Plan	<code>plansecret</code>
Unica Platform	<code>platsecret</code>

- Update the secret arn, secret name, and key in the following files (see the example for reference):

◦ values.yaml

```
awssecrets:
  secrets:
    iamserviceaccountforawssecretmanager: "suite-unicall1"
    kubernetessecret: "application-api-key"
  platsecret:
    platformdatabasepassword: "PLATFORM_DATABASE_PASSWORD"
    secretsmanagerarnplat: "arn:aws:secretsmanager:ap-south-1:385481138434:secret:platsecret1-7dBQks"
```

◦ deployment.yaml

```
- name: {{ .Values.image.awssecrets.platsecret.platformdatabasepassword }}
  valueFrom:
    secretKeyRef:
      name: {{ .Values.image.awssecrets.secrets.kubernetessecret }}
      key: {{ .Values.image.awssecrets.platsecret.platformdatabasepassword }}
```

Implementing AWS Secret Manager

To implement AWS Secret Manager on your setup, complete the following steps:

1. Using a command line interface, restrict access to your pods using IAM roles for service accounts. Alternatively, you can also restrict access using a console.
2. To turn on Open ID Connect (OIDC), run the following eksctl command:

```
eksctl utils associate-iam-oidc-provider --region=<REGION> --cluster=<CLUSTERNAME> --approve
```



Note:

- You must run the earlier mentioned command only once.
 - In the command, mentioned earlier, replace <REGION> and <CLUSTERNAME> with relevant and appropriate values.
3. For retrieving secrets from AWS Secret Manager, create a policy by running the following command:

```
aws iam create-policy --policy-name <my-policy> --policy-document file://policy
```

A sample policy file follows:

```
{
  "Version": "2012-10-17",
  "Statement": [
    {
      "Effect": "Allow",
      "Action": [
        "secretsmanager:GetResourcePolicy",
        "secretsmanager:GetSecretValue",
        "secretsmanager:DescribeSecret",
        "secretsmanager:ListSecretVersionIds"
      ],
      "Resource": "arn:aws:secretsmanager:ap-south-1:385481138434:secret:*"
    }
  ],
  {
```

```

    "Effect": "Allow",
    "Action": "secretsmanager:ListSecrets",
    "Resource": "*"
  }
]
}

```

4. Create a service account role to associate the policy (created in *Step 2*) with your service account. To create a service account, run the following command:

```
eksctl create iamserviceaccount --name <SERVICE_ACCOUNT_NAME> --namespace <NAMESPACE> --cluster
<CLUSTERNAME> --attach-policy-arn <IAM_policy_ARN> --approve --override-existing-serviceaccounts
```



Note: In the command, mentioned earlier, replace <NAMESPACE>, <CLUSTERNAME>, <IAM_policy_ARN>, and <SERVICE_ACCOUNT_NAME> with relevant and appropriate values.

5. To install the Kubernetes secrets store CSI driver, using helm with `syncSecret.enabled=true`, run the following commands:

- a. Run the following command:

```
helm repo add secrets-store-csi-driver
https://kubernetes-sigs.github.io/secrets-store-csi-driver/charts
```

- b. If you do not require a periodical pull of updated secrets, initialize the driver by running the following command:

```
helm install csi-secrets-store secrets-store-csi-driver/secrets-store-csi-driver --set
syncSecret.enabled=true --namespace kube-system
```

- c. If you want to turn on automated rotation for the driver, using the rotation reconciler feature which is currently in alpha, run the following command:

```
helm -n kube-system install csi-secrets-store secrets-store-csi-driver/secrets-store-csi-driver
--set enableSecretRotation=true --set rotationPollInterval=3600s
```



Note: You can adjust the rotation intervals, as per your requirements, to find an appropriate balance between API call cost consideration and rotation frequency

6. To install the ASCP, run the following command:

```
kubectl apply -f
https://raw.githubusercontent.com/aws/secrets-store-csi-driver-provider-aws/main/deployment/aws-provid
er-installer.yaml
```

7. Create the custom resource **SecretProviderClass** and deploy it to sync with AWS secret with Kubernetes. For details, access the `spc.yaml` inside the Unica helm chart.

```

5 spec:
6   provider: aws
7   secretObjects:
8     - secretName: {{ .Values.image.awssecrets.secrets.kubernetessecret }} # the k8s secret name
9       type: Opaque
10      data:
11        - objectName: key1 # reference the corresponding parameter
12          key: {{ .Values.image.awssecrets.platsecret.platformdatabasepassword }}
13  parameters:
14    objects: |
15      - objectName: {{ .Values.image.awssecrets.platsecret.secretsmanagerarnplat }}
16        jmesPath:
17          - path: {{ .Values.image.awssecrets.platsecret.platformdatabasepassword }}
18            objectAlias: key1

```

8. Configure and deploy the pods to mount the volumes based on the configured secrets.

```

volumeMounts:
- name: volume-mount
  mountPath: /docker/unica
- name: api-secret
  mountPath: "/mnt/secrets-store"
  readOnly: true

```

```

1 spec:
2   volumes:
3     - name: volume-mount
4       {{- if .Values.persistence.enabled }}
5       persistentVolumeClaim:
6         {{- if .Values.persistence.existingClaim }}
7         claimName: {{ .Values.persistence.existingClaim }}
8         {{- else }}
9         claimName: {{ include "unica.fullname" . }}
10        {{- end }}
11      {{- else }}
12      emptyDir: {}
13      {{- end }}
14     - name: api-secret
15       csi:
16         driver: secrets-store.csi.k8s.io
17         readOnly: true
18         volumeAttributes:
19           secretProviderClass: "aws-secrets"

```

9. In the `rbac.yaml` file, assign the **ClusterRoleBinding** permissions to the `iamservice` account, created in *Step 3*, for internal Kubernetes communication.

```
36 subjects:
37   - name: {{ include "unica.fullname" . }}
38     namespace: {{ .Release.Namespace | quote }}
39     kind: ServiceAccount
40   - name: {{ .Values.image.awssecrets.secrets.iamserviceaccountforawssecretmanager }}
41     namespace: {{ .Release.Namespace | quote }}
42     kind: ServiceAccount
43 {{- end -}}
```

Chapter 14. Enabling Multicast using Weave-Net CNI plugin on AWS EKS cluster

You can enable multicasting on AWS EKS cluster only for Kubernetes versions 1.21 or above,

Before you begin

- Create a role on AWS having the necessary privileges for creating AWS clusters (example: `AWS_EKS_CLUSTER_ROLE`).
- Create a minimum of two subnets within the VPC. You must create the cluster within this VPC.

About this task

To enable multicasting on AWS EKS cluster using Weave-Net CNI plugin, complete the following steps:

1. Use the AWS CLI and create an EKS cluster without any node group.



Note: Multicasting will not work if you create clusters using AWS web console.

Sample Command:

```
aws eks create-cluster --region <region-name> --name <cluster-name> --kubernetes-version 1.21 --role-arn <full-arn-of-the-role> --resources-vpc-config subnetIds=<subnet-id1>,<subnet-id2>,...<subnet-idn>
```

2. Run the following command to delete the aws-node default daemon-set:

```
kubectl delete ds aws-node -n kube-system
```

Result

This disables the default vpc-cni plugin.

3. Confirm if your security group allows TCP port `6783` and UDP ports `6783` and `6784`. If your security group does not allow these ports, add the necessary firewall rules to your security groups to allow these ports.
4. Run the following command to delete the `kube-proxy` ds:

```
kubectl delete ds kube-proxy -n kube-system
```

5. Run the following command to create an add-on for Kube-proxy:

```
aws eks create-addon --cluster-name <your-cluster-name> --addon-name kube-proxy --resolve-conflicts OVERWRITE
```

Result

This will add the latest kube-proxy add-on to the cluster, based on the Kubernetes cluster version.

6. Run the following command to apply weave-net daemset:

```
kubectl apply -f "https://cloud.weave.works/k8s/net?k8s-version=$(kubectl version | base64 | tr -d '\n')"
```

7. Verify the Daemon sets on cluster. There should be two daemon sets for Weave and correspondingly two Kube-proxy daemon sets.
8. Add the node group to the Cluster and wait till the nodes are created and all the required nodes are ready.
9. Deploy the Unica product and verify the Multicasting.

Chapter 15. Uninstalling the chart

1. To uninstall or delete the `my-release` deployment, run the following command:

```
helm delete --purge <releasename>
```

2. Delete the persistent volumes.
3. Delete the file systems.

What to do next

If required, clean the persisted data of the database.