

**Unica Platform V 12.0
Administrator's Guide**



Contents

- Chapter 1. Unica Platform Administrator Guide..... 1**
- Unica Platform features..... 1
 - About Unica Platform security features..... 1
 - Configuration management..... 4
 - Localization in Unica..... 4
 - The common user interface..... 5
 - Logging in to Unica..... 5
 - Unica Platform documentation and help..... 7
- Unica user account management..... 8
 - Types of user accounts: internal and external..... 8
 - Properties of internal user accounts..... 9
 - Adding internal user accounts..... 10
 - Deleting internal user accounts..... 10
 - Changing internal user password expiration dates..... 11
 - Resetting internal user passwords..... 11
 - Changing internal user account properties..... 12
 - Changing internal user system status..... 12
 - Adding internal user data sources..... 13
 - Changing internal user data sources..... 13
 - Deleting internal user data sources..... 13
 - The user management pages..... 14
 - Locale preference..... 17
 - Synchronization of external users..... 18

Security management.....	19
Permissions and tasks of the security administrator in Unica Platform.....	20
Special characters in role and policy names.....	20
Roles and permissions in Unica Platform and Unica Campaign.....	21
Overview of managing user application access in Unica Platform.....	22
Types of groups: internal and external.....	22
Partitions and security management.....	23
Pre-configured users and roles.....	24
Cross-partition administration privileges.....	26
Adding an internal group.....	27
Adding a subgroup.....	27
Deleting a group or subgroup.....	28
Changing a group or subgroup description.....	28
Assigning a group to a partition.....	29
Adding a user to a group or subgroup.....	29
Removing a user from a group or subgroup.....	30
The user group management pages.....	31
Creating a role.....	33
Modifying role permissions.....	33
Removing a role from the system.....	34
Assigning a role to or removing a role from a group.....	34
Assigning a role to or removing a role from a user.....	35
Definitions of permission states.....	35
Permissions for products that use only basic roles.....	36
Permissions for Unica Platform.....	38

Permissions for Opportunity Detect.....	39
Configuration management.....	41
Property categories.....	41
Property descriptions.....	43
The refresh function.....	43
The default user locale preference.....	44
Navigating to a category.....	44
Editing property values.....	45
Creating a category from a template.....	45
Deleting a category.....	46
Dashboard management.....	46
Dashboard planning.....	47
Dashboard audiences.....	47
User permissions required to view dashboards.....	47
Pre-defined portlets.....	48
Pre-assembled dashboards.....	56
IBM® Cognos® report performance considerations.....	59
Dashboard setup.....	61
Quick link portlets.....	68
Custom portlets.....	69
Dashboard membership administration.....	76
The Unica Scheduler.....	77
Scheduler triggers that are sent on success or failure of runs.....	79
Schedules that depend on completion of multiple runs.....	80
Schedule triggers that are sent from an external script.....	81

Scheduler recurrence patterns.....	83
Time zone support.....	83
Scheduler throttling.....	84
Whitelist prerequisite for external tasks (with FixPack 10.0.0.1 only).....	86
Best practices for setting up schedules.....	88
To create a schedule wizard.....	89
Run exclusions.....	95
What to consider when you use the scheduler with Unica Campaign.....	101
Schedule notifications.....	106
Schedule management.....	109
SAML 2.0 based federated authentication.....	118
How to implement federated authentication.....	121
Related concepts.....	133
SAML 2.0 single sign-on.....	134
Behavior when SAML 2.0 single sign-on is implemented.....	135
Configuration process roadmap: SAML 2.0 single sign-on.....	136
Setting up the metadata file.....	137
Setting SAML 2.0 configuration properties.....	137
Setting up a data source for SAML single sign-on.....	138
Sample SAML 2.0 IdP assertion.....	138
Sample IdP metadata.....	143
Configuring JWT authentication between applications.....	146
Single sign-on between Unica and IBM Digital Analytics.....	147
Setting up single sign-on between Unica and Digital Analytics using automatic user account creation.....	149

Setting up single sign-on between Unica and Digital Analytics using manual user account creation.....	151
Configuring WebLogic for single sign-on between Digital Analytics and Unica....	153
Configuring WebSphere® for single sign-on between Digital Analytics and Unica.....	153
Digital Analytics integration with Websense using a custom proxy.....	154
Integration between Unica and Windows™ Active Directory.....	158
Active Directory integration features.....	158
Active Directory integration prerequisites.....	162
Configuration process roadmap: Active Directory integration.....	162
Integration between Unica and LDAP servers.....	173
LDAP integration features.....	173
LDAP integration prerequisites.....	177
Configuration process roadmap: LDAP integration.....	177
Integration with web access control platforms.....	188
About context roots.....	189
SiteMinder integration prerequisites.....	190
IBM Security Access Manager integration prerequisites.....	194
Configuration process roadmap: integrating Unica with a web access control system.....	200
Configuring integration with an SSL type of WebSEAL junction.....	203
Alert and notification management.....	204
Alert and notification subscriptions.....	205
Configuring email notifications in Unica.....	205
Implementation of one-way SSL.....	206
Overview of SSL certificates.....	207

Client and server roles in Unica.....	208
SSL in Unica.....	210
Configuration process roadmap: implementing SSL in Unica.....	211
Certificates for SSL.....	211
Configure your web application servers for SSL.....	220
Configure HCL Unica for SSL.....	222
Verifying your SSL configuration.....	235
Useful links for SSL.....	236
Quality of protection (QoP) settings for WebLogic.....	236
Quality of protection (QoP) settings for WebSphere.....	236
Security framework for Unica APIs.....	237
Data filter creation and management.....	241
Overview of data filter creation.....	241
Configuration process roadmap: creating data filters.....	244
Data filter XML reference.....	250
Example: Manually specifying data filters.....	260
Example: Automatically generating a set of data filters.....	268
About assigning users and groups in the XML.....	278
About assigning user and groups though the user interface.....	288
Adding data filters after the initial set has been created.....	291
Audit event tracking in Unica.....	291
Limitations on audit event tracking.....	292
Legacy audit events.....	292
Retroactive changes.....	293

Permissions for viewing the Audit Events report in a multi-partition environment.....	293
Enabling and disabling event auditing.....	294
Configuring which audit events appear in the report.....	294
Modifying the audit report content and display.....	295
Fields in the Report Parameters window.....	296
Fields and buttons in the Audit Events report.....	297
Archived audit events.....	299
Configuring audit backup notifications.....	299
Exporting the Audit Events report.....	300
Optimizing the export of the Audit Events report for large event volumes.....	301
The Unica Platform system log.....	301
System log configuration.....	302
Enabling single-user logging.....	305
Unica Platform utilities.....	308
Setting up Unica Platform utilities on additional machines.....	311
Unica Platform utilities.....	312
Unica Platform SQL scripts.....	332
Unica configuration properties.....	336
Unica Platform configuration properties.....	336
Digital Analytics configuration properties.....	418
Report configuration properties.....	419
Unica Plan configuration properties.....	453
Unica Campaign configuration properties.....	512
IBM eMessage configuration properties.....	740

Unica Interact configuration properties.....	750
Unica Optimize configuration properties.....	907
Unica Collaborate configuration properties.....	928
IBM SPSS Modeler Advantage Enterprise Marketing Management Edition configuration properties.....	972
Opportunity Detect and Unica Interact Advanced Patterns configuration properties.....	976
Customization of stylesheets and images in the Unica user interface.....	984
Preparing your corporate theme.....	985
Applying your corporate theme.....	985
Adding internal user accounts.....	986
Deleting internal user accounts.....	986
Changing internal user password expiration dates.....	987
Resetting internal user passwords.....	987
Adding internal user data sources.....	988
Changing internal user account properties.....	988
Changing internal user system status.....	988
Deleting internal user data sources.....	989
The user management pages.....	989
Resetting internal user passwords.....	993
Changing internal user data sources.....	993
Locale preference.....	994
The default user locale preference.....	994
restoreAccess.....	995
Cross-partition administration privileges.....	997
Types of groups: internal and external.....	998

Partitions and security management.....	999
Pre-configured users and roles.....	1000
Overview of managing user application access in Unica Platform.....	1002
Adding an internal group.....	1002
Adding a subgroup.....	1003
Deleting a group or subgroup.....	1004
Assigning a group to a partition.....	1004
Adding a user to a group or subgroup.....	1004
Removing a user from a group or subgroup.....	1005
Changing a group or subgroup description.....	1006
The user group management pages.....	1006
Creating a role.....	1008
Modifying role permissions.....	1009
Removing a role from the system.....	1009
Assigning a role to or removing a role from a group.....	1010
Assigning a role to or removing a role from a user.....	1010
Definitions of permission states.....	1011
Permissions for products that use only basic roles.....	1011
Permissions for Unica Platform.....	1013
Permissions for Opportunity Detect.....	1014
Unica configuration properties.....	1016
Configuration management.....	1016
Templates for duplicating categories.....	1016
Category naming restrictions.....	1017
Creating a category from a template.....	1017

Navigating to a category.....	1018
Editing property values.....	1018
Templates for duplicating categories.....	1019
Category naming restrictions.....	1019
Assigning or changing a dashboard administrator.....	1020
The dashboard administrator.....	1020
Pre-defined portlets.....	1020
Custom portlet types and availability.....	1021
Adding a pre-defined portlet to a dashboard.....	1021
Adding a custom portlet to a dashboard.....	1022
Scheduling a dashboard report.....	1023
Adding a pre-defined portlet to a dashboard.....	1024
Dashboards and partitions.....	1024
Partitions and security management.....	1025
Dashboard management.....	1026
Custom portlets.....	1026
Enabling or disabling pre-defined portlets.....	1026
Creating a pre-assembled dashboard.....	1027
Single sign-on between Unica and IBM Digital Analytics.....	1027
Implementation of one-way SSL.....	1029
Preparing the URL from a Digital Analytics report.....	1029
The Create Custom Portlet page.....	1030
Dynamic tokens.....	1031
The dashboard administrator.....	1031
Granting or removing dashboard membership.....	1032

Adding a pre-defined portlet to a dashboard.....	1032
The Manage Portlets page.....	1033
Dashboards and partitions.....	1033
Enabling or disabling pre-defined portlets.....	1034
Creating a dashboard that is not pre-assembled.....	1034
Creating a pre-assembled dashboard.....	1035
Overview of working with dashboards in a multi-partition environment.....	1035
Quick link portlets.....	1036
Creating a quick link portlet.....	1037
Preparing the URL from a Digital Analytics for On Premises report.....	1038
Preparing the URL from an IBM® Cognos® dashboard report.....	1039
Preparing the URL from a Digital Analytics report.....	1039
Adding a custom portlet to a dashboard.....	1040
Overview of the portlet creation process.....	1041
Scheduling a dashboard report.....	1042
Preparing the URL from an IBM® Cognos® dashboard report.....	1042
Difference between the Unica Campaign Schedule process and Unica Scheduler....	1043
The Unica Scheduler.....	1044
Schedule triggers that are sent from an external script.....	1045
scheduler_console_client.....	1046
Scheduler throttling.....	1049
Setting up throttling for the Unica Scheduler.....	1050
Whitelist prerequisite for external tasks (with FixPack 10.0.0.1 only).....	1051
Adding an API to the whitelist.....	1051
Adding a script to the whitelist.....	1052

Time zone support.....	1053
Schedules that depend on completion of multiple runs.....	1054
To create a schedule wizard.....	1055
Schedule management.....	1061
The Schedule management pages.....	1062
scheduler_console_client.....	1069
Schedule triggers that are sent from an external script.....	1072
Creating a category from a template.....	1073
Setting up throttling for the Unica Scheduler.....	1074
SAML 2.0 single sign-on.....	1074
Setting SAML 2.0 configuration properties.....	1076
Platform Security Login method details SAML 2.0.....	1076
Setting configuration properties on the Configuration page.....	1082
Platform Security Federated authentication.....	1083
Platform Security Federated authentication partitions partition[n].....	1084
Configuring JWT authentication between applications.....	1084
Platform Security JWT authentication.....	1085
Setting up single sign-on between Unica and Digital Analytics using manual user account creation.....	1086
Configuring WebLogic for single sign-on between Digital Analytics and Unica.....	1089
Configuring WebSphere® for single sign-on between Digital Analytics and Unica....	1089
Next steps.....	1090
Campaign partitions partition[n] Coremetrics.....	1090
Setting up single sign-on between Unica and Digital Analytics using automatic user account creation.....	1093

Setting up single sign-on between Unica and Digital Analytics using manual user account creation.....	1095
Digital Analytics configuration properties.....	1097
About Distinguished Names.....	1098
Obtaining required information.....	1098
Configuration process roadmap: Active Directory integration.....	1100
The user management pages.....	1101
Active Directory integration features.....	1105
Forcing synchronization of external users.....	1108
LDAP integration features.....	1109
Storing directory server credentials in Unica Platform.....	1112
Unica Platform Security Login method details LDAP.....	1114
Setting LDAP login method connection properties in Unica.....	1118
Setting LDAP synchronization properties.....	1119
Platform Security LDAP synchronization.....	1120
Setting user attributes map properties.....	1132
Configuration process roadmap: LDAP integration.....	1134
Platform Security LDAP synchronization LDAP reference to Unica Platform group map.....	1135
Mapping LDAP groups to Unica groups.....	1136
Adding an internal group.....	1137
Assigning a role to or removing a role from a group.....	1138
Adding a user to a group or subgroup.....	1138
Setting up an Active Directory user with PlatformAdminRole permissions.....	1139
Platform Security Login method details Web access control.....	1139
Setting the security mode to enable NTLMv2 authentication.....	1140

Platform Security Login method details Web access control.....	1141
HCL Unica General Navigation.....	1142
Setting web access control connection properties in Unica.....	1144
Implementation of one-way SSL.....	1145
Configuring integration with an SSL type of WebSEAL junction.....	1146
Configuring SiteMinder for Unica products.....	1146
Enabling single logouts with SiteMinder.....	1150
Two ways to create data filters: automatic generation and manual specification.....	1150
datafilteringScriptTool.....	1151
ManagerSchema_PurgeDataFiltering.sql.....	1152
Populating the data filter system tables.....	1153
Creating the XML to specify data filters.....	1153
Data filter XML reference.....	1155
Example: Manually specifying data filters.....	1155
Example: Automatically generating a set of data filters.....	1162
Setting required data filter configuration properties.....	1172
Optional configuration property to improve data filter performance.....	1173
HCL Unica General Data filtering.....	1173
Two ways to assign users and groups: in the user interface and in the XML.....	1175
Assigning users and groups to data filters.....	1175
About assigning users and groups in the XML.....	1175
About assigning user and groups though the user interface.....	1185
Optional configuration property to improve data filter performance.....	1186
HCL Unica General Data filtering.....	1186
Schedule notifications.....	1187

Configuring email notifications in Unica.....	1188
Alert and notification management.....	1189
HCL Unica General Communication Email.....	1190
Platform Notifications.....	1192
Configure your web application servers for SSL.....	1193
SSL in Unica.....	1193
Configuring SSL in Unica Platform.....	1194
Configuring SSL in Unica Platform with LDAP integration.....	1195
Configuring SSL in Unica Platform with data filters.....	1196
Security framework for Unica APIs.....	1197
Platform Security API management [Product] (API configuration template).....	1200
Security framework for Unica APIs.....	1202
SAML 2.0 based federated authentication.....	1206
Configuring which audit events appear in the report.....	1209
Platform Audit Events.....	1210
Platform Audit Events Audit events configuration.....	1210
Platform Audit Events Audit events severity configuration.....	1215
Archived audit events.....	1215
Platform Audit Events Audit events configuration.....	1216
Configuring audit backup notifications.....	1220
Configuring which audit events appear in the report.....	1221
Modifying the audit report content and display.....	1221
Fields in the Report Parameters window.....	1223
configTool.....	1223
Configuration management.....	1229

Unica Platform utilities.....	1230
encryptPasswords.....	1233
partitionTool.....	1235
ManagerSchema_DeleteAll.sql.....	1238
SQL scripts for creating system tables.....	1238
populateDb.....	1240
ManagerSchema_DropAll.sql.....	1241
Preparing your corporate theme.....	1242
Applying your corporate theme.....	1242
Index.....	

Chapter 1. Unica Platform Administrator Guide

This guide provides information on how to install and configure HCL Unica.

Unica Platform features

Unica Platform provides security, configuration, notification, and dashboard features for Unica products.

Unica Platform provides a common user interface for Unica products, as well as the infrastructure for the following features.

- Support for reporting in many products in Unica.
- Support for security in applications, including authentication and authorization.
- Configuration management, including setting user locale preferences and an interface for editing configuration properties for some Unica applications.
- A scheduler that enables you to configure a process to run at intervals that you define.
- Dashboard pages that you can configure to include information useful to groups of users who fill various roles within your organization.
- Support and the user interface for alerts and notifications.
- Security audit reports.

About Unica Platform security features

The security features in Unica Platform consist of a central repository and web-based interface where Unica internal users are defined and where users are assigned various levels of access to functions within Unica applications.

Unica applications use the security features of Unica Platform to authenticate users, check user application access rights, and store user database credentials and other necessary credentials.

Security technologies used in Unica Platform

Unica Platform employs industry-standard encryption methods to perform authentication and enforce security across all Unica applications. User and database passwords are protected using a variety of encryption technologies.

Permission management through roles

Unica Platform defines the user's basic access to the functions within most Unica applications. In addition, for Unica Campaign and Unica Platform, you can control a user's access to functions and objects within the application.

You can assign various permissions to roles. You can then manage user permissions in either of the following ways.

- By assigning roles to individual users
- By assigning roles to groups and then making users a member of that group

About Unica Campaign partitions

Unica Platform provides support for partitions in the Unica Campaign family of products. Partitions provide a way to secure the data associated with different groups of users. When you configure Unica Campaign or a related Unica application to operate with multiple partitions, each partition appears to application users as a separate instance of the application, with no indication that other partitions exist on the same system.

About groups

A subgroup inherits the roles assigned to its parents. An administrator can define an unlimited number of groups, and any user can be a member of multiple groups. This makes it easy to create different combinations of roles. For example, a user could be an IBM eMessage administrator and a Unica Campaign user with no administration privileges.

A group can belong to only one partition.

Data source credential management

Both users and administrators can set up the user's data source credentials in advance, so the user is not prompted to provide data source credentials when working with an application that requires access to a data source.

Integration with external user and group management systems

Unica Platform can be configured to integrate with external systems that are used to manage users and resources centrally. These include Windows™ Active Directory Server, other supported LDAP directory servers, and web access control platforms such as Netegrity SiteMinder and IBM® Security Access Manager. This reduces errors, support costs, and the time needed to deploy an application in production.

SAML 2.0 support

Unica Platform supports SAML (Security Assertion Markup Language) 2.0 for the following.

- SAML 2.0 federated authentication, which enables single sign-on access among diverse applications.

You can use federated authentication to implement single sign-on between Unica applications and other applications or third-party applications.

The Unica Platform installation includes the following components that support federated authentication.

- An identity provider server WAR file.
- A client JAR file that you can use with Java™ applications to generate and parse SAML 2.0 assertions. The Java™ products that you integrate with Unica use the assertions to communicate with the identity provider server.
- SAML 2.0 single sign-on

A fully functional SAML 2.0 IdP server is a prerequisite for this integration.

After you set up the required configuration properties and a metadata file, users who attempt to log in through the Unica Platform login page are authenticated through your organization's SAML 2.0 Identity Provider (IdP) server.

Users who are logged in to any application that uses the IdP server for authentication can access HCL HCL UnicaUnica without logging in again.

Data filters

Unica Platform supports configurable data filters that allow you to specify data access restrictions in Unica products. Data filters make it possible to restrict the customer data that an Unica user can view and work with in applications.

Configuration management

The Configuration page provides access to the central configuration properties for Unica applications.

Users with Admin privileges in the Unica Platform can use the Configuration page to do the following.

- Browse configuration properties, which are organized by product into a hierarchy of categories and sub-categories.
- Edit the values of configuration properties.
- Delete some categories (categories that you can delete display a **Delete Category** link on the Settings page).

You can make additional changes on the Configuration page using the configTool utility provided with Unica Platform.

Localization in Unica

Unica Platform supports localization through its character set encoding and by enabling an administrator to set locale preferences for individual users or all users. Users can also set their own locale preferences.

For both internal and external users, you can set locale preferences on a per-user basis or across the applications that support this feature. This preference setting affects the display of language, time, numbers, and dates in Unica applications.

Unica Platform supports UTF-8 as the default character set encoding, which allows users to enter data in any language (for example Chinese or Japanese). However, note that full support for any character set in Unica Platform also depends on the configuration of the following:

- Unica Platform system table database
- The client machines and browsers used to access Unica.

The common user interface

Unica Platform provides a common access point and user interface for Unica applications.

The common interface provides the following features.

- When multiple Unica products are installed, you can navigate between products without launching new windows.
- You can view a listing of the pages that you have recently visited, and navigate back to any of those pages using the **Recent** menu.
- You can set an Unica page as a home page (the first page you see when you log in) and you can return to that page at any time by clicking the Home icon.
- You can access the search function for each installed product using the **Search** field. The context of this search function is the page you are viewing. For example, if you are viewing a list of campaigns within Unica Campaign, a search would take place across campaigns. If you wanted to search for a Unica Plan project, you would perform the search while viewing a list of Unica Plan projects.

Logging in to Unica

Use this procedure to log in to Unica.

You need the following.

- An intranet (network) connection to access your Unica server.
- A supported browser installed on your computer.
- User name and password to sign in to Unica.
- The URL to access Unica on your network.

The URL is:

```
http://host.domain.com:port/unica
```

where

host is the machine where Unica Platform is installed.

domain.com is the domain in which the host machine resides.

port is the port number where the Unica Platform application server is listening.



Note: The following procedure assumes that you are logging in with an account that has Admin access to Unica Platform.

Access the Unica URL using your browser.

- If Unica is configured to integrate with Windows™ Active Directory or with a web access control platform, and you are logged in to that system, you see the default dashboard page. Your login is complete.
- If you see the login screen, log in using the default administrator credentials. In a single-partition environment, use `asm_admin` with `password` as the password. In a multi-partition environment, use `platform_admin` with `password` as the password.

A prompt asks you to change the password. You can enter the existing password, but for good security you should choose a new one.

- If Unica is configured to use SSL, you may be prompted to accept a digital security certificate the first time you sign in. Click **Yes** to accept the certificate.

If your login is successful, Unica displays the default dashboard page.

With the default permissions assigned to Unica Platform administrator accounts, you can administer user accounts and security using the options listed under the **Settings** menu.

To perform the highest level administration tasks for Unica dashboards, you must log in as **platform_admin**.

Unica Platform documentation and help

Unica Platform provides documentation and help for users, administrators, and developers.

Table 1. Get up and running

Task	Documentation
View a list of new features, known issues, and workarounds	<i>Unica Platform Release Notes®</i>
Learn about the structure of the Unica Platform database	<i>Unica Platform System Tables</i>
Install or upgrade Unica Platform and deploy the Unica Platform web application	One of the following guides: <ul style="list-style-type: none"> • <i>Unica Platform Installation Guide</i> • <i>Unica Platform Upgrade Guide</i>
Implement the Cognos® reports provided with Unica	Unica Reports Installation and Configuration Guide

Table 2. Configure and use Unica Platform

Task	Documentation
<ul style="list-style-type: none"> • Adjust configuration and security settings for products • Integrate with external systems such as LDAP and web access control • Implement single sign-on with diverse applications using SAML 2.0-based federated authentication or single sign-on • Run utilities to perform maintenance on products 	<i>Unica Platform Administrator's Guide</i>

Table 2. Configure and use Unica Platform (continued)

Task	Documentation
<ul style="list-style-type: none"> • Configure and use audit event tracking • Schedule runs of Unica objects 	

Unica user account management

You can manage the attributes of user accounts created using Unica Platform user interface, which we refer to as internal accounts. This is in contrast to external user accounts, which are imported from an external system such as an LDAP server or web access control system.

External accounts are managed in the external system.

Types of user accounts: internal and external

When Unica is integrated with an external server (such as a supported LDAP server or a web access control system), it supports two types of user accounts: internal and external.

- **Internal** - User accounts that are created within Unica using the security user interface. These users are authenticated through Unica.
- **External** - User accounts that are imported into Unica through synchronization with an external server. This synchronization occurs only if Unica has been configured to integrate with the external server. These users are authenticated through the external server. Examples of external servers are LDAP and web access control servers.

Depending on your configuration, you might have only internal users, only external users, or a combination of both. If you integrate Unica with Windows™ Active Directory and enable LDAP, you can have only external users.

For more information about integrating Unica with an LDAP or Windows™ Active Directory server, see the relevant sections in this guide.

Management of external users

Usually, the attributes of external user accounts are managed through the external system. Within Unica, you can control the following aspects of an external user account: data sources, notification preferences, locale preference for Unica applications, and membership in internal groups (but not external groups).

Identifying internal and external users in the Unica interface

In the Users section of Unica, internal and external users have different icons, as follows.

- Internal - 
- External - 

Properties of internal user accounts

Administrators can manage the properties of user accounts that have been created using the Unica Platform user interface.

When a user forgets a password

Unica Platform stores internal user passwords in hashed form, and these stored passwords cannot be restored to clear text. You must assign a new password for users with an internal account who forget their password.

Resetting a password

Users with internal accounts can change their own passwords by providing the original password and entering and confirming the new password. The Unica administrator can also reset any user password as needed.

Password expiration dates

You can set password expiration intervals for all users on the Configuration page. You can also set expiration dates on a per-user basis for users (when the system-wide expiration date is not set to never expire).

System status of user accounts

The system status of a user is either active or disabled. A user with a disabled account cannot log in to any Unica application. If a disabled user account was formerly active, with membership in one or more groups, you can make the account active again. When you make a disabled user account active the group memberships are retained.

Alternate login

You can specify an alternate login for any user account. An alternate login is typically required when the Unica Campaign listener runs as root on a UNIX™-type system.

Data sources

A user needs appropriate credentials to access the data sources used by some Unica applications. You can enter these credentials as a data source in the user account properties.

When a user is working in an Unica application such as Unica Campaign and is prompted for data source information, the Unica application stores this information in Unica Platform data store. These data sources appear in the data source list for the user in Unica Platform even though they were not created using the Unica interface.

Adding internal user accounts

Use this procedure to add internal user accounts.

1. Click **Settings > Users**.
2. Click **New user**.
3. Complete the form and click **Save changes**.

Use caution if you employ special characters in login names. Allowed special characters are listed in the New user page reference.

4. Click **OK**.

The new user name appears in the list.

Deleting internal user accounts

Use this procedure to delete internal user accounts.



Important: If Unica Campaign permissions are set up in a way that restricts ownership or access to a Unica Campaign object to a single user, deleting the account of that user makes the object inaccessible. Instead, you should disable rather than delete such accounts.

1. Click **Settings > Users**.
2. Click the user name of the account you want to delete.
3. Click **OK**.

Changing internal user password expiration dates

Use this procedure to change password expiration dates for internal users.



Restriction: If the system-wide password expiration property **General | Password settings | Validity (in days)** is set to zero, you cannot change the password expiration date of any internal user.

1. Click **Settings > Users**.
2. Click the user name.
3. Click the **Edit properties** link at the bottom of the page.
4. Change the date in the **Password expiration** field.
5. Click **OK**.

Resetting internal user passwords

Use this procedure to reset internal user passwords.

1. Click **Settings > Users**.

The **Users** list is displayed in the left pane.

2. Click the user name you want to change.
3. Click the **Reset password** link at the bottom of the page.
4. Enter the new password in the **Password** field.
5. Enter the same password in the **Confirm** field.
6. Click **Save changes** to save your changes.
7. Click **OK**.



Note: When user passwords are reset, users are prompted to change their password the next time they log in to an Unica application.

Changing internal user account properties

Use this procedure to change the properties of internal user account.

1. Click **Settings > Users**.
2. Click the name of the account you want to change.
3. Click the **Edit properties** link at the bottom of the page.
4. Edit the fields as needed.
5. Click **Save changes** to save your changes.
6. Click **OK**.

Changing internal user system status

Use this procedure to change the system status of internal users.

1. Click **Settings > Users**.
2. Click the name of the account you want to change.
3. Click the **Edit properties** link at the bottom of the page.
4. Select the status in the **Status** drop-down list. The options are **ACTIVE** and **DISABLED**.



Note: If you select **DISABLED**, the user will no longer be able to log in to any Unica applications. Users with Admin access to Unica Platform cannot disable themselves.

5. Click **Save changes** to save your changes.
6. Click **OK**.

Adding internal user data sources

Use this procedure to add data sources for internal users.

1. Click **Settings > Users**.
2. Click the name of the account you want to change.
3. Click the **Edit data sources** link at the bottom of the page.
4. Click **Add new**.
5. Complete the form and click **Save changes** to save your changes.
6. Click **OK**.

Changing internal user data sources

Use this procedure to change data source passwords or login names.

1. Click **Settings > Users**.
2. Click the name of the account you want to change.
3. Click the **Edit data sources** link at the bottom of the page.
4. Click the **Data source name** you want to change.
5. Edit the fields.

If you do not set a new password, the old one is retained.
6. Complete the form and click **Save changes** to save your changes.
7. Click **OK**.

Deleting internal user data sources

Use this procedure to delete internal user data sources.

1. Click **Settings > Users**.
2. Click the name of the account you want to change.
3. Click the **Edit Data Sources** link at the bottom of the page.
4. Click the name of the data source you want to delete.
5. Click **Delete**.
6. Click **OK**.

The user management pages

Refer to this table if you need help completing the fields on the Users page.

The New user page

Table 3. Fields on the New user page

Field	Description
First name	The user's first name.
Last name	The user's last name.
Login	<p>The user's login name. This is the only required field. Only the following special characters are allowed in login names.</p> <ul style="list-style-type: none"> • Upper and lower case alphabetic characters (A-Za-z) • Numbers (0-9) • The 'at' sign (@) • Hyphen (-) • Underscore (_) • Dot (.) • Double byte characters (such as Chinese characters)

Table 3. Fields on the New user page (continued)

Field	Description
	Do not include other special characters (including spaces) in the login name.
Password	<p>A password for the user. Follow these rules when creating a password.</p> <ul style="list-style-type: none"> • Passwords are case-sensitive. For example, <code>password</code> is not the same as <code>Password</code>. • You may use any character when you create or reset a password in Unica. <p>Additional password requirements are set on the Configuration page. To see what they are for your installation of Unica, click the Password Rules link next to the Password field.</p>
Confirm password	The same password you entered in the Password field.
Title	The user's title.
Department	The user's department.
Company	The user's company.
Country	The user's country.
Address	The user's address.
Work phone	The user's work phone number.
Mobile phone	The user's mobile phone number.
Home phone	The user's home phone number.
Email address	The user's email address. This field must conform to email addresses as defined in RFC 821. See RFC 821 for details.

Table 3. Fields on the New user page (continued)

Field	Description
Alternate login	The user's UNIX™ login name, if one exists. An alternate login is typically required when the Unica Campaignlistener runs as root on a UNIX™-type system.
Status	Select ACTIVE or DISABLED from the drop-down list. ACTIVE is selected by default. Disabled users are prevented from logging in to all Unicaapplications.

The Edit properties page

The fields are the same as the fields on the New user page, except for the ones shown in the following table.

Table 4. Fields on the Edit properties page

Field	Description
Password	This field is not available on the Edit properties page.
Login	This field is not available on the Edit properties page.
Password expiration	The date in the format appropriate for your locale (for example, for en_US, the format is MM, dd, YYYY). You cannot change a user's expiration date when the system-wide expiration date is set to never expire.
IBM® Digital Analytics user name	When integration is enabled with IBM Digital Analytics, and you choose to create users manually, you enter the user's Digital Analytics user name here as part of the configuration process.

The Reset password page

Table 5. Fields on the Reset password page

Field	Description
Password	The new password.
Confirm	The same password you entered in Password field.

The New Data Source and Edit Data Source Properties pages

Table 6. Fields on the Data Source pages

Field	Description
Data source	The name of a data source you want the user to be able to access from an Unica application. Unica names preserve case for display purposes, but use case-insensitive rules for comparison and creation (for example, you cannot create both <code>customer</code> and <code>Customer</code> data source names).
Data source login	The login name for this data source.
Data source password	The password for this data source. You can leave this field empty, if the data source account does not have a password.
Confirm password	The password again (leave empty if you left the Data Source Password field empty).

Locale preference

You can set the locale for both internal and external users. This setting affects the display of language, time, numbers, and dates in Unica applications.

There are two ways to set locale in Unica Platform.

Globally

A configuration property, `Platform | Region setting`, on the **Settings > Configuration** page, sets the locale globally.

Per user

An attribute on the **Settings > Users** page sets the locale for individual users.

This setting overrides the global setting.

Availability of locales that you can set either per user or globally may vary depending on the Unica application, and not all Unica applications support this locale setting in Unica Platform. See specific product documentation to determine availability and support for the `Region setting` property.



Note: Availability of locales that you can set either per user or globally may vary depending on the Unica application. Not all Unica applications support this locale setting. See specific product documentation to determine availability and support for the locale settings in Unica.

Setting the user locale preference

Use this procedure to set the locale preference for a user.

1. Click **Settings > Users**.
2. Click the user name you for which you want to set locale preferences.
3. Click the **Edit preferences** link at the bottom of the page.
4. Click **Unica Platform** in the left pane.
5. Select an option from the **Region** drop-down list.
6. Click **Save changes**.

Synchronization of external users

When Unica is configured to integrate with a Windows™ Active Directory or LDAP server, users and groups are automatically synchronized automatically at pre-defined intervals.

Automatic synchronization has limited functionality.

- Automatic synchronization updates user attributes only. Because group membership changes such as adding, removing, or changing members in a group require administrator oversight, import of these changes is confined to the manual synchronization process by default.
- Users deleted from the LDAP server are not deleted during automatic synchronization.

You can force a full synchronization of all users and groups by using the Synchronize function in the Users area of Unica.

Forcing synchronization of external users

Use this procedure to force synchronization of users when Unica is integrated with an LDAP server or web access control system.

1. Log in to Unica and click **Settings > Users**.
2. Click **Synchronize**.

Users and groups are synchronized.

Security management

Unica Platform supports roles and permissions to control user access to objects and features in Unica applications.

For the most part, only Unica Platform itself and Unica Campaign use the User roles and permissions page to manage users' application access in detail.

The other Unica products use some basic application access roles set on the User roles and permissions page, and either do not have detailed security settings, or the settings are not managed on the User roles and permissions page.

For example, in Unica Plan, setting up the basic roles on the User roles and permissions page is only the starting point for developing a customized security scheme. Unica Plan has a detailed security scheme you can manage through a user interface on the Unica Plan pages.

This guide explains how to use the functions on the User roles and permissions page, and describes the basic security roles and permissions shown on this page for the various products. For products other than Unica Platform, if you do not see the security management information you need in this guide, see the product's documentation.

Permissions and tasks of the security administrator in Unica Platform

Only users with either the AdminRole or PlatformAdminRole role in Unica Platform have access to security administration features for user accounts other than their own.

In a multi-partition environment, only users with the PlatformAdminRole role can administer users across partitions. Users with the AdminRole role can administer users in their own partition only.

The security administrator performs the following tasks on the User groups and User roles & permissions pages.

- Create internal groups and manage their memberships and partition assignments.
- Create roles for Unica Platform and Unica Campaign, if necessary, and assign permissions to these roles.
- Manage user access to Unica applications by assigning roles to individual users and/or to internal and external groups.

Read this overview to gain an understanding of the following.

- The difference between internal and external groups
- The process of creating internal groups and assigning roles and permissions
- The properties of internal groups
- The pre-configured user accounts, groups, and roles in Unica Platform

Special characters in role and policy names

You may use only the following characters when you create role and policy names.

- Upper and lower case alphabetic characters (A–z)
- Numbers (0–9)
- Single quote (')
- Hyphen (-)
- Underscore (_)
- The 'at' sign (@)
- Forward slash (/)
- Parenthesis
- Colon (:)
- Semi-colon (;)
- Space (except as the first character)
- Double byte characters (such as Chinese characters)

Roles and permissions in Unica Platform and Unica Campaign

Roles in Unica Platform and Unica Campaign are a configurable collection of permissions. For each role in Unica Platform and Unica Campaign, you can specify permissions that control access to the application.

You can use the default roles or create new roles. The set of available permissions is defined by the system; you cannot create a new permission.

About role assignment

Generally, you should give users roles with permissions that reflect the functions that users perform in your organization when they use Unica. You can assign roles to a group or to an individual user. The advantage of assigning roles by group is that you can assign a combination of roles to the group, and if you later want to change that combination, you can do it in one place rather than having to do it multiple times for multiple users. When you assign roles by group, you add and remove users from your groups to control user access.

How the system evaluates roles

If a user has multiple roles, the system evaluates permissions from all those roles together. The ability to perform a function on a particular object is then granted or denied based on the aggregated permissions from all roles. In the case of Unica Campaign, the ability to

perform a function on a particular object is granted or denied based on the security policy of the object.

Overview of managing user application access in Unica Platform

Using Unica Platform security administration features to manage user application access is a multi-step process. The following procedure provides an overview of the basic process, which is described in detail in the remainder of this guide.

1. Plan the roles you want to use to control user access to Unica products. Configure roles and their permissions as needed.
2. Plan what groups you need to fulfill your security requirements. You may have only internal groups, only external groups, or a combination of both, depending on how your system is configured.
3. Create any necessary internal and external groups.
4. Assign your groups to roles.
5. If you have only internal user accounts, create any internal user accounts as needed.
6. Assign users to groups, or assign roles to individual users, based on the application access you want the users to have.

Types of groups: internal and external

When Unica is integrated with an external server (such as a supported LDAP server or a web access control system), it supports two types of groups: internal and external.

- **Internal** - Groups that are created within Unica using the security user interface. These users are authenticated through Unica.
- **External** - Unica groups that are mapped to groups in the external system. Examples of external servers are LDAP and web access control servers.



Attention: A group referred to as an external group in this guide is one that is actually created in Unica but is mapped to an external system.

Depending on your configuration, you may have only internal groups, only external groups, or a combination of both.

For more information about integrating Unica with an LDAP or Windows™ Active Directory server, see the relevant sections of this guide.

Management of external groups

The membership of external groups is managed in the external system.

You can assign roles to Unica external groups just as you do to internal groups.

Management of internal groups and subgroups

You can define an unlimited number of internal groups, and any internal or external user can be a member of multiple internal groups and subgroups.

A subgroup does not inherit the user members assigned to its parents, but it does inherit the roles assigned to its parents. A group and its subgroups always belong to one partition.

Only internal groups may be assigned to a partition, and only the platform_admin user, or another account with the PlatformAdminRole role, can create groups in all partitions in a multi-partition environment.

Partitions and security management

Partitions in Unica Campaign and related products provide a way to secure the data associated with different groups of users. With partitioning, a user's partition appears as if it were a separate running instance of Unica Campaign, with no indication that other partitions are running on the same system. This section describes special security management considerations in a multi-partition environment.

User membership in a partition

You assign users to a partition based on their group membership. You assign a group to a partition and then assign users to a group to give them access to a partition.

A group or subgroup may be assigned to just one partition, and parent groups do not acquire the partition assignments of their subgroups. Only the `platform_admin` user, or another account with the `PlatformAdminRole` role, can assign a group to a partition.

You should make a user a member of only one partition.

About roles and partitions

A role always exists in the context of a partition. In a single-partition environment, all roles are automatically created within the default partition, `partition1`. In a multi-partition environment, a role is created in the partition of the user who created it. The exception is the `platform_admin` user and any other accounts with the `PlatformAdminRole` role; these accounts can create roles in any partition.

More information about partitions

This section provides instructions on assigning a group to a partition, and assigning users to groups. For complete details on configuring partitions, see the Unica Campaign installation documentation.

Pre-configured users and roles

When Unica is first installed, three users are pre-configured and are assigned system-defined roles in Unica Platform and Unica Campaign, as described in this section.

These internal user accounts all have "password" as the default password.

The `platform_admin` user account

The `platform_admin` user account is designed to allow an Unica administrator to manage product configuration, users, and groups across all partitions in a multi-partition environment, and to use all Unica Platform features (except reporting, which has its own roles) without any filtering by partition. By default, this account has the following roles in Unica Platform.

- In Unica Platform, in the default partition, partition1
 - AdminRole
 - UserRole
 - PlatformAdminRole

These roles allow the platform_admin user to perform all administrative tasks within Unica Platform, except for the reporting functions. When additional partitions are created, the platform_admin user can access and administer users, groups, roles, and configuration within the additional partitions.

The PlatformAdminRole role is unique in that no user can modify permissions for this role, and only a user with this role can assign the PlatformAdminRole role to another user.

- In Unica Campaign, in the default partition, partition1
 - The Global policy Admin role

This role allows the platform_admin user to perform all tasks within Unica Campaign.

By default, this user does not have access to any Unica products beyond Unica Platform and Unica Campaign.

The asm_admin user account

The asm_admin user account is designed to allow an Unica administrator to manage users and groups in a single-partition environment, and to use all Unica Platform features (except reporting, which has its own roles). This account has the following roles.

- In Unica Platform, in the default partition, partition1
 - AdminRole
 - UserRole

With the exceptions noted below, these roles allow the asm_admin user to perform all administrative tasks within Unica Platform within the partition to which asm_admin belongs, which is partition1 by default.

These roles allow this user to administer the Configuration page, which does not filter by partition for any user. For this reason, you should remove the Administer

Configuration page permission from the AdminRole role in Unica Platform, and reserve configuration tasks for the platform_admin user.

The exceptions are as follows.

- To access reporting functions, you must grant the Reports System role.
- This user cannot assign the PlatformAdminRole role to any user or group.

The demo account

The demo account has the following roles.

- In Unica Platform, in the default partition, partition1
 - UserRole

This role allows the demo user to view and modify his or her own account attributes on the Users page, but not to change roles or partitions for his or her own account or access any of the other features contained within Unica Platform. By default, this user does not have access to any of the Unica products.

- In Unica Campaign, in the default partition, partition1
 - The Global policy Review role

This role allows the demo user to create bookmarks and to view campaigns, sessions, offers, segments, and reporting in Unica Campaign.

Cross-partition administration privileges

In a multi-partition environment, at least one user account with the PlatformAdminRole role in Unica Platform is required, to enable you to administer security for Unica users across all partitions.

The platform_admin account is pre-configured with the PlatformAdminRole role. The platform_admin account is a superuser account that cannot be deleted or disabled through the Users functions in Unica. However, this account is subject to the password constraints of any other user. For example, someone attempting to log in as platform_admin might enter an incorrect password N times in a row. Depending on the password rules in effect,

the `platform_admin` account might be disabled in the system. To restore this account, you must take one of the following actions.

- If you have another user with the PlatformAdminRole role in Unica Platform, log in as that user and reset the `platform_admin` user's password or create another account with the PlatformAdminRole role in Unica Platform.
- If you have only one user with the PlatformAdminRole role in Unica Platform (for example, `platform_admin`), and this user is disabled, you can create a new `platform_admin` account using the `restoreAccess` utility provided with Unica Platform.

To avoid a situation where you must restore PlatformAdminRole access using the `restoreAccess` utility, it is a good practice to create more than one account with PlatformAdminRole privileges.

Adding an internal group

Use this procedure to add an internal group.

1. Click **Settings > User groups**.
2. Click **New group** above the **Group Hierarchy** list.
3. Complete the **Group name** and **Description** fields.



Important: Do not give the group a the same name as system-defined roles. For example, do not name a group "Admin," which is a role name used in Unica Campaign. Doing so can cause problems during upgrades.

4. Click **Save changes**.

The new group's name appears in the **Group hierarchy** list.

Adding a subgroup

Use this procedure to add an internal subgroup.

1. Click **Settings > User groups**.
2. Click the name of the group to which you want to add a subgroup.
3. Click **New subgroup**.
4. Complete the **Group name** and **Description** fields.



Important: Do not give the subgroup a the same name as system-defined roles. For example, do not name a subgroup "Admin," which is a role name used in Unica Campaign. Doing so can cause problems during upgrades.

5. Click **Save changes**.

The new subgroup is added under the appropriate group in the **Group Hierarchy** list.



Tip: If the parent group's folder icon is closed, click the plus sign (+) to expand the list.

Deleting a group or subgroup

Remember, when you delete a group or subgroup, members of the group lose the roles assigned to that group, and any parents of that group also lose those role assignments, unless the roles are also explicitly assigned to the parents.

1. Click **Settings > User groups**.
2. Click the name of the group or subgroup that you want to delete.



Note: To select a subgroup when the parent group's folder icon is closed, click the plus sign (+) to expand the list.

3. Click the **Delete group** button at the top of the right pane.
4. Click **OK**.

Changing a group or subgroup description

Use this procedure to change a group or subgroup description.

1. Click **Settings > User groups**.
2. Click the name of the group or subgroup whose description you want to change.



Note: To select a subgroup when the parent group's folder icon is closed, click the plus sign (+) to expand the list.

3. Click **Edit properties**.
4. Edit the description as desired.
5. Click **Save changes** to save your changes.
6. Click **OK**.

Assigning a group to a partition

This procedure is necessary only if multiple partitions are configured for Unica Campaign. Only an account with the PlatformAdminRole role, such as the platform_admin user, can perform this task.

1. Determine which groups you want to assign to each partition. Create the groups, if necessary.
2. Click **Settings > User groups**.
3. Click the name of the group or subgroup that you want to assign to a partition.
4. Click **Edit properties**.
5. Select the desired partition from the **Partition ID** drop-down list.

This field is available only when multiple partitions are configured.

6. Click **Save changes** to save your changes.
7. Click **OK**.

Adding a user to a group or subgroup

Use this procedure to add a user to a group or subgroup.

1. Click **Settings > Users**.



Note: You can perform the same task on the **User groups** page by clicking the group name and then clicking **Edit Users**.

2. Click the user name you want to change.
3. Click the **Edit groups** link at the bottom of the page.
4. Click a group name in the **Available groups** box to select it.
5. Click the **Add** button.

The group name moves to the **Groups** box.

6. Click **Save changes** to save your changes.
7. Click **OK**.

The user account details are displayed, with the group or subgroup you assigned listed.

Removing a user from a group or subgroup

Use this procedure to remove a user from a group or subgroup.



Important: Removing a user from a group or subgroup removes the roles assigned to that group or subgroup from the user.

1. Click **Settings > Users**.
2. Click the user name you want to change.
3. Click the **Edit groups** link at the bottom of the page.
4. Click a group name in the **Groups** box to select it.
5. Click the **Remove** button.

The group name moves to the **Available groups** box.

6. Click **Save changes** to save your changes.
7. Click **OK**.
8. Click the **Edit properties** link at the bottom of the page.
9. Change the name or description as desired.

10. Click **Save changes** to save your changes.

11. Click **OK**.

The user group management pages

These are the fields you use to configure user groups.

Fields on the New group, New subgroup, and Edit properties pages

Table 7. Fields on the New group, New subgroup, and Edit properties pages

Field	Description
Group name	<p>The group name. The limit is 64 characters.</p> <p>You may use the following characters when you create a group name.</p> <ul style="list-style-type: none"> • Upper and lower case alphabetic characters (A-Z) • Numbers (0-9) • Single quote (') • Hyphen (-) • Underscore (_) • The 'at' sign (@) • Forward slash (/) • Parenthesis • Colon (:) • Semi-colon (;) • Space (except as the first character) • Double byte characters (such as alpha-numeric Chinese characters) <p>Do not give a group or subgroup a the same name as system-defined roles. For example, do not name a group "Admin," which is</p>

Table 7. Fields on the New group, New subgroup, and Edit properties pages (continued)

Field	Description
	<p>a role name used in Unica Campaign. Doing so can cause problems during upgrades.</p> <p>Unica names preserve case for display purposes, but use case-insensitive rules for comparison and creation (for example, you cannot create both Admin and admin as separate group names).</p> <p>When you create a subgroup, it is a good idea to give your subgroup a name that relates it to its parent group.</p>
Description	<p>The group description. The limit is 256 characters.</p> <p>It is helpful to include the roles you plan to give the group or subgroup in the description. Then you can see at a glance on the group detail page both the roles and users.</p>
Partition ID	<p>Available only when multiple partitions are configured.</p> <p>If you assign a partition to a group, the members of that group are members of that partition. A user can be a member of only one partition.</p>

Fields on the Edit users and Edit roles pages

Table 8. Fields on the Edit users and Edit roles pages

Field	Description
Available groups or Available roles	A list of groups and subgroups or roles to which the user is not assigned.
Groups or Roles	A list of groups and subgroups or roles to which the user is assigned

Creating a role

You should create new roles only for products that have detailed permissions. The reporting function and some Unica products have only basic permissions available, so there is no need to create additional roles for these products.

1. Click **Settings > User roles & permissions**.
2. Click the plus sign next to the product name in the list on the left, and then click the name of the partition where you want to create the role.
3. For Unica Campaign only, if you want to create a new role under the Global Policy, click Global Policy.
4. Click **Add roles and assign permissions**.
5. Click **Add a role**.
6. Enter a name and description for the role.
7. Click **Save changes** to save the role, or **Save and edit permissions** to go to the Permissions page to add or modify permissions for any of the roles in the list.

Modifying role permissions

Use this procedure to modify role permissions.

1. Click **Settings > User roles & permissions**.
2. Click the plus sign next to a product in the list on the left, and then click the name of the partition where you want to modify a role.
3. For Unica Campaign only, if you want to create a new role under the Global Policy or a user-created policy, click the policy name.
4. Click **Add roles and assign permissions**.
5. Click **Save and edit permissions**
6. Click the plus sign next to a role group to display all available permissions and the state of those permissions within each role.
7. In the role column where you want to modify permissions, click the box in the permissions rows to set the state to Grant, Deny, or Not granted.

8. Click **Save changes** save your changes.

You can click **Revert to saved** to undo changes since your last save and remain on the Permissions page, or **Cancel** to discard your changes since your last save and go to the partition or policy page.

Removing a role from the system

Use this procedure to remove a role from Unica.



Important: If you remove a role, it is removed from all users and groups to which it was assigned.

1. Click **Settings > User roles & permissions**.
2. Click the plus sign next to a product in the list on the left, and then click the name of the partition where you want to create the role.
3. For Unica Campaign only, if you want to create a new role under the Global Policy, click Global Policy.
4. Click **Add roles and assign permissions**.
5. Click the **Remove** link for the role you want to delete.
6. Click **Save changes**.

Assigning a role to or removing a role from a group

If you add a role to a group or remove a role from a group, members of that group acquire or lose that role.

1. Click **Settings > User groups**.
2. Click the name of the group that you want to work with.
3. Click **Assign roles**.

Roles that are not assigned to the group are shown in the **Available roles** box on the left. Roles that are currently assigned to the group are shown in the **Roles** box on the right.

4. Click a role name in the Available roles box to select it.

5. Click **Add** or **Remove** to move the role name from one box to the other.
6. Click **Save changes** to save your changes.
7. Click **OK**.

Assigning a role to or removing a role from a user

Use the **Edit roles** window to assign a role to or to remove a role from a user.

Complete the following tasks to assign or remove a role from a user:

1. Click **Settings > Users**.
2. Click the name of the user account that you want to work with.
3. Click **Edit roles**.

Roles that are not assigned to the user are shown in the **Available Roles** box on the left. Roles that are currently assigned to the user are shown in the **Selected roles** box on the right.

4. Select a role in the **Available roles** box. Complete one of the following tasks:
 - To assign a role to a user, select a role in the **Available roles** box, and click **Add**.
 - To remove a role from a user, select a role in the **Selected roles** box, and click **Remove**.
5. Click **Save changes**, and then click **OK**.

Definitions of permission states

For each role, you can specify which permissions are granted, not granted, or denied. You set these permissions on the **Settings > User roles and permissions** page.

These states have the following meanings.

- **Granted** - indicated with a check mark . Explicitly grants permission to perform this particular function as long as none of the user's other roles explicitly denies permission.
- **Denied** - indicated with an "X" . Explicitly denies permission to perform this particular function, regardless of any other of the user's roles which might grant permission.
- **Not granted** - indicated with a circle . Does not explicitly grant nor deny permission to perform a particular function. If this permission is not explicitly granted by any of a user's roles, the user is not allowed to perform this function.

Permissions for products that use only basic roles

The following table describes the functional definitions of the roles available for the Unica products that use only the basic roles. See the product documentation for additional information.

Table 9. Permissions for products that use only basic roles

Application	Roles
Leads	Leads roles are reserved for future use.
Reports	<ul style="list-style-type: none"> • ReportsSystem - grants the <code>report_system</code> permission, which gives you access to the Report SQL Generator and Sync Report Folder Permissions options in the Settings menu. • ReportsUser - grants the <code>report_user</code> permission, which is used by the Authentication Provider installed on the IBM® Cognos® 11 BI system only. <p>For information about authentication options for the IBM® Cognos® 11 BI integration and how the Authentication Provider uses the reporting permissions, see the Unica Reports Installation and Configuration Guide.</p>

Table 9. Permissions for products that use only basic roles (continued)

Application	Roles
IBM eMessage	<ul style="list-style-type: none"> • Deliver_Admin - Has full access to all features. • Deliver_User - Reserved for future use. <p>Access is further defined through the security policies in Unica Campaign. See the IBM eMessage Startup and Administrator's Guide for details.</p>
Unica Interact	<ul style="list-style-type: none"> • InteractAdminRole - Has full access to all features.
Unica Collaborate	<ul style="list-style-type: none"> • collab_admin - Has full access to all features. • corporate - Can use Unica Campaign and Unica Collaborate to develop reusable Lists and On-demand Campaign templates. Can create and execute Corporate Campaigns. • field - Can participate in Corporate Campaigns and can create and execute Lists and On-demand Campaigns in Unica Collaborate.
Unica Plan	<ul style="list-style-type: none"> • PlanUserRole - By default, users with the PlanUserRole role have very few permissions enabled in Unica Plan. They cannot create plans, programs, or projects and have limited access to the Administrative settings. • PlanAdminRole - By default, users with the PlanAdminRole role have most permissions enabled in Unica Plan, including access to all administrative and configuration settings, allowing a broad range of access. <p>Access is further defined through the security policies in Unica Plan.</p>

Table 9. Permissions for products that use only basic roles (continued)

Application	Roles
IBM SPSS Modeler Advantage Enterprise Marketing Management Edition	<ul style="list-style-type: none"> • SPSSUser - Users with the SPSSUser role can do the following: <ul style="list-style-type: none"> ◦ Run reports ◦ View items in their Content Repository ◦ Perform scoring • SPSSAdmin - Users with the SPSSAdmin role have all permissions enabled in IBM SPSS Modeler Advantage Enterprise Marketing Management Edition, including access to all administrative and configuration settings.

Permissions for Unica Platform

The following table describes the permissions you can assign to roles in Unica Platform.

Table 10. Unica Platform permissions

Permission	Description
Administer users page	Allows a user to perform all user administration tasks on the Users page for user accounts in his or her own partition: add and delete internal user accounts, and modify attributes, data sources and role assignments
Access users page	Allows a user to view the User page.
Administer User groups page	Allows a user to perform all actions on the User groups page except assign a partition to a group, which can only be done by the platform_admin user. This permission allows a user to create, modify, and delete groups, manage group membership, and assign roles to groups.
Administer User roles page	Allows a user to perform all actions on the User roles & permissions page: create, modify, and delete roles in Unica Platform

Table 10. Unica Platform permissions (continued)

Permission	Description
	and Unica Campaign, and assign users to roles for all listed Unica products.
Administer Configuration page	Allows a user to perform all actions on the Configuration page: modify property values, create new categories from templates, and delete categories that have the Delete Category link.
Administer Data filters page	Allows a user to perform all actions on the Data filters page: assign and remove data filter assignments.
Administer Scheduled tasks page	Allows a user to perform all actions on the Schedule management page: view and modify schedule definitions and view runs.
Administer dashboards	Allows a user to perform all actions on the dashboards pages: create, view, modify, and delete dashboards, assign dashboard administrators, and administer dashboard access.

Permissions for Opportunity Detect

The following table describes permissions that you can assign to roles in Opportunity Detect.

All permissions that have the **Not Granted** status are treated as **Denied**.

Table 11. Permissions in Opportunity Detect

Permission	Description
View only	Can access all of the user interface, in view-only mode.
Design triggers	<ul style="list-style-type: none"> • Can create workspaces and design trigger systems. • Can create, modify, and delete all trigger related resources. • Can access Workspace, Component, Audience Level, Data Source, and Named Value List pages.

Table 11. Permissions in Opportunity Detect (continued)

Permission	Description
	<ul style="list-style-type: none"> • Can not access the Server Groups page or the Deployment tab of a workspace. • Can not set off a batch run. • Can not administer objects that the web service creates when Opportunity Detect is integrated with Unica Interact.
Run for testing	<ul style="list-style-type: none"> • Deploy deployment configurations and run batch deployment configurations on server groups not designated for production. • Can access Server Group page and the Deployment tab of a workspace, but can not designate a server group for production. • Can not deploy deployment configurations or run deployment configurations that use a production server group.
Run for production	<ul style="list-style-type: none"> • Deploy deployment configurations and run batch deployment configurations on any server group. • Perform all actions on the Server Group page and the Deployment and Batch Run tabs of a workspace, including designating a server group for production.
Administer real time	<p>Manage objects that the web service creates when Opportunity Detect is integrated with Unica Interact to enable real time mode.</p> <p>Allows the following.</p> <ul style="list-style-type: none"> • Delete workspaces and components created by the web service. • Start and stop real time deployment configurations and update their log level. <p>The user with this permission alone can not start runs for real time deployment configurations.</p>

Table 11. Permissions in Opportunity Detect (continued)

Permission	Description
	<p>No one, even with this permission, can do any of the following.</p> <ul style="list-style-type: none"> • Delete and update audience levels, data sources, named value lists, server groups, or deployment configurations created by the web service. • Create and deploy deployment configurations created by the web service.

Configuration management

When Unica is first installed, the Configuration page shows only the properties used to configure Unica Platform and some global configuration properties. When you install additional Unica applications, the properties used to configure these applications are registered with Unica Platform. These properties are then shown on the Configuration page, where you can set or modify their values.

Some applications might have additional configuration properties that are not stored in the central repository. See application documentation for complete information about all configuration options for the application.

Property categories

The **Reports**, **General**, and **Unica Platform** categories are present when Unica Platform is first installed. These categories contain properties that apply across all Unica applications installed in a suite.

- The default locale setting
- The **Security** category and sub categories with properties that specify login modes and mode-specific settings.
- Password settings
- Properties that configure data filters

- Properties that configure schedules
- Properties that configure the reporting feature
- Properties that configure how alerts are handled

Depending on the Unica applications that are installed, additional categories contain application-specific categories and sub categories. For example, after Unica Campaign is installed, the **Campaign** category contains Unica Campaign-related properties and sub categories.

Category types

A category can be one of three types, which are identified by different icons.

Table 12. Icons for category types

Category type	Icon
Categories that contain no configurable properties	
Categories that contain configurable properties	
Template categories that you can use to create a category Names of template categories are also shown in italics and enclosed in parentheses.	

Templates for duplicating categories

The properties for an Unica application are registered with Unica Platform when the application is installed. When an application requires users to create duplicate categories for configuration purposes, a category template is provided.

To create a category, you duplicate the template. For example, you can create a new Unica Campaign partition or data source by duplicating the appropriate template.

You can also delete any category that was created from a template.

Category naming restrictions

The following restrictions apply when you name a category that you create from a template.

- The name must be unique among categories that are siblings in the tree (that is, among categories that share the same parent category).
- The following characters are not allowed in category names.



! " ' # \$ % & () * + : ; ,
 ^ < > + ? @ [] { } / \ ` ~

Also, the name cannot start with a period.

Property descriptions

You can access property descriptions in either of the following ways.

- Click **Help > Help for this page** to launch online help and display a topic that describes all of the properties for the page you are viewing.
- Click **Help > Product documentation** to launch a page that gives you access to all of the product documentation in online or PDF format. All property descriptions are included as an appendix in the Unica Platform Administrator's Guide.

The refresh function

A refresh button  located at the top of the Configuration navigation tree provides the following functions.

- Refreshes the contents of the tree, which is useful you want to obtain the latest information about configuration settings. These settings might have been updated while you are viewing the tree (for example, when an application has been registered or unregistered or when someone else has updated settings).
- Returns the navigation tree to the state it was in the last time you selected a node, collapsing or expanding the tree as necessary.



Important: If you are in edit mode when you click **Refresh**, the page is returned to the read mode. Any unsaved changes are lost.

The default user locale preference

Unica Platform contains a default locale attribute that applies to all Unica applications that implement it.

You can set this default by setting the value of the **Region setting** property in the **Platform** category.

For details on this property, see its online help in the Configuration area or the Unica Platform Administrator's Guide. To learn whether an Unica application implements this attribute, see the documentation for that application.

In addition, you can override these default values on a per-user basis by changing the value of this property in the user's account.

Navigating to a category

Use this procedure to navigate to a category on the Configuration page.

1. Log in to Unica.
2. Click **Settings > Configuration** in the toolbar.

The Configuration page shows the Configuration Categories tree.

3. Click the plus sign beside a category.

The category opens, showing sub categories. If the category contains properties, they are listed along with their current values.

The internal names for the categories are displayed under the page title. You use these internal names when you manually import or export categories and their properties using the `configTool` utility.

4. Continue to expand the categories and sub categories until the property you want to edit appears.

Editing property values

Use this procedure to modify a property value on the Configuration page.

1. Navigate to the category that contains the property you want to set.

The Settings page for the category shows a list of all the properties in the category and their current values.

2. Click **Edit settings**.

The Edit settings page for the category shows the property values in editable fields.

3. Enter or edit values as needed.

In UNIX™, all file and directory names are case-sensitive. The case of any file and folder name you enter must match the case of the file or folder name on the UNIX™ machine.

4. Click **Save changes** to save your changes or **Cancel** to exit the page without saving.

Creating a category from a template

Use this procedure to create a category from a template on the Configuration page.

1. On the Configuration page, navigate to the template category you want to duplicate.

Unlike other categories, template category labels are in italics and enclosed in parentheses.

2. Click the template category.
3. Enter a name in the **New category name** field (required).
4. You can edit properties within the new category now, or later.
5. Click **Save changes** to save the new configuration.

The new category appears in the navigation tree.

Deleting a category

Use this procedure to delete a category on the Configuration page.

On the Configuration page, some categories can be deleted and others cannot. Any category you create from a template can be deleted. In addition, when an Unica product is registered, its set of categories might include categories that can be deleted.

1. On the Configuration page, navigate to the category you want to delete and click to select it to open its Settings page.

If the category you have selected can be deleted, you see a **Delete Category** link.

2. Click the **Delete category** link.

A window shows the message, Are you sure you want to delete "category name"?

3. Click **OK**.

The category no longer appears in the navigation tree.

Dashboard management

Dashboards are configurable pages that contain information useful to groups of users who fill various roles within your company. The components that make up dashboards are called portlets. Dashboards can contain pre-defined portlets or portlets that you create.

You can create and configure dashboards yourself, or you can use the pre-assembled dashboards. Pre-assembled dashboards contain pre-defined portlets in combinations that are designed to be useful to users in a variety of roles within your organization.

You can also create your own custom portlets from Unica product pages, pages on your company intranet, or pages on the internet.

Dashboard planning

To plan how your organization uses the dashboard feature, you should work with your marketing management team to decide the following details.

- Which dashboards your users need.
- Which users should have access to which dashboards.
- Which portlets should go into each dashboard.
- Who should be designated as the dashboard administrator for each dashboard after the dashboards are rolled out. The dashboard administrator manages user access to the dashboard and modifies individual dashboard content and layout if necessary.

Dashboard audiences

You can control who views your dashboards by associating them with groups or by assigning individual users to them. Members of a group can access the dashboard or dashboards associated with that group, while non-members cannot view these dashboards.

You can also create one or more global dashboards, which can be seen by all Unica users within a partition regardless of their group membership or individual assignments.

When you create a global dashboard, you should include portlets that are of interest to the widest possible range of users. For example, if you have installed Unica Campaign, you may want to include the My Custom Bookmarks portlet, one of the pre-defined Unica portlets.

User permissions required to view dashboards

Dashboards allow Unica users to view pages from multiple products (such as Unica Plan and Unica Campaign) in a single page, regardless of the permissions that are configured for them within those products.

Some dashboard portlets allow users to perform work in an Unica product by clicking a link within a portlet to open a page on which they can work. If the user does not have permissions to perform the task, the page does not display.

Some content within portlets is filtered based on the user. For example, if a user never works directly with campaigns, the My Recent Campaigns portlet might not display any links.

Pre-defined portlets

Unica provides two types of pre-defined dashboard portlets, which you can enable and then add to any dashboard you create.

Unica pre-defined portlets use Unica Platform single-sign-on mechanism to access Unica content. Users are not prompted for credentials when they view a dashboard containing these portlets.

- **List:** A list of Unica items specific to the user. Examples of list portlets are My Recent Campaigns (Unica Campaign), My Alerts (Unica Plan, and the Continent Summary report (Digital Analytics for On Premises).
- **IBM® Cognos® report:** A specially formatted version of an Unica report.

You can also create your own custom dashboard portlets.

Pre-defined portlet availability

Unica provides pre-defined portlets with many of its products. Availability of the pre-defined portlets depends on the Unica products you have installed. Also, the IBM® Cognos® portlets are available only when the Unica reporting feature is implemented.

You must enable the pre-defined portlets in Unica Platform before you can use them in a dashboard. Unica portlets are listed in Unica Platform whether or not the product they belong to is installed. It is a good practice to enable only those portlets that belong to products that are installed. Only the portlets that are enabled appear in the list of portlets you can add to a dashboard.

Unica Plan IBM Cognos® report portlets

The following table describes the Unica Plan dashboard portlets that are available after the Unica Plan reports package is installed.

Table 13. Standard Unica Plan Cognos® report portlets

Report	Description
Budget by Project Type	An example Cognos® report shows a 3-D pie chart of the budget per project type for the current calendar year. This report requires the Financial Management module.
Completed Projects by Quarter	An example Cognos® report shows a 3-D bar chart of the number of early, on-time, and late projects completed this quarter.
Forecast by Project Type	An example Cognos® report shows a 3-D pie chart of the forecasted spending per project type for the current calendar year.
Manager Approval Summary	An example Cognos® report shows data for active and completed approvals for all In Progress projects in the system.
Manager Task Summary	An example Cognos® report shows data for active and completed tasks for all In Progress projects.
Marketing Financial Position	An example Cognos® report shows a timeline with Budget, Forecasted, Committed, and Actual amounts for all plans in all states in the current calendar year. This report requires the Financial Management module.
My Task Summary	An example Cognos® report shows data about all active and completed tasks for the user who is viewing the report in all In Progress projects.
My Approval Summary	An example Cognos® report shows data about active and completed approvals for the user who is viewing the report.
Projects by Project Type	An example Cognos® report shows a 3-D pie diagram that shows all In Progress projects in the system by template type.

Table 13. Standard Unica Plan Cognos® report portlets (continued)

Report	Description
Projects by Status	An example Cognos® report shows a 3-D bar chart that shows all projects in the system by status: draft, in progress, on hold, canceled, and finished.
Projects Requested and Completed	An example Cognos® report shows a timeline graph of the number of project requests and number of completed projects per month. This report counts project requests with the following states only: Submitted, Accepted, or Returned.
Spend by Project Type	An example Cognos® report shows a 3-D pie chart of the actual amount that is spent per project type in the current calendar year. This report requires the Financial Management module.

Unica Plan list portlets

If the Unica Plan reports package is not installed, you still have access to the Unica Plan list portlets that are available on your dashboard.

Your system administrator selects the portlets that members of your organization can add to the dashboard. To manage your dashboards and add portlets to them, select **Dashboard > Create Dashboard**.

Table 14. Standard Unica Plan list portlets

Report	Description
Approvals Awaiting Action	List of approvals that wait for your action.
Manage My Tasks	Lists your Pending and Active tasks and Not Started and In Progress approvals. An option to change the status of each item appears.

Table 14. Standard Unica Plan list portlets (continued)

Report	Description
	<ul style="list-style-type: none"> • For tasks, you can change the status to Finish or Skip. • For Not Started approvals, you can change the status to Submit or Cancel. • For In Progress approvals that you own, you can change the status to Stop, Finish, or Cancel. • For In Progress approvals that you are assigned to approve, you can change the status to Approve or Reject.
My Active Projects	Lists your active projects.
My Alerts	Lists your Unica Plan alerts.
My Project Health	<p>Lists the name, health status, percentage complete, and number of tasks that are assigned to you for each project that you own or that includes you as a reviewer or member. The percentage complete is calculated as:</p> $\frac{(\text{Number of Finished Tasks} + \text{Number of Skipped Tasks})}{\text{Total Number of Workflow Tasks}}$ <ul style="list-style-type: none"> • To recalculate project health status, click . The system recalculates the health status for display by this portlet only. It does not work elsewhere in Unica Plan. <p> Note: Project health calculations can be made only at 5-minute intervals.</p> <ul style="list-style-type: none"> • If you own more than 100 projects, click Show All to open the list in a new dialog. • To export listed project data into a .CSV file, click Export.

Table 14. Standard Unica Plan list portlets (continued)

Report	Description
	<ul style="list-style-type: none"> You can view the summary information for a project on the Summary tab. To view more metrics for project health, click the percentage complete indicator. To view the My Tasks list, click the number in the Tasks column.
My Requests	Lists requests that you own.
My Tasks	Lists tasks that you own.
Projects Over Budget	<p>Lists all projects that are over budget for the calendar year.</p> <p> Note: This report requires the Financial Management module.</p>

IBM® Cognos® report portlets for Unica Campaign

The IBM® Cognos® report portlets are provided with the Unica Campaign reports package. Use the report portlets to analyze response rates and campaign effectiveness.

You can enable and then add pre-defined dashboard portlets to any dashboard that you create. To manage your dashboards and add portlets to them, click **Dashboard > Create Dashboard**.

Table 15. IBM® Cognos® report portlets for Unica Campaign

Report	Description
Unica Campaign Return on Investment Comparison	An IBM® Cognos® report that compares, at a high level, the ROI of campaigns created or updated by the user viewing the report.
Unica Campaign Response Rate Comparison	An IBM® Cognos® report that compares the response rates of one or more campaigns created or updated by the user viewing the report.

Table 15. IBM® Cognos® report portlets for Unica Campaign (continued)

Report	Description
Unica Campaign Revenue Comparison by Offer	An IBM® Cognos® report that compares the revenue received to date per campaign containing offers created or updated by the user viewing the report.
Offer Responses for Last 7 Days	An IBM® Cognos® report that compares the number of responses that were received over the last 7 days based on each offer created or updated by the user viewing the report.
Offer Response Rate Comparison	An IBM® Cognos® report that compares the response rate by offer created or updated by the user viewing the report.
Offer Response Breakout	An IBM® Cognos® report that shows the active offers created or updated by the user viewing the report, broken out by status.

Unica Campaign list portlets

The standard Unica Campaign list portlets are available for use on dashboards even if the reports package for Unica Campaign is not installed.

Table 16. Unica Campaign list portlets

Report	Description
My Custom Bookmarks	A list of links to websites or files created by the user viewing the report.
My Recent Campaigns	A list of the most recent campaigns created by the user viewing the report.
My Recent Sessions	A list of the most recent sessions created by the user viewing the report.
Unica Campaign Monitor Portlet	A list of the campaigns that have run or are currently running that were created by the user viewing the report.

IBM eMessage IBM Cognos® report portlets

The following dashboard portlets are available in the IBM eMessage reports package.

Report	Description
Recent Email Bounce Responses	This dashboard report presents data for various types of email bounces as a bar chart. The chart presents current bounce responses for the five most recent mailings that were sent before the current day.
Recent Email Campaigns Sent	This dashboard report provides a summary view of your most recent mailing activity. It lists totals for message transmission, recipient responses, and email bounces for the five most recent mailings that were sent before the current day.

Unica Interact IBM® Cognos® report portlet

Interaction Point Performance - Shows the number of offers accepted per interaction point over a seven day period.

This dashboard report is defined to point to the interactive channel with the ID of 1. To create additional versions of this report (to report on additional interactive channels) or to change the ID of the interactive channel that this report points to, see [How to configure the Interaction Point Performance dashboard portlet \(on page 54\)](#).

How to configure the Interaction Point Performance dashboard portlet

Unica Interact has one Cognos® dashboard report: Interaction Point Summary. Because dashboard reports do not prompt users for query parameters, the channel ID of the interactive channel in the Interaction Point Performance report is a static value. By default, the channel ID for this report is set to 1. If the channel ID is not correct for your implementation, you can customize the report and change the channel ID in the report's filter expression.

To customize any of the Cognos® reports, you need Cognos® report authoring skills. For detailed documentation about creating and editing Cognos® BI reports, see the Cognos® BI documentation, especially Cognos® BI Report Studio Professional Authoring User Guide for your version of Cognos®.

For information about the queries and data items in the Interaction Point Performance report, see the reference documentation that is provided in the Unica Interact reports package.

To display a chart for more than one interactive channel in the Dashboard, make a copy of the Interaction Point Performance Dashboard and modify the channel ID. Then, create a new dashboard portlet for the new report and add it to your dashboards.

Unica Collaborate list portlets

This section describes the standard Unica Collaborate portlets that are available for use on dashboards.

Table 17. Unica Collaborate list portlets

Report	Description
List Management	A list of active Lists for the user viewing the report.
Campaign Management	A list of active Corporate Campaigns and On-demand Campaigns for the user viewing the report.
Subscription Management	A list of subscriptions to Corporate Campaigns for the current user.
Calendar	The Calendar showing the schedule for active Corporate Campaigns and On-demand Campaigns.

Unica Optimize list portlets

The standard Unica Optimize portlets that are available for use on dashboards.

These portlets are available for use in the Unica dashboard only.

Table 18. Unica Optimize list portlets

A two-column table that describes the Unica Optimize list portlets.

Report	Description
My recent Unica Optimize sessions	A list of the last 10 Unica Optimize sessions run by the user viewing the report within the last 30 days.
My recently successful Unica Optimize run instances	A list of the last 10 Unica Optimize sessions run by the user viewing the report that completed successfully within the last 30 days.
My recently failed Unica Optimize run instances	A list of the last 10 Unica Optimize sessions run by the user viewing the report that did not complete successfully within the last 30 days.

Pre-assembled dashboards

Unica provides pre-assembled dashboards that include portlets appropriate for various audiences.

Pre-assembled dashboard availability

Pre-assembled dashboards are available as soon as you install Unica Platform. However, to fully implement these dashboards you must also install any products required to support the portlets they include, and the portlets must be enabled.

For a pre-assembled dashboard to be available, at least one of the products that support it must be installed. For example, if a pre-assembled dashboard includes portlets that come from Unica Campaign and IBM eMessage, the dashboard will be available if either of these products is installed. If neither product is installed, the dashboard is not shown in the user interface. If one of the products is missing, the portlets that depend on that product are listed with a message indicating that they are not available.

List of pre-assembled dashboards

The following table describes the pre-assembled dashboards: their purpose, the portlets that comprise them, and the required products.

Table 19. List of pre-assembled dashboards

Pre-assembled dashboard	Purpose	Portlets	Required products
Campaign Management	This dashboard shows the financial results from campaigns.	<ul style="list-style-type: none"> • Financial Summary by Offer • Campaign Performance Comparison 	<ul style="list-style-type: none"> • Unica Campaign • Unica Campaign Report Pack
Project and Traffic Management	This dashboard provides status updates for projects.	<ul style="list-style-type: none"> • My Tasks • My Alerts • My Active Projects • My Task Summary • Projects Requested and Completed • Approvals Awaiting Action • My Approval Summary • Projects by Status 	<ul style="list-style-type: none"> • Unica Plan • Unica Plan Report Pack
Project Member	This dashboard shows tasks that require action and al-	<ul style="list-style-type: none"> • My Tasks • My Active Projects 	Unica Plan

Table 19. List of pre-assembled dashboards (continued)

Pre-assembled dashboard	Purpose	Portlets	Required products
	allows users to close completed tasks.	<ul style="list-style-type: none"> • My Alerts • My Requests 	
Project Requests and Approvals	This dashboard shows tasks that require action, and provides status updates on projects and a high level overview of the marketing financial position and where funds are being spent.	<ul style="list-style-type: none"> • Approvals Awaiting Action • My Alerts • Marketing Financial Position • Projects by Project Type • Budget by Project Type • Spend by Project Type • Completed Projects by Quarter 	<ul style="list-style-type: none"> • Unica Plan with the Financial Management Module • Unica Plan Report Pack
Project Financials	This dashboard provides a high level overview of the marketing financial position and where funds are being spent.	<ul style="list-style-type: none"> • Approvals Awaiting Action • Marketing Financial Position • Alerts 	<ul style="list-style-type: none"> • Unica Plan with the Financial Management Module • Unica Plan Report Pack

Table 19. List of pre-assembled dashboards (continued)

Pre-assembled dashboard	Purpose	Portlets	Required products
		<ul style="list-style-type: none"> • Projects by Type • Completed Projects by Quarter 	

IBM® Cognos® report performance considerations

Reports are desirable components to add to dashboards because they add a visual element that makes it easy to scan large amounts of data. However, because reports require additional processing resources, performance can become an issue when many users access dashboards that contain many reports on a regular basis.

While organizations use data in different ways tailored to their needs, this section provides some general guidelines that should help you improve performance for dashboards that contain IBM® Cognos® reports. All of these guidelines apply to IBM® Cognos® report portlets, which are the most resource-intensive.

Scheduling runs in IBM® Cognos®

IBM® Cognos® reports can be scheduled to run at regular intervals. When a report is scheduled, it does not run every time a user accesses a dashboard containing that report. The result is improved performance of dashboards containing the report.

Only Unica reports that do not contain a user ID parameter can be scheduled in Cognos®. When a report has no ID parameter, all users see the same data; the data is not filtered based on the user. The following portlets cannot be scheduled.

- All of the Unica Campaign pre-defined portlets
- The Unica Plan My Task Summary and My Approval Summary pre-defined portlets

Scheduling reports is a task that you perform in IBM® Cognos®; consult the Cognos® documentation to learn more about scheduling in general. For specific scheduling requirements for dashboard portlets, see [Scheduling a dashboard report \(on page 60\)](#).

Data considerations

You should plan scheduled runs based on the data contained in the report. For example, you would run the Offer Responses for Last 7 Days dashboard report every night so that it contains information relevant to seven days preceding the current day. In contrast, you might choose to run the Marketing Financials Position dashboard report once a week, because it compares financial indicators on a quarterly basis.

User expectations

An additional scheduling consideration is how frequently the intended users of the report expect the data to be updated. You should consult users about this when planning schedules.

Guidelines

Here are some broad guidelines to help you plan scheduling for dashboard IBM® Cognos® reports.

- Reports that include roll-up information should generally be scheduled to run every night.
- Reports that contain many calculations should be placed on a schedule.

Scheduling a dashboard report

To schedule a dashboard report (either a pre-defined or user-created portlet), you must first create a view and schedule it, and then configure the portlet as described here.



Note: You can schedule only those reports that are not filtered by user.

1. In Cognos®, copy the report and save it under a new name.
2. In Cognos®, open the copied report and save it as a view with the same name as the original report. Save it in the `Unica Dashboard/Product` folder, where `Product` is the appropriate product folder
3. In Cognos®, schedule the view.
4. In Unica, add the report to the dashboard, if you have not done so already.
5. Only if the report is one of the pre-defined portlets, do the following in Unica.
 - On the Dashboard Administration page, click the **Edit portlet** icon next to the portlet.
 - Select **Yes** next to **Has this report been scheduled?**
 - Click **Save**.

Dashboard setup

Topics in this section describe how to set up dashboards.

Permissions required to administer dashboards

Only users with the Administer Dashboards permission in a partition can administer all of the dashboards in that partition. By default, this permission is granted to users with the AdminRole role in Unica Platform.

When Unica Platform is first installed, a pre-defined user, `asm_admin`, has this role for the default partition, `partition1`. See your administrator for the appropriate dashboard administrator credentials.

A user with the AdminRole role in Unica Platform can assign any Unica user to administer individual dashboards in the partition to which that user belongs. Dashboard administration is done in the dashboard administration area of Unica Platform.

Dashboard layout

The first time you add a portlet to a new dashboard, a window opens prompting you to select and save a layout. You can change the layout later by selecting the tab for the dashboard and selecting a different layout.

The options are as follows.

- 3 columns, equal width
- 2 columns, equal width
- 2 columns, 2/3-1/3 width
- 1 column, entire width
- Custom

Dashboards and partitions

If you are administering dashboards in a multi-partition environment, read this section to understand how multiple partitions affect dashboards.

In a multi-partition environment, a user can view or administer only those dashboards associated with the partition to which the user belongs.

When a dashboard administrator creates a dashboard, the following partition-related rules apply.

- Any dashboard that is created is available only to members of the same partition as the user who created it.
- Only those pre-defined portlets that are enabled in the partition to which the administrator belongs are available for inclusion in the dashboard.
- Only groups and users assigned to the same partition as the administrator are available for assignment to the dashboard.

Overview of working with dashboards in a multi-partition environment

When you have multiple partitions configured, follow these guidelines when you set up dashboards.

1. Before working with dashboards, associate one or more groups with each partition, and assign the appropriate users to each group.

Only the platform_admin user, or another user with the PlatformAdminRole permissions can perform this task.

2. For each partition, ensure that at least one user has the Administer Dashboards permission, and make a note of these user names.

The Unica Platform AdminRole role has this permission by default, but you might want to create a role with more restricted access for dashboard administrators. These dashboard administrators can administer all dashboards within their partition.

3. For each partition configured in your system, do the following.
 - a. Use an account that is a member of the partition and that can administer all dashboards in a partition to sign in to Unica.

Refer to the list of users you created in the previous step.

- b. On the **Settings > Dashboard portlets** page, enable pre-defined portlets as needed.
- c. On the Dashboard Administration page, create the needed dashboards and add portlets.
- d. For each non-global dashboard, assign users who can view the dashboard.

You can assign individual users or groups to the dashboard.

- e. For each dashboard, assign one or more users as dashboard administrator.

Enabling or disabling pre-defined portlets

Perform this task before you begin to create dashboards. You should enable only those portlets that reference Unica products that you have installed.

1. Log in to Unica and select **Settings > Dashboard portlets**.
2. Click the check box next to portlet names to enable or disable them.

A check mark enables a portlet, and clearing the check box disables a portlet.

The portlets you selected are enabled and are available for inclusion in dashboards.

Creating a dashboard that is not pre-assembled

Use this procedure to create a dashboard that is not pre-assembled

1. In Unica, select **Dashboard** to open the Dashboard administration page.

All dashboards associated with your partition are shown.

2. Click **Create dashboard** to open the Create dashboard page.
3. Enter a unique title (required) and description (optional).
4. Select basic permissions.
 - If you want to restrict access to users who belong to a group associated with the dashboard, select **User or group-specific dashboard**.
 - If you want all users in the partition to be able to view the dashboard, select **Global dashboard for everyone**.
5. For the **Type** select **Create dashboard**.
6. Click **Save**.

Your new dashboard appears as a tab on the Dashboard administration page, and is listed on the Administration tab.

You can now add portlets.

Creating a pre-assembled dashboard

Use this procedure to create a pre-assembled dashboard.

1. Ensure that the portlets that comprise the pre-assembled dashboard you want to create are enabled.
2. In Unica, select **Dashboard** to open the Dashboard administration page.
3. Click **Create dashboard**.
4. For the **Type** select **Use pre-assembled dashboards**.

The available pre-assembled dashboards are listed.

5. Select the pre-assembled dashboard you want to use and click **Next**.

A list of the portlets comprising the selected pre-assembled dashboard is displayed. The list lets you know when a portlet is not available, either because the required product is not installed or because the portlet has not been enabled.

6. Click **Save** to finish creating the dashboard.

Your new dashboard appears as a tab on the Dashboard administration page, and is listed on the Administration tab. You can now modify the portlets it contains, if necessary.

Adding a pre-defined portlet to a dashboard

Use this procedure to add a pre-defined portlet to a dashboard.

1. In Unica, select **Dashboard** and then select the tab for the dashboard you want to work with.
2. Click **Manage portlets** to view a list of enabled portlets.

You can also access the Manage portlets page from the Administration tab, by clicking the Manage Portlets icon on the dashboard.

3. Select the check box next to one or more portlets to select it for addition to the dashboard.

Use the following features to assist you in selecting portlets.

- Filter the list of portlets by name or by the product that is the source of the portlet.
- Display all portlets at once or page through the list.
- Click column headings to sort the list alphabetically by source or portlet name, in ascending or descending order.

4. Click **Update**.

The selected portlets are added to the dashboard.

Removing a portlet from a dashboard

Use this procedure to remove a portlet from a dashboard.

1. In Unica, select **Dashboard**.

A Dashboard Administration page opens. All dashboards associated with your partition are shown, with their portlets listed.

2. In the dashboard where you want to remove a portlet, click the **Delete** icon next to the portlet you want to remove.
3. Click **Yes, Delete** at the prompt.

The portlet is removed from the dashboard.

Changing the name or properties of a portlet

Use this procedure to change the name or properties of a portlet.

1. In Unica, select **Dashboard**

A Dashboard Administration page opens. All dashboards associated with your partition are shown, with their portlets listed.

2. In the dashboard you want to work with, click the **Edit Portlet** icon next to the portlet whose name you want to change.

An Edit Portlet window opens.

3. Edit the name, description, URL, or hidden variables of the portlet.
4. Click **Save**.

Changing the name or properties of a dashboard

Use this procedure to change the name or properties of a dashboard.

1. In Unica, select **Dashboard**

A Dashboard Administration page opens. All dashboards associated with your partition are shown.

2. In the dashboard you want to work with, click the **Manage Settings** icon at the bottom of the dashboard.

A Settings tab opens.

3. Click the **Edit Dashboard** icon.

An Edit Dashboard window opens.

4. Edit the title, description, or type of the dashboard, enable or disable it, or change whether users can change the layout..
5. Click **Save**.

Deleting a dashboard

Use this procedure to delete a dashboard.

1. In Unica, select **Dashboard**

A Dashboard Administration page opens. All dashboards associated with your partition are shown.

2. In the dashboard you want to work with, click the **Delete Dashboard** icon at the bottom of the dashboard.
3. When prompted, click **Yes, Delete**.

The dashboard is deleted.

Assigning or changing a dashboard administrator

Use this procedure to assign or change a dashboard administrator.

1. In Unica, select **Dashboard**

A Dashboard Administration page opens. All dashboards associated with your partition are shown, with their portlets listed.

2. Click the **Manage Permissions** icon at the bottom of the dashboard you want to work with.

A Manage Permissions tab opens.

3. Click the **Manage Dashboard Administrators** icon.

A Manage Dashboard Administrators page opens. All dashboards associated with your partition are shown, with their portlets listed.

4. Select or deselect names.

Users whose names are selected have administration permissions for the dashboard.

You can do the following to find users.

- Filter the list by entering all or part of a user name in the **Search** field.
- Display all users, or only unassigned users, or only assigned users.
- Sort the list by clicking column headings.
- Display all users at once (based on your filtering criteria) or page through the list.

5. Click **Update**.

The Manage Portlets page

Refer to this table if you need help completing the fields in the Manage Portlets page.

Table 20. Fields on the Manage Portlets page

Field	Description
Filter	Enter part or all of a product name or portlet name to filter the portlet list based on the product that supplies the report or the name of the portlet.
Create Custom Portlet	Click to open a page where you can create a portlet that uses a URL you have obtained.
Create Quick Link Portlet	Click to open a page where you can create a quick link portlet.

Quick link portlets

Quick links are pre-defined links to Unica products. Some quick links enable users to perform basic actions in the Unica product within the dashboard, without navigating to the product. You can configure portlets that contain a set of quick links that you choose.

Quick links for Unica products are installed when the product is installed. As of the 9.0.0 release, only Unica Plan provides quick links. The same security considerations apply for quick links as for pre-defined portlets.

To add a quick links portlet to one of your dashboards, click **Manage Portlets > Create Quick Link Portlet** and select the quick links you want to include.

The following table describes the quick links available when Unica Plan is installed.

Table 21. List of quick link portlets

Quicklink	Function
Create New Project Request	Opens up a popup window where you can choose a project template to create a Project Request. You can also click Continue to open the Project Request wizard in the application.

Table 21. List of quick link portlets (continued)

Quicklink	Function
Create New Project	Opens up a popup window where you can choose a Project template to create a Project. You can also click Continue to open the Project wizard in the application.
Add Invoice	Opens the Add Invoice wizard in the application.
Projects	Opens the Project List page in the application.
Reports	Opens the Analytics > Operational Analytics page.
Resource Library	Opens the Asset Library page in the application.
Approvals	Opens the Approvals List page in the application.

Creating a quick link portlet

Use this procedure create a quick link portlet.

1. In the dashboard to which you want to add a quick link portlet, click **Manage Portlets**.
A Manage Portlet page opens, listing the pre-defined portlets.
2. Click **Create Quick Link Portlet**.
3. Enter a portlet name and description, and select the quick links you want to include in the portlet.
4. Click **Save** to finish creating the portlet and to add it to the dashboard.

Custom portlets

Topics in this section describe how to create and use custom portlets.

Custom portlet types and availability

You can create portlets from the following types of Unica pages.

- Any Unica IBM® Cognos® report, including Unica Interact Interaction Point Performance reports that you have customized to point to additional interactive channels. You can customize any existing dashboard reports as described in this guide, or you can customize a non-dashboard report. For details on how to customize a non-dashboard report, see the *Unica Reports Installation and Configuration Guide*.
- Quick links portlets, which you can build using pre-defined links to Unica products.
- Any Digital Analytics for On Premises or Digital Analytics for On Premises On Demand report or dashboard that auto-updates.
- Any IBM Digital Analytics report.

In addition, you can create a portlet from a page on the internet or your company intranet.

Portlets that you create yourself are available for use in any dashboard. Your custom portlets are listed in the Manage Portlets window, where you can choose to add them to a dashboard.

Authentication considerations for custom portlets

When you are planning to create portlets, you should keep in mind the following authentication considerations.

- If your portlet is a Digital Analytics for On Premises report from an installation configured to use Unica Platform for authentication or to use no authentication, or a dashboard report from any other Unica product that uses Unica Platform for authentication, users are not prompted for credentials when they view the portlet.
- If your portlet is a Digital Analytics for On Premises report from an installation that is not configured to use Unica Platform for authentication, the user must enter login credentials one time per browser session.
- If your portlet is a NetInsight OnDemand report or an internet or intranet page that requires authentication, the portlet behaves as a browser would. The user must enter login credentials in the content of the page the first time they view it during a browser session, and cookies are used to keep the user logged in.
- If your portlet is an IBM Digital Analytics report, users can view only those reports for which they have permissions in Digital Analytics. Also, if single-sign-on is enabled

with Digital Analytics, users can view Digital Analytics reports in Unica Platform dashboards without entering their credentials. Otherwise, users must enter their Digital Analytics credentials to view Digital Analytics reports in Unica Platform dashboards.

Overview of the portlet creation process

This section provides an overview of the steps for creating a portlet, which are described in detail elsewhere in this guide.

See the related references if you need more information about performing this procedure.

1. Obtain and prepare the URL of the page you want to use as a portlet.

To do this, you obtain the URL and modify it as needed.

You can create portlets from the following sources.

- Digital Analytics for On Premises report
- IBM Cognos® report
- Digital Analytics report
- NetInsight OnDemand report and pages on the internet or your company intranet

2. Add the URL to the `Platform_Admin_URL.properties` file.

The `Platform_Admin_URL.properties` file is located in the `conf` directory under your Unica Platform installation.

3. Stop and restart the Unica Platform web application.
4. Add the portlet to a dashboard.

Preparing the URL from a Digital Analytics for On Premises report

Use this procedure for reports in a Digital Analytics for On Premises installation.

1. In Digital Analytics for On Premises, display the report you want to export.

If you are using a Digital Analytics for On Premises dashboard, only the top left report on the dashboard is exported.

2. Click the **Export** icon  located in the toolbar at the upper right of the report.

The Export options window opens.

3. Complete the fields as follows.
- Select **Portlet URL** from the **Export Type** drop-down.
 - Select `Web Browser` from the **Format of Report** drop-down.
 - Specify the number of values to include in the report.
 - Specify the width of the report graphic, in pixels. Path reports self-adjust their size, regardless of the width you specify. Stacked bar reports automatically increase the width you specify by 30%.
 - Choose to hide the report header, as the portlet has a title that you can edit.
4. Click **Export**.

The report URL is displayed in a dialog box.

5. Copy the URL and paste it into a text editor.
6. Add the following to the beginning of the report URL:

`Your_HCL_Unica_URL/suiteSignOn?target=`

where `Your_HCL_Unica_URL` is the login URL for your installation of Unica.

For example, suppose you have the following information.

- Your report URL is `MyReportURL`
- The login URL for your installation of Unica is `http://myHost.myDomain:7001/unica`

Your final URL would be `http://myHost.myDomain:7001/unica/suiteSignOn?target=MyReportURL`

Preparing the URL from an IBM® Cognos® dashboard report

The format of an IBM® Cognos® dashboard portlet URL is as follows.

For information about creating dashboard reports with IBM® Cognos®, see the Unica Reports Installation and Configuration Guide.

```
http(s)://HOST.DOMAIN:port/unica/reports/jsp/dashboard_portlet.jsp?
product=Product& report=ReportName
```

where

- *Product* is the name of the Unica application's subfolder in the **Unica Dashboards** folder on the IBM® Cognos® system. That is: Campaign, Interact, or Plan for Unica Plan. (Plan was the previous name of the Unica Plan application.)
- *ReportName* is the name of the dashboard report. For example: Campaign Performance Comparison

For example,

```
http://serverX.example.com:7001/unica/reports/jsp/dashboard_portlet.jsp?
product=Campaign&report=Campaign Performance Comparison
```

If you have scheduled the report, add the following to the end of the URL:

```
&isView=true
```

Preparing the URL from a Digital Analytics report

Use this procedure for Digital Analytics reports.

If you want users to be able to view Digital Analytics reports in dashboards without having to log in to Digital Analytics, you must enable single sign-on between Unica and Digital Analytics.

1. Log in to Digital Analytics and navigate to the report that you want to add as a portlet.
2. Copy the URL shown in your browser.

The link is copied to your clipboard and is ready to be pasted into the IBM® Digital Analytics URL field in the Create Custom Portlet window in Unica Platform.

To ensure the URL is not overwritten should you copy something else before using it to create a portlet, you can paste it into a text editor.

Preparing the URL from an intranet or internet page

For portlets created from intranet or internet pages, including Digital Analytics for On Premises pages, point your browser to the desired page and copy the URL from your browser's address field.

Use the copied URL when you create your custom portlet.

Adding a custom portlet to a dashboard

Perform this procedure to add a custom portlet to a dashboard.

Before performing this procedure, you should have done the following.

- Prepared a URL as described elsewhere in this section
- Added the URL to the `Platform_Admin_URL.properties` file, which is located in the `conf` directory under your Unica Platform installation
- Stopped and restarted the Unica Platform web application

1. In Unica, select **Dashboard** and then select the tab for the dashboard you want to work with.

2. Click **Manage Portlets**.

A **Manage Portlets** window opens.

3. Click **Create Custom Portlet**.

A **Create Custom Portlet** window opens.

4. Do one of the following sets of steps, depending on the type of portlet you are adding.

If you are creating a portlet that is not a Digital Analytics report portlet, do the following.

- For the **Type**, select **Custom**.
- Complete the **Name** and **Description** fields.
- Paste the contents of your clipboard (which contains the URL you obtained earlier) into the **URL** field.

If you are creating a Digital Analytics report portlet, do the following.

- For the **Type**, select **IBM Digital Analytics**.
- Complete the **Name** and **Description** fields.
- Paste the contents of your clipboard (which contains the URL you obtained earlier) into the **IBM Digital Analytics URL** field.

5. Click **Save**.

The window closes and you return to the Administration tab. The new portlet is located in the upper left corner, where it may overlay a previously added portlet. Click and drag the portlet heading to place the portlet in an appropriate position in the dashboard.

Dynamic tokens

When you define a custom dashboard portlet, you can use pre-defined tokens that are replaced with the values stored in Unica Platform for the current user when the portlet is invoked.

This feature is not available for custom portlets from Digital Analytics.

The following tokens are supported.

- `<user_name>`
- `<user_first_name>`
- `<user_last_name>`
- `<user_email>`

The URL is invoked with hidden variables passed as request parameters.

The values must be present in the user details in Unica Platform. Also, you must know the names of the variables used by the target web site.

To use these tokens, enter the name value pairs in the **Hidden Variables** field of the Create Custom Portlet page. If you use multiple tokens, separate them with a semicolon.

For example, suppose you want to send a user's first and last name in a portlet URL. In this example, the receiving web site expects `fname` and `lname` to contain the user's first and last names respectively. You would complete the **URL** and **Hidden Variables** fields as follows.

- **URL** - `www.example.com`
- **Hidden Variables** - `fname=<user_first_name>;lname=<user_last_name>`

The Create Custom Portlet page

Refer to this table if you need help completing the fields on the Custom Portlet page.

Table 22. Fields on the Create Custom Portlet page

Field	Description
Type	Select the portlet type: a portlet that is not from Digital Analytics, or a portlet that is from Digital Analytics.
Name	Enter an appropriate name for the portlet.
Description	Enter a description for the portlet that lets other administrators know why it is part of this dashboard.
URL or Digital Analytics URL	Paste in your prepared URL.
Hidden Variables	Available only when the portlet is not from Digital Analytics. If your portlet requires users to log in, you can enter name/value pairs to securely send these credentials to the site. You must obtain the expected variable name from the web site.

Dashboard membership administration

Topics in this section describe how to manage dashboard membership.

The dashboard administrator

If you have been designated a dashboard administrator, you are responsible for managing the membership, layout, and content of that dashboard. This section describes how to manage dashboard membership.

Granting or removing dashboard membership

Use this procedure to grant or remove dashboard membership.

1. In Unica, select **Dashboard** and then select the tab for the dashboard you want to work with.
2. Click the **Manage Permissions** icon at the bottom of the dashboard you want to work with.

A Manage Permissions tab opens.

3. Click the **Manage Dashboard Users** icon.

A Manage Dashboard Users page opens.

4. Select or deselect the checkbox to grant or remove access to the dashboard.

Users whose names are selected can view the dashboard.

You can do the following to find users.

- Filter the list by entering all or part of a user name in the **Search** field.
- Display all users, or only unassigned users, or only assigned users.
- Sort the list by clicking column headings.
- Display all users at once (based on your filtering criteria) or page through the list.

5. Click **Update**.

The Unica Scheduler

The Unica Scheduler enables you to configure a process to run at intervals that you define.

Items that you can schedule

You can schedule the following.

- Unica Campaign flowchart runs



Note: The Unica Scheduler is completely independent of the Schedule process in Unica Campaign.

- Unica Optimize optimization session and post-optimization flowchart runs
- IBM eMessage mailings
- Unica Plan bulk deactivations
- Calls to external APIs
- Unica alerts and notifications
- External batch or shell scripts

Schedules and runs

The scheduler uses two basic concepts: schedules and runs.

- A schedule is any task that you want to run once or on a recurring basis. When you define a schedule you specify the Unica object, the start and end dates, and optionally, the frequency with which the task is run (called a recurrence pattern).
- A run is an execution instance of a schedule.

Types of schedules

There are three types of schedules.

- Time-based - Runs occur at specified times.
- Trigger-based - Runs occur when a schedule receives a specified trigger (for example, when another schedule sends a trigger on success or failure of its run, or when the scheduler utility sends a trigger).
- Multiple-run-based - Runs are dependent on other schedules, and occur only when multiple other schedules have finished their runs

Schedule notifications

You can set up notifications that are sent to yourself for schedules you create, and administrators can set up notifications that are sent to groups of users for schedules created by anyone.

Scheduler triggers that are sent on success or failure of runs

When you create or edit a schedule, you can configure a trigger that the schedule sends on success or failure of a run, and you can also configure one or more schedules to listen for these triggers.

Triggers work across products. For example, a Unica Campaign flowchart can send a trigger that starts an IBM eMessage mailing.

A trigger is a text string that the Unica Scheduler can send when a run completes successfully or when a run fails. Each schedule can send one trigger on successful conclusion of a run, and one trigger on failure of a run. Also, each schedule can listen for one success and one failure trigger.

All schedules set to listen for a trigger receive all sent triggers, but a schedule initiates a run only if it receives the trigger for which it is listening. An unlimited number of dependencies between schedules can be created in this manner.

After you have created a trigger, it appears in a dropdown list of triggers in the scheduler user interface, which makes it easy to use again.

Trigger example

You can schedule a set of Unica Campaign flowcharts to run at the same time by configuring them to all listen for the same trigger, which can be sent by any other schedule or by an external application using the [scheduler_console_client \(on page 330\)](#) utility. You can also use triggers to cause a set of flowcharts to run in series, one after another.

The following example illustrates how to set up a series of flowcharts to run in a specified order.

- Flowchart 1 is scheduled with a "Flowchart 1 run complete" trigger that is sent when the run completes successfully.
- Flowchart 2 is scheduled as follows.

- Start when a "Flowchart 1 run complete" trigger is received.
- Send a "Flowchart 2 complete" trigger when the run completes successfully.
- Flowchart 3 is scheduled to start when a "Flowchart 2 run complete" trigger is received.


About start triggers

A schedule that is set up with a start trigger begins to listen for a trigger as soon as it is created, regardless of its start date. However, the trigger does not override the start date. For example, if a schedule has a start date of December 12, 2016 and on December 5, 2016 it receives its start trigger, the run does not start until December 12, 2016.

Schedules that depend on completion of multiple runs

You can configure a schedule to run only when multiple other schedules have finished their runs by using the **On completion of other tasks** option in the **When to start** drop down list.

For example, suppose you have a schedule, S1, that is set up with a recurrence pattern. S1 has a trigger that is sent every time an S1 run completes successfully. Three schedules, S2, S3, and S4, are configured to start when they receive the outbound trigger from S1. You can set up an additional schedule, S5, that runs when S2, S3, and S4 complete successfully. S5 runs only when all three of the runs on which it is dependent complete. The following diagram illustrates this example.



To set up a scenario like the one described in the example, you would configure S5 using the **On completion of other tasks** option in the **When to start** drop down list.

When you configure a run to be dependent on other runs in this way, you must keep in mind the following considerations.

- The schedules on which the schedule you are configuring depends must be non-recurring. In the example above, S2, S3, and S4 must be non-recurring. However, because S1 recurs, S2, S3, and S4 effectively recur, based on S1 runs.
- The schedule that is dependent on other schedules must also be non-recurring. In the example, S5 must be non-recurring. Again, because S1 recurs, S5 effectively recurs as well.
- The schedule that is dependent on other schedules cannot be used as one of the criteria in the **On completion of other tasks** option for any other schedule. In the example, S5 cannot be used as a criterion in the **On completion of other tasks** option for any other schedule.
- If you want to delete a schedule that is configured with the **On completion of other tasks** option, you must first change the configuration to remove the **On completion of other tasks** option. Then you can delete the schedule.

Schedule triggers that are sent from an external script

The Unica Scheduler can respond to triggers sent by an external application. The `scheduler_console_client` utility enables this feature. This utility issues triggers that can launch one or more schedules set up to listen for that trigger.

Because `scheduler_console_client` is a batch script application, it can be called by external applications, possibly using another batch script.

For example, if you set up a schedule that is listening for a trigger "T1," you could run the `scheduler_console_client` utility with the following command to send the T1 trigger:

```
scheduler_console_client.bat -v -t T1
```

The utility can provide the following information.

- A list of the schedules that are configured to listen for any given trigger.
- Whether it has successfully sent the trigger. Note that the utility cannot report whether the schedule that is listening for the trigger executed successfully. That information is available on the scheduler management pages.

You can not use this utility to set up a schedule to listen for a trigger or to modify a trigger for which a schedule is listening. You must perform these actions in the scheduler user interface.

Example script

Here is an example of a script to that causes the `scheduler_console_client` utility to issue the string "example_trigger". This trigger would set off a run of a schedule set up to listen for "example_trigger".

You could call a script like this from an external application when that application generates an event.

The example script assumes that the script is in the same directory as the utility.

```
@rem*****
@rem This script is used to call the Platform
@rem scheduler_console_client.
@rem*****

echo Now starting scheduler trigger.
set JAVA_HOME=c:\jdk15_12
call scheduler_console_client.bat -v -t example_trigger

@rem*****
```

Security considerations

Scheduling within the enterprise applications is considered to be an administrator's activity. It is assumed that any user who has execute permission in the host operating system for the `scheduler_console_client` utility is also authorized to issue triggers.

To prevent any user from using this utility to issue a trigger, you should revoke execute permission for the `scheduler_console_client` utility for that user.

Scheduler recurrence patterns

You can set up a schedule to run repeatedly by configuring a recurrence pattern. Any recurrence pattern you set begins after the start time you specify.

You have several recurrence pattern options.

- Pre-defined - A set of common recurrence patterns from which you can select
- Cron expression - A string composed of 6 or 7 fields separated by white space that represents a set of times
- Simple custom recurrence pattern - A user interface for creating recurring patterns that is similar to many common meeting schedulers

All of the scheduler recurrence patterns are based on cron expressions. The scheduler provides pre-defined patterns in the user interface for easier creation of these cron expressions. If you write your own custom cron expression, it is a good practice to provide a meaningful description of the recurrence pattern, to make it easier for anyone who is not fluent in reading these expressions to understand the pattern.



Important: All of the recurrence patterns reset at the end of the next longer interval. For example, if you set a custom weekly pattern to run every three weeks, it runs the third week of every month, because the pattern resets at the end of every month. This is a characteristic of all cron expressions. To set a schedule that actually runs on week 3, 6, 9, 12, and so on, you must create separate schedules for each desired execution date.

Time zone support

You can schedule runs to occur in the context of any one of a large number of worldwide time zones.

When you create a schedule, the default is always the time zone of the server on which Unica Platform is installed. However, you can select from any other time zones listed in the **Select time zone** drop down list. These options are expressed as GMT times followed by the commonly used term for that time zone. For example, (GMT-08:00) Pitcairn Islands or (GMT-08:00) Pacific Time (US & Canada).

The selected time zone is applied to all aspects of the schedule, including the following.

- Information shown on the Schedules and Runs tabs
- Recurrence patterns and triggers

Scheduler throttling

Throttling is used to manage performance when a large number of processes are likely to place high demands on the system. Throttling is based on scheduler groups that you set up on the **Settings > Configuration** page. You assign a throttling threshold to a group, and associate schedules with that group.

The throttling threshold is the highest number of runs associated with that group that can run concurrently. To reduce resource consumption on the server, you can set the throttling threshold to a smaller value. Only schedules created in the Unica Scheduler are subject to throttling.

Unlimited threshold in the default group

All schedules must belong to a throttling group. If you do not want to enable throttling for a schedule, make it a member of the Default scheduler group (the default selected option in the **Scheduler Group** field when you create a schedule). This group has a high throttling threshold, which effectively means that no throttling is in place.

Throttling exception

If you run a flowchart from within Unica Campaign or by using the Unica Campaign `unica_svradm` utility, these runs do not count in the throttling threshold, and they begin execution immediately.

Throttling examples

- If system resources are a concern, you can use throttling to manage the load on a server. For example, if many complex Unica Campaign flowcharts must be run, you can assign them to a throttling group that limits the number of flowcharts that can be run at the same time. This throttling helps to manage the load on the Unica Campaign server or the marketing database.
- You can use throttling to set priorities for schedules. By assigning high-priority schedules to a group with a high throttling threshold, you ensure that runs of these schedules are performed using system resources as efficiently as possible. You should assign lower-priority schedules to groups with lower throttling thresholds.
- If you have a flowchart that is scheduled with a recurrence pattern, you can use throttling to ensure that runs occur in sequence, without overlapping. For example, suppose you have scheduled a flowchart with a recurrence pattern set to execute a run every hour for 10 hours. If the flowchart takes more than one hour to complete a run, the next run could attempt to begin before the previous run is completed, resulting in failure because the still running flowchart would be locked. To ensure that this does not happen, you can create a throttling group with a threshold of 1, and assign the flowchart's schedule to this group.

Setting up throttling for the Unica Scheduler

You must set up a throttling group for each type of object being scheduled.

1. On the Configuration page, navigate to one of the throttling group templates under `Platform > Scheduler > Schedule registrations > [Product] > [Object] > Throttling group`.
2. Create a category from the throttling group template.

The number you set for the `Throttling threshold` property is the highest number of runs associated with that group that can execute concurrently. Any schedules eligible to run that exceed the throttling threshold are queued to run in the order in which the run notification is received by the scheduler.

The configured scheduler groups appear in the **Scheduler Group** drop-down list in the Scheduler user interface for creating and editing schedules.

You must create a throttling group for each type of object whose runs you want to control in this way. For example, flowchart throttling groups are available only for scheduling flowcharts; mailing throttling groups are available only for scheduling mailings.

3. Assign one or more schedules to the group, as needed.

Whitelist prerequisite for external tasks (with FixPack 10.0.0.1 only)

Only if you have applied Unica Platform FixPack 10.0.0.1, a whitelist prerequisite applies to any external tasks that you create to schedule API calls or scripts.

Before you can schedule an external task, you must add the API or script to a whitelist located in the `conf` directory under your Unica Platform installation.

Adding a script to the whitelist

Only if you have applied Unica Platform FixPack 10.0.0.1, perform this procedure before you create any external tasks that schedule a script.

The script must be on the web application server where Unica Platform is deployed.

1. Open the whitelist file for scripts in a text editor.

The whitelist file for scripts is

`Platform_Admin_Scheduler_Scripts.properties`. This file is located in the `conf` directory under your Unica Platform installation.

2. Enter the full path of the batch or shell script you plan to schedule, and include the number of parameters that are used in the script you are scheduling.

For example, suppose you want to schedule a script that is named `RunETLJobs.bat` and that takes these three parameters: `username`, `password`, `db_table`.

You would make the following entry in the whitelist file. The entry includes the absolute path of the script, followed by a space and the number of parameters used.

The parameter count must exactly match the number of parameters that are used in the scheduled script.

```
C:\Scripts\RunETLJobs.bat 3
```

When you create the schedule, in the **Run parameters** field you specify the parameter names between double number signs (##) followed by a space, as shown in the following example.

```
C:\Scripts\RunETLJobs.bat ##username## ##password##
##db_table##
```

3. Save and close the whitelist file.

Now you can schedule the script on the Schedules tab of the **Settings > Schedule management** page.

Adding an API to the whitelist

Only if you have applied Unica Platform FixPack 10.0.0.1, perform this procedure before you create any external tasks that schedule an API call.

1. Open and edit the whitelist file for APIs in a text editor.

The whitelist file for APIs `Platform_Admin_Scheduler_API.properties`. This file is located in the `conf` directory under your Unica Platform installation.

2. Enter the URI of the API you plan to schedule, and if query parameters are used, include these parameter names, without including values.

For example suppose you want to schedule the following API call, using all of the query parameters shown.

```
http://www.example.com/tickets?
fields=id&state=open&sort=updated_at
```

You would make the following entry in the whitelist file, listing all of the parameters.

```
http://www.example.com/tickets?fields&state&sort
```

With this whitelist entry, you can schedule API calls that use some or all of the listed parameters. For example:

- `http://www.example.com/tickets`
- `http://www.example.com/tickets?fields=id`
- `http://www.example.com/tickets?fields=id&state=open`
- `http://www.example.com/tickets?fields=id&state=open&sort=updated_at`
- `http://www.example.com/tickets?fields=id&sort=updated_at`
- `http://www.example.com/tickets?fields=id&state=open`

API calls that use non-listed query parameters cannot be scheduled. Scheduler validation fails if any parameters are used that are not present in the whitelist.

3. Save and close the whitelist file.

Now you can schedule the API call on the Schedules tab of the **Settings > Schedule management** page.

Best practices for setting up schedules

These are some best practices for planning and configuring scheduled runs of Unica objects.

For optimal performance and ease of maintenance, keep these guidelines in mind.

- Because scheduled runs are executed on the system where the client product is installed, consider the scaling capabilities of the client system. Stagger runs or use throttling to tune the system.
- When possible, schedule heavy jobs during low system load times.
- Avoid overlapping runs, which cause run failures.
 - Use caution if you use the same object in multiple schedules. For example, if you use flowchart F1 in three schedules, these schedule definitions could cause a run to be started before a previous run completes, causing run failure.
 - If a flowchart run is initiated manually or by an external script, a subsequent attempt to run the flowchart by any means fails with a lock error if the previous run has not completed.

- The scheduler creates large quantities of data. If you observe performance issues with the scheduler, consider removing schedule definitions that you no longer need.



Important: Removing a schedule definition also removes its associated run history from the database.

To create a schedule wizard

This section describes in detail the pages you use when you create a schedule.

The following table describes the fields you use when you schedule runs of Unica Campaign flowcharts, IBM eMessage mailings, Unica Optimize sessions, external scripts, and API calls.

Table 23. Fields in the create a schedule wizard

Field	Description
Select a task type	<p>The type of object to be scheduled. The following options are available.</p> <ul style="list-style-type: none"> • External task - script Allows you to schedule invocation of tasks defined in batch or shell scripts external to Unica. Only if you have applied Unica Platform FixPack 10.0.0.1, the script must be listed in a whitelist file located in the <code>conf</code> directory under your Unica Platform installation. Also, the script must be on the web application server where Unica Platform is deployed. • External task - API Allows you to schedule invocation of APIs external to Unica. Only if you have applied Unica Platform FixPack 10.0.0.1, the API must be listed in a whitelist file located in the <code>conf</code> directory under your Unica Platform installation.

Table 23. Fields in the create a schedule wizard (continued)

Field	Description
	<ul style="list-style-type: none"> <li data-bbox="597 348 976 380">• Unica Campaign flowchart <li data-bbox="613 415 1446 604">Allows you to schedule invocation of Unica Campaign flowcharts. Selecting this option takes you to the Unica Campaign list page where you select a campaign, optionally set flowchart override parameters, and schedule the flowchart run. <li data-bbox="597 625 935 657">• Unica Optimize session <li data-bbox="613 693 1419 882">Allows you to schedule invocation of Unica Optimize sessions. Selecting this option takes you to the Unica Optimize sessions list page where you select a session and schedule the session. <li data-bbox="597 903 927 934">• IBM eMessage mailing <li data-bbox="613 970 1446 1106">Allows you to schedule invocation of IBM eMessage mailings. Selecting this option takes you to the IBM eMessage mailings list page where you select and schedule the mailing. <li data-bbox="597 1127 1003 1159">• Unica Plan bulk deactivation <li data-bbox="613 1194 1446 1383">Allows you to schedule bulk deactivation of projects in Unica Plan. Selecting this option takes you to the Unica Plan Administrative Settings page where you click Deactivation Administration and schedule the bulk deactivation. <li data-bbox="597 1404 683 1436">• Alert <li data-bbox="613 1472 1438 1661">Allows you to schedule alerts for users of Unica. Selecting this option opens a window where you set the message title, message body, and severity. After you click Schedule this alert, you can create a schedule for the alert. <li data-bbox="613 1696 1419 1770">Users can manage their notification subscriptions based on severity. <li data-bbox="597 1791 776 1822">• Notification

Table 23. Fields in the create a schedule wizard (continued)

Field	Description
	<p>Allows you to schedule notifications for users of Unica.</p> <p>Selecting this option opens a window where you set the message title, message body, and severity. After you click Schedule this notification, you can create a schedule for the notification.</p> <p>Users can manage their notification subscriptions based on severity.</p>
Schedule name	Enter a name for the schedule.
Scheduler group	If you have created one or more throttling groups, you can associate this schedule with a group to limit the number of runs of this schedule that can execute at the same time. Throttling groups configured on the Configuration page appear as options in this field
Description	Enter a description for the schedule.
Run parameters	<p>Used when you schedule APIs and scripts.</p> <p>Only if you have applied Unica Platform FixPack 10.0.0.1, a whitelist prerequisite applies to any external tasks that you create to schedule API calls or scripts. Before you can schedule an external task, you must add the API or script to a whitelist located in the <code>conf</code> directory under your Unica Platform installation.</p> <ul style="list-style-type: none"> • For API schedules, enter the URI, plus any parameters in the format shown in the examples. <p>API with no parameters: <code>http://example.com</code></p> <p>API with parameters: <code>http://www.example.com/tickets?fields=id&state=open&sort=updated_at</code></p> <p>Currently, there is no support for Unica Platform tokens in the URI.</p>

Table 23. Fields in the create a schedule wizard (continued)

Field	Description
	<ul style="list-style-type: none"> • For script schedules, enter the full path to the script on the Unica Platform server, plus any parameters in the format shown in the examples. Specify the parameter names between double number signs (##) followed by a space. <ul style="list-style-type: none"> ◦ Windows™ examples <p>Script with no parameters: <code>C:\Scripts\ExecuteDatabaseJob.bat</code></p> <p>Script with parameters: <code>C:\Scripts\RunETLJobs.bat ##username## ##password## ##db_table##</code></p> ◦ UNIX™ examples <p>Script with no parameters: <code>/opt/ExecuteDatabaseJob.sh</code></p> <p>Script with parameters: <code>/opt/RunETLJobs.sh ##username## ##password## ##db_table##</code></p> <p>Execution of these tasks is asynchronous. Unica Platform does not track success or failure of script and API tasks. Status indicates only whether they are launched successfully.</p>
On successful completion, send a trigger	If you want runs of this schedule to send a trigger when the run completes successfully, enter the trigger text here. Other schedules can be set to listen for this trigger.
On error, send a trigger	If you want runs of this schedule to send a trigger when the run fails, enter the trigger text here. Other schedules can be set to listen for this trigger.

Table 23. Fields in the create a schedule wizard (continued)

Field	Description
Search tags / key-words	Enter any tags you want you associate with the schedule for use in searches. Separate multiple entries with commas.
Schedule status	Whether the schedule is enabled or disabled. Disabling a schedule applies only to future or queued runs of that schedule. Any run currently underway is not affected. The default status is Enabled .
Select time zone	If you select an option other than the server default, the Start, End, and Last updated columns on the Schedule management page show both the server default time and the time in the selected zone.
When to start	<p>Select one of the following options to specify the first time the schedule runs. The start time applies only to the first run; it defines the time when a schedule is first eligible to run. The actual first run might be after the start date if any of the following conditions are present.</p> <ul style="list-style-type: none"> • The schedule is configured to wait for a trigger. • The schedule is a member of a throttling group. • The schedule uses a recurrence pattern. <ul style="list-style-type: none"> • Now • On a date and time - Select a date and time. • On a trigger - Select an existing trigger or enter a new one. If you enter a new one, you must configure a schedule to send this same string on success or failure. • On a trigger after a date - Select an existing trigger or enter a new one, and select a date and time. If you enter a new trig-

Table 23. Fields in the create a schedule wizard (continued)

Field	Description
	<p>ger, you must configure a schedule to send this same string on success or failure.</p> <ul style="list-style-type: none"> • On completion of other tasks - Select from a list of existing schedules. The schedule runs only when the selected other schedules have finished their runs.
Number of runs	<p>Select one of the following options to specify the number of runs.</p> <ul style="list-style-type: none"> • Run once only - The schedule runs one time. It is eligible to execute the run on the start date and time you specify. • Stop after n occurrences - Runs stop after the specified number of runs have occurred (whether the runs succeed or fail) or the end date arrives, whichever is first. • Stop by a date and time - Runs are initiated as many times as defined until the specified end date and time is reached. A run might execute after this time if the run execution has been delayed due to throttling constraints. • On completion of other tasks - The schedule runs only when all the other tasks selected for this option complete successfully. <p>When you click the Set up recurrences button, you can select one of the following options.</p> <ul style="list-style-type: none"> • Use a pre-defined recurrence pattern - Select a pattern from the list. The Unica Platform provides a set of pre-defined patterns, and you can create your own by adding properties on the Configuration page. • Use a simple custom recurrence pattern - Select an interval. • Use a cron recurrence expression - Enter a valid cron expression.

Run exclusions

10.0.02 From the 10.0 Fix Pack 2 release onwards, you can create exclusion rules to exclude the scheduler run for certain days or time. You can add multiple rules for various schedules.

You can create exclusion rules for specific schedules or apply a single rule to multiple schedules. You can also enable or disable the rules, or delete the exclusion rules if they are no longer required.

The Run exclusions feature is available when you upgrade to the 10.0 Fix Pack 2 release.

Two new system tables are introduced for this feature. For details about the system tables, see the Unica Platform System Tables guide.

Viewing exclusion rules

Exclusions rules that are already defined for schedules can be viewed from the Run exclusions tab of the Schedule Management page.

The information in the **Previous 1 and next 2 runs** field is shown as per the scheduler definition. It is not currently validated against the exclusion rules.

To view exclusion rules, complete the following steps:

1. Log in to Unica Platform as the administrator.
2. Click **Settings > Schedule management**.
3. Click **Run exclusions**.

You can view the exclusion rules and complete various tasks for the rules. You can also view the status of the rules, the various schedules for which they are applicable, exclusion period, and exclusion type for the rules.

You can also search for exclusion rules by using a wildcard search in the **Filter** text box.

Adding exclusion rules

Exclusion rules can be added for schedules and runs. You can add Absolute or Relative rules, and select the schedules for which the rules will be applicable.

Absolute exclusion rules are set for a set time period. Relative exclusion rules are set only once and was limited to a yearly only. From 11.0 release onwards, in addition to yearly relative date, weekly and monthly date time should be configurable. Exclusion Rules can be enabled or disabled, and can be applied to multiple schedules.

To add an exclusion rule, complete the following steps:

1. Log in to Unica Platform as the administrator.
2. Click **Settings > Schedule management**.
3. On the **Run exclusions** tab, click **Add exclusion rule**.
4. On the **Rule definition** tab, specify the **Rule name**.
5. **Optional:** Specify the **Description**.
6. Select the **Rule status** as **Enabled** or **Disabled**.

By default, **Enabled** is selected.

7. Select the **Exclusion type**.

If you select **Absolute**, complete the following steps:

- a. Select the **Time Zone**.

By default, the Server default time zone is selected.

- b. Select the **Start date and time**.
- c. Select the **End date and time**.

If you select **Relative**, complete the following steps:

- a. Select the Time Zone. By default the server time zone is selected.
- b. Select when to start. 1.Now 2.On a date and time - Select a date and time.
- c. Configuring the recurrence pattern to set up relative run Exclusion. Any recurrence pattern you set begins after the start time and End Time you specify. Recurrence pattern options are 1.For weekly user should be able to select one or more day of the week, associated with a start date end time. 2.For monthly user should be able to select a day in a month, associated with a start and end time. 3.For yearly user should be able to select a day in the year, associated with a start and end time.

- d. Select Stop after n occurrences - Relative Run Exclusion Rule stop after the specified number of runs have occurred (whether the Relative Run Exclusion Rule succeed or fail)
- e. Select Stop by a date and time - Relative Run Exclusion Rule are initiated as many times as defined until the specified end date and time is reached.



Note: A single date of the current year can be selected. Schedules are skipped for the entire day when you select a relative date.

8. On the **Eligible schedules** tab, select the schedule for which you want to apply the exclusion rule by completing the following steps:
 - a. Search for the available schedules by entering a wildcard search in the **Filter** text box.
 - b. From **Available schedules**, select the schedules.
 - c. Click .

The selected schedules are moved to the **Selected schedules** table.
 - d. Click **Save**.
9. Click **Save**.

Deleting exclusion rules

You can delete the exclusion rules that are available in your system only if the rules are not associated with any schedules or runs.

To delete an exclusion rule, complete the following steps:

1. On the **Run exclusions** tab, select the rule that you want to delete.



Note: Ensure that the exclusion rule that you want to delete does not have any schedule or run associated with it.

2. Click **Delete**.
3. Confirm the deletion.

Enabling and disabling exclusion rules

You can enable and disable exclusion rules while you create the rules or after you create the rules. By default, a new rule that is created is always Enabled.

When exclusion rules that are applied to schedules are disabled, all schedule runs continue to run as before. When exclusion rules are enabled, the rules are applied to the schedules and schedules are run as per the exclusion criteria that are applied.

To enable or disable an exclusion rule, complete the following steps:

1. On the **Run exclusions** tab, select a disabled rule.
2. Click **Enable**.

The status of the rule changes to Enabled.

3. To disable a rule, select an enabled rule.
4. Click **Disable**.

The status of the rule changes to Disabled.

Importing exclusion rules

You can import exclusion rules to apply them to schedules or runs in the system. You can import the rules through an XML file.

The XML file in the specific format must be available to import the exclusion rules. The format of the XML file can be viewed when you click **Import exclusion rules** on the UI.

A sample exclusion rule file is provided with installation and is available in the `<platform_home>\conf\` directory as the `Exclusion_Rule.xml` file.

To import exclusion rules, complete the following steps:

1. On the **Run exclusions** tab, click **Import exclusion rules**.
2. Use the format that is provided to create the XML file to import the rules.

3. Click **Browse** to select the file.
4. Click **Save**.

Understanding the XML file to import exclusion rules

The XML file that can be used to import exclusion rules has certain tags that define the exclusion rules.

Tags in the XML file

The following table lists the tags in the XML file that can be used to import exclusion rules.

Table 24. Tags in the XML file

Tag	Description
ruleName	Name of the exclusion rule.
ruleDescription	Description of the exclusion rule.
ruleStartDate	Date on which the exclusion rule starts. The format of the date must be MM/DD/YYYY.
ruleStartTime	Time at which the exclusion rule starts. The format of the time must be HH:MM:SS.
ruleEndDate	Date on which the exclusion rule ends. The format of the date must be MM/DD/YYYY.
ruleEndTime	Time at which the exclusion rule ends. The format of the time must be HH:MM:SS.
SchedulerID	IDs of the scheduler on which the exclusion rule must be applied. Multiple scheduler task IDs can be specified. The IDs of the scheduler tasks are available in the <code>USCH_TASK</code> table in the database.
ruleStatus	Status of the exclusion rule. The value can be <code>Enabled</code> or <code>Disabled</code> .

By using the tags, you can define multiple exclusion rules. Reuse the rule tags and modify them as required to define multiple rules.

Example of the XML file to import exclusion rules

An example of the XML file that is used to import exclusion rules is provided for users to reuse the tags and modify the values to create a new XML file according to your requirements.

The following XML tags can be used to create an XML file to import exclusion rules.

```
<rules>
  <rule>
    <ruleName>Rule1</ruleName><!-- specify rule name -->
    <ruleDescription>Rule for skipping 1/13 to 1/19.</ruleDescription><!--
specify rule description -->
    <ruleStartDate>1/13/2017</ruleStartDate><!-- specify exclusion start
date. This should be of format MM/DD/YYYY -->
    <ruleStartTime>8:00:00</ruleStartTime><!-- specify exclusion start time.
This should be of format HH:MM:SS-->
    <ruleEndDate>1/19/2017</ruleEndDate><!-- specify exclusion end date. This
should be of format MM/DD/YYYY -->
    <ruleEndTime>18:15:00</ruleEndTime><!-- specify exclusion end time. This
should be of format HH:MM:SS -->
    <SchedulerIDs>
      <SchedulerID>10</SchedulerID> <!-- specify scheduler task Ids, on which
this rule should get applied. This needs to be obtained from database. -->
      <SchedulerID>15</SchedulerID>
    </SchedulerIDs>
    <ruleStatus>Enabled</ruleStatus> <!-- specify exclusion rule status.
valid values Enabled/Disabled -->
  </rule>
</rules>
<rules>
```

```

<rule>
  <ruleName>Rule2</ruleName><!-- specify rule name -->
  <ruleDescription>Rule for skipping 2/6 to 2/10</ruleDescription><!--
specify rule description -->
  <ruleStartDate>2/6/2017</ruleStartDate><!-- specify exclusion start date.
This should be of format MM/DD/YYYY -->
  <ruleStartTime>00:00:00</ruleStartTime><!-- specify exclusion start time.
This should be of format HH:MM:SS-->
  <ruleEndDate>2/10/2017</ruleEndDate><!-- specify exclusion end date. This
should be of format MM/DD/YYYY -->
  <ruleEndTime>23:59:59</ruleEndTime><!-- specify exclusion end time. This
should be of format HH:MM:SS -->
  <SchedulerIDs>
    <SchedulerID>45</SchedulerID> <!-- specify scheduler task Ids, on which
this rule should get applied. This needs to be obtained from database. -->
    <SchedulerID>88</SchedulerID>
  </SchedulerIDs>
  <ruleStatus>Disabled</ruleStatus> <!-- specify exclusion rule status.
valid values Enabled/Disabled -->
</rule>
</rules>

```

What to consider when you use the scheduler with Unica Campaign

Some special configuration applies when you use the Unica Scheduler with Unica Campaign

- Manual starts of flowchart runs or command-line flowchart commands have no effect on the scheduler, and vice versa with one exception. If a flowchart run is initiated by any means, a subsequent attempt to run the flowchart by any means fails with a lock error if the previous run has not completed.
- Scheduler triggers do not interact in any way with Unica Campaign flowchart triggers. Triggers sent by the Schedule process or by the Unica Campaign trigger utility `unica_actrg` cannot cause schedules in the Unica Scheduler to run, and vice versa.

Difference between the Unica Campaign Schedule process and Unica Scheduler

Starting with the 8.0 release of Unica Platform, the Unica Scheduler is intended to replace the Unica Campaign Schedule process for scheduling runs of an entire flowchart. The Unica Scheduler is more efficient, as it does not consume any server system resources when the flowchart is not actually running.

The Unica Scheduler starts a flowchart even if it is not running, while the Unica Campaign Schedule process in a flowchart works only if the flowchart is running.

The Unica Campaign Schedule process is preserved for full compatibility with earlier versions, and for other use cases not handled by the Unica Scheduler. For example, you might want to use the Unica Campaign Schedule process to send Unica Campaign triggers or to delay execution of dependent processes.

Do not use the Unica Scheduler to schedule a flowchart that uses the Unica Campaign Schedule process as the top-level process that starts a flowchart run. Typically, only one or the other is necessary. However, if the Schedule process appears in a flowchart that is started by the Unica Scheduler, it functions as configured; conditions required by the Unica Scheduler and the Schedule process must be met before subsequent processes run.

Unlike the Unica Scheduler, the Unica Campaign Schedule process can send external triggers to call command-line scripts. The Unica Scheduler can send triggers only to its own schedules.

Permissions for scheduling flowcharts

Scheduling Unica Campaign flowcharts using the Unica Scheduler requires the following permissions.

Table 25. Permissions for scheduling

Permission	Description
Schedule Batch Flowcharts	Allows scheduling flowcharts using the default run parameters
Schedule Override Batch Flowcharts	Allows overriding the default run parameters for scheduling flowcharts
Run Batch Flowcharts	Allows running flowcharts (required for scheduled flowcharts to run successfully)



Note: When a scheduled flowchart runs, it is run by the Unica Platform user that created the scheduled task. If this user account is disabled or deleted, any flowcharts previously scheduled by that user will fail to run. If you want to deactivate this user account but allow these previously scheduled flowcharts to run, leave the user account status set to "active" with only the Run Batch Flowcharts permission granted.

Creating a flowchart schedule using default parameters

To schedule a flowchart using the default parameters, complete the following steps.

1. On the **Flowchart** tab in **View** mode, click the **Schedules** icon and select **Schedule This**. This opens the Override Flowchart Parameters window. All parameters are optional in this screen.
2. Click the **Schedule a Run** button located at the lower pane. This opens a window which allows you to schedule a flowchart using default parameters.

3. Complete the fields in the **Schedule flowchart** box. If you choose to run more than once, click **Set up Recurrences** to set up a recurrence pattern.
4. Click **Run** with this schedule.

About overriding the default parameters for Unica Campaign flowchart run schedules

You can override the default run parameters when you schedule a flowchart run.

When you schedule a Unica Campaign flowchart run, the scheduler uses the default run parameters that have been defined for the flowchart. These parameters include the following:

- The table catalog containing the table mappings that the flowchart uses
- Any user variables values that have been defined within the flowchart
- Login information for any data sources that the flowchart accesses. The default is the user who is scheduling the flowchart.

Unica Campaign allows you override these defaults to run against different data sources or to achieve different results, similar to the capabilities provided by the `unica_svradm` utility. For example, you could schedule multiple runs for a single flowchart to test different combinations of values for user variables. You could specify an alternate table catalog to switch from your production database to a sample database for these test runs. If your organization requires different database logins for test runs and production runs, you can specify the appropriate login information.

Run parameters for scheduling Unica Campaign flowcharts

When you schedule a Unica Campaign flowchart, the flowchart can pass a string containing run parameters to the Unica Scheduler. This string is then passed back to Unica Campaign when a run is started.

In Unica Campaign, all of the values set on the **Override Flowchart Parameters** dialog are passed to the scheduler as a single string. This string is displayed in the **Run parameters** field.

Creating a flowchart schedule

Follow this procedure to schedule a flowchart.

1. On a flowchart tab in **View** mode, click the **Schedules** icon  and select **Schedule**.

The Override flowchart parameters for dialog box opens.

2. If you want to override the default flowchart parameters, complete the fields in the dialog box to specify your flowchart parameters. This step is optional.

You can add multiple user variables and data sources by clicking the **Add user variable** and **Add data source** links.

The system does not check syntax of the parameters you enter in these fields. Double-check that you have entered the correct values before proceeding.

If you do not want to override default flowchart parameters, go on to the next step.

3. Click **Schedule a run** to open the Create a schedule dialog box.

You can define when the schedule runs and optionally set up recurrences, triggers, and throttling.

4. Click **Run with this schedule**.



Important: When you schedule a flowchart, the scheduled task is based on the flowchart name. If the flowchart name is changed after a scheduled task is created, the scheduled task fails.

The Override Flowchart Parameters page

The following table describes the fields on the Override flowchart parameters dialog. All of the editable fields in this dialog are optional. The system does not check syntax of the parameters you enter in these fields. Double-check that you have entered the correct values before proceeding.

The values you enter in this dialog are shown on the next page of the wizard in the **Run parameters** field.

Table 26. Fields on the Override Flowchart Parameters page

Field	Description
Flowchart Id	Unique ID for the flowchart. This field is filled automatically, and is read-only.
Campaign - Flowchart name	The name of the campaign, campaign code, and flowchart name. This field is filled automatically, and is read-only.
Catalog file name	Specify a stored table catalog file to use for this run.
User variable name	Enter the name of any user variable that has been defined within the flowchart.
Value	Enter a value for the user variable.
Data source name	Enter the name of any data source that the flowchart accesses.
Login	Use this field to override the default login name for the specified data source. The default is the login name of the user who is creating the schedule.
Password	Use this field to override the default password for the specified data source. The default is the password of the user who is creating the schedule.

Schedule notifications

You can set up notifications for any schedule, to alert you to the status of scheduled runs. In addition, users with Administrator permissions in Unica Platform can set up groups to which notifications are sent.

Individual schedule notifications

You can create notifications for your schedules only after you have created and saved the schedule, not during the creation process. You can configure which statuses trigger a notification, and whether the notifications for each schedule are sent to your email account, or appear in your notification in-box, or both.

Group schedule notifications

If you want users other than the creator of a schedule to receive schedule notifications, you can enable group-based notifications. You must have administrator permissions in Unica Platform to set up group notifications.

A configuration property, **Group Name to receive the Job Notifications**, is included for each object type that can be scheduled under the **Platform | Scheduler | Schedule registration | [Product] | [Object type]** category on the **Settings > Configuration** page. All members of the group specified in this configuration property receive notifications for all schedules for that object type (for example, Campaign flowcharts).

Group members receive notifications set up for scheduled runs that have the **Long Duration** or **Not Started/Queued** status. They do not receive notifications for runs with the **On Failure, On Success, or Unknown/"Other" problem** status.

By adding or removing users in a group, you can control who receives these notifications.

Setting up notifications for schedules you create

Use this procedure to set up notifications on schedules you create. You can create notifications only after a schedule has been created and saved, not during the creation process.

1. Select **Settings > Schedule management** and click the name of the schedule for which you want to set up notifications.
2. Click **Edit job notifications** to open the My job notifications window, and then click **New**.
3. Complete the fields and click **Save**.

Deleting or modifying notifications for schedules you create

You can delete or modify any notifications you created.

1. Select **Settings > My job notifications** to open the My job notifications window.
2. To delete notifications, select the notifications you want to delete and click **Delete**.
3. To modify notifications, click the name of the notification you want to modify to open the Edit Job Notification window, where you can make and save changes.

Setting up schedule notifications for a group of users

Use this procedure to set up notifications for all schedules that are sent to groups of users that you specify. You must have administrator permissions in Unica Platform to perform this procedure.

1. On the **Settings > Configuration** page, go to the **Unica Platform | Scheduler | Schedule registrations** category.
2. For each object type for which you want to enable group-based notifications, set the value of the **Name of group to receive job notifications** property to the name of the group you want to receive notifications for this object type.

You can use existing groups or create groups for these notifications.

You might want to set up a group for each object type for which you want to enable group-based notifications.

3. On the User groups page, assign users to the group or groups that you specified in the previous step, as required.

The My job notifications page

You can configure schedule notifications on the My job notifications page.

Table 27. Fields on the My job notifications page

Field	Definitions
Notification title	Enter a name for the notification
Condition	<p>Select the status condition that causes a notification to be sent.</p> <p>You can create a different notification for each status that you want to trigger a notification.</p>

Table 27. Fields on the My job notifications page (continued)

Field	Definitions
Send the notification to	<p>Select how you want to receive the notification.</p> <p>The notification can be sent to the email account associated with your Unica user account, it can appear in your notifications in the user interface, or both.</p>
Notification status	<p>Select whether this notification is active or inactive. If you select inactive, no notifications are sent.</p>

Schedule management

You can manage all schedules from the **Settings > Schedule management** page. You must have the Administer Scheduled tasks page permission in Unica Platform to manage schedules.

These are the tabs on the Scheduled tasks page.

- Schedules - On this tab you can create schedules and view or delete schedule definitions. You can click the schedule name to edit a definition, including adding notifications and enabling or disabling the schedule.
- Runs - On this tab you can view queued and completed runs of every schedule, cancel a queued run, and delete a run. You can click the schedule name to edit a definition, including adding notifications and enabling or disabling the schedule.

Schedules and partitions

In a multi-partition environment, you see only the schedules that are created in the partition to which you belong, unless you have the PlatformAdminRole role, which allows you to see all scheduled runs across all partitions.

Unknown status

If you see a large number of runs with a status of Unknown, you can adjust the Scheduler polling frequency by setting the **Platform | Scheduler | Maximum Unknown Status Polling**

Count property on the **Settings > Configuration** page. This property specifies the number of times the Scheduler checks the status of a run before reporting a status of Unknown.

The Unknown status indicates that Unica Platform can not determine whether the job is still running, completed or failed.

If your organization has a large number of scheduled jobs, increasing polling frequency can affect performance.

The schedule list filter

You can filter the schedule list on the Runs and Schedules tabs.

You can enter text in the box at the top right of the list for a quick filter that compares your search term against the values in all of the columns in the list. If your search string is contained in any of the columns, the schedule or run is included in the search result.

For advanced search, you can click **Edit the schedule list filter** to open a window where you can set criteria to evaluate against the attributes of the listed schedules or runs.

Disabling and enabling multiple schedules (with FixPack 10.0.0.1 only)

If you have applied Unica Platform FixPack 10.0.0.1, you can select multiple schedules on the Schedules tab and disable or enable them by clicking the **Disable** or **Enable** button at the top of the list.

You can use this bulk disable and enable feature in conjunction with the filter to obtain a list of the schedules you want to disable or enable. For example, if you added search tags when you created schedules, you can filter the list to show only schedules with a specific tag.

Then you can select all of these schedules and disable or enable them with a single click.

When you disable a scheduled task, any schedules that depend on a trigger from the disabled task are not disabled, but they will not run because they will not receive the trigger.

The Schedule management pages

You access the scheduler management pages by selecting **Settings > Schedule Management** or by selecting **View when scheduled** from a flowchart's **Run** menu.

The Schedules tab

Table 28. Fields and links on the Schedules tab

Field or link	Description
 Disable	Disable one or more selected schedules. Available only if you have applied Unica Platform FixPack 10.0.0.1.
 Enable	Enable one or more selected schedules. Available only if you have applied Unica Platform FixPack 10.0.0.1.
Create a schedule	Click to open a wizard where you can set up a schedule.
Edit the schedule list filter	Click to create an advanced filter for the list.
Delete	Delete one or more selected schedules. You can select schedules by clicking in the column at the left of the schedule. To select all schedules, click at the top of the left side column.
Refresh	Click to refresh the list.
Filter	Click to create a simple filter for the list.
Schedule name	The schedule of which the run is an instance.
Schedule state	Whether the schedule is enabled or disabled.
Scheduled item	The name of the object to be run.
Item type	The type of object to be run.
Created by	The user name of the account that created the schedule.
Start trigger	If the schedule depends on a trigger, the trigger that causes the schedule to run.

Table 28. Fields and links on the Schedules tab (continued)

Field or link	Description
Start	Date and time when the first run of this task is scheduled.
Recurrence pattern	A description of the recurrence pattern.
End	Date and time when the last run of this task is scheduled.  Note: Applies to recurring scheduled tasks only.
Previous 1 and next 2 runs	Date and time of the previous run and next two scheduled runs.  Note: Applies to recurring scheduled tasks only. The information about previous one and next two scheduled runs is shown as per the scheduler definition. It is not currently validated against the exclusion rules.
Dependencies	If the scheduled object depends on other objects, they are listed here.
On success trigger	The string that is sent if the product reports that a run of this schedule has completed successfully. This field is blank if no on success trigger is specified.
On failure trigger	The string that is sent if the product reports that a run of this schedule has failed. This field is blank if no on failure trigger is specified.

The Runs tab

Table 29. Fields and links on the Runs tab

Field or link	Description
Edit the schedule list filter	Click to create an advanced filter for the list.

Table 29. Fields and links on the Runs tab (continued)

Field or link	Description
Delete	Delete one or more selected schedules. You can select schedules by clicking in the column at the left of the schedule. To select all schedules, click at the top of the left side column.
Mark as cancelled	Cancel one or more selected schedules.
Refresh	Click to refresh the list.
Filter	Click to create a simple filter for the list.
Run id	The identification number assigned to the run in the Unica Platform system tables.
Schedule name	The name specified for the schedule by its creator.
Scheduled item	The name of the object to be run.
Item type	The type of object to be run.
Start	The date and time when the run started.
Last updated	The date and time when the information for this run was updated.
Execution state	<p>State of the run as defined in the scheduler, as follows.</p> <ul style="list-style-type: none"> • Scheduled - The run has not begun. • Queued - The scheduler has started the run, but the Unica product has not begun executing the scheduled run due to throttling constraints. • Completed- The run has completed and has returned a status of Failed or Succeeded. • Cancelled - A user has cancelled a run by clicking Mark as Cancelled on the Scheduled Runs page. If the run was queued when the user marked it as cancelled, it does not execute. If the run was executing, this action does not stop the run, but it is marked as cancelled, and any triggers configured for this

Table 29. Fields and links on the Runs tab (continued)

Field or link	Description
	<p>run are not sent. Also, runs that depend on the cancelled run do not execute.</p> <ul style="list-style-type: none"> • Unknown - Indicates that Unica Platform can not determine whether the job is still running, completed or failed.
Run status	Status of the object's run as defined by the product executing the run. If the run sends a status of Cancelled, and the run is later started again and sends any other status to the scheduler, the status is updated in this field.
Details	Information about the run as provided by the product. For example, for a flowchart run, details include the flowchart name and ID, the error if the run fails, and the elapsed time if the run succeeds.

Edit the schedule list filter - Schedules

Table 30. Edit the schedule list filter on the Schedules tab

Column	Description
Filter by search tags / keywords	Select this check box if you want to include search tags or keywords in your filter. The string you enter here is matched with strings entered in the Search tags / keywords fields when schedules are created.
Search tags / keywords	Enter the search tags or keywords you want to use in your filter.
Filter on other criteria	Select this check box if you want to include additional criteria in your filter.
Run metadata	Select one of the following options to include in your rule. The options are:

Table 30. Edit the schedule list filter on the Schedules tab (continued)

Column	Description
	<ul style="list-style-type: none"> • Schedule name • Schedule state • Item type • Created by • Scheduled item
Condition	<p>Select one of the following options to determine how your rule is evaluated.</p> <ul style="list-style-type: none"> • Matches • Starts with • Ends with • Contains
Value	<p>Enter or select the value you want to apply to the rule. The options vary depending on the metadata you select for the rule.</p> <ul style="list-style-type: none"> • Schedule name Enter any characters. • Schedule state Value options are Enabled and Disabled. • Item type Value options are the various schedule types. • Created by Enter any characters. Your value is compared with user login names. • Scheduled item Enter any characters. The string you enter here is compared with the text in the Scheduled item column.

Table 30. Edit the schedule list filter on the Schedules tab (continued)

Column	Description
And / Or	Select one of these operators for each rule you create.

Edit the schedule list filter - Runs**Table 31. Edit the schedule list filter on the Runs tab**

Column	Description
Filter based on time	Select this check box if you want to show runs that occurred within a specified time interval.
Time zone	If you select an option other than the server default, the search uses the selected time zone to calculate which schedules fall within the date range you specify.
List runs for the last n instances	For recurring runs, specify how many previous runs to show in the list.
List runs from	Specify a time interval for the runs shown in the list.
Filter on other criteria	Select this check box if you want to include additional criteria in your filter.
Run metadata	<p>Select one of the following options to include in your filter.</p> <p>The options are:</p> <ul style="list-style-type: none"> • Schedule name • Execution state • Run status • Scheduled item
Condition	Select one of the following options to determine how your criteria are evaluated.

Table 31. Edit the schedule list filter on the Runs tab (continued)

Column	Description
	<ul style="list-style-type: none"> • Matches • Starts with • Ends with • Contains
Value	<p>Enter or select the value you want to apply to the filter. The options vary depending on the metadata you select for the rule.</p> <ul style="list-style-type: none"> • Schedule name Enter any characters. • Execution state Value options are: <ul style="list-style-type: none"> ◦ Queued ◦ Running ◦ Completed ◦ Unknown ◦ Cancelled • Run status Value options are Succeeded, Running, Cancelled, Failed, and Unknown. • Scheduled item Enter any characters. The string you enter here is compared with the text in the Scheduled item column.
And / Or	Select one of these operators for each rule you create.

SAML 2.0 based federated authentication

Unica Platform implements a SAML 2.0 based Identity Provider (IdP) that enables a single sign-on federation among Unica products or between Unica products and third party applications.

A federation is a group of IdPs and applications that works together in a trusted environment and provides services to each other using SAML 2.0 (Security Assertion Markup Language) based standards.

Applications that are members of a federation are called Service Providers (SPs). The IdP server and the SPs can be hosted on premises or on cloud.


A SAML 2.0 federation supports a variety of authentication mechanisms for single sign-on. For example, a user can be authenticated in an SP using that application's authentication mechanism (for example, in-house, OAuth, OpenId, SAML, Kerberos), and then the user can access other SPs using federated single sign-on, provided the applications are part of same federation and the user is mapped appropriately.

The IdP server creates, validates, or deletes tokens based on user mappings. Data access objects are implemented for the supported database types, and are included in the IdP server.

An administrator maps user IDs between SPs to provide single sign-on access to mapped users. For example, suppose SP_A and SP_B are both members of a federation. User1 is an account in SP_A, and User2 is an account in SP_B. The User1 account is mapped to the User2 account in the federation. When a user logs in to SP_A with User1 credentials, that user has single sign-on access to SP_B. Also, when a user logs in to SP_B with User2 credentials, that user has single sign-on access to SP_A.

Diagram

The following diagram illustrates the federation.



Components of the HCL implementation

The implementation of SAML 2.0 based federated single sign-on consists of the following components.

These components are located in the `tools/lib` directory under your Unica Platform installation.

- A SAML 2.0 based IdP server, delivered as a WAR file: `idp-server.war`
- A client façade: `idp-client.jar`

The IdP client façade is Java™ implementation with an API that works with security tokens. It is delivered as a JAR file. Javadoc™ documentation for the API is included with the Unica Platform Javadoc™.

The IdP client façade enables Java™ SPs to quickly integrate with the IdP server and become part of the federation.

Supported use cases

The current implementation enables SPs to work with security tokens to establish single sign-on authentication among the SPs.

Generating a new SAML token

The implementation can generate a new SAML token for a user who initiates a single sign-on authentication request. This user must be mapped on the IdP server. Based on the trusted party's credentials and user mapping, the IdP server creates a new security token and issues it using a SAML 2.0 assertion.

For example, if User1 from SP_A is mapped with User2 from SP_B on the IdP server, and User1 tries to access SP_B resources, the IdP server generates a security token for User1 as a trusted party.

Validating an existing SAML token

The implementation can validate an existing SAML token presented by an SP that receives the access request from a user from another SP. The SP first validates the security token and client mapping with the IdP server to identify the mapped user in its own domain.

For example, when SP_A tries to access SP_B resources on behalf of User1 and presents the IdP security token, SP_B takes this token to the IdP server. If the token is valid and User1 is mapped to an SP_B user, the IdP server resolves the SP_B user in the SP_B domain and returns the assertion.

Deleting an existing SAML token

The implementation can delete an existing SAML token for an SP user when a user logs out from the system or the session times out due to inactivity. Based on the trusted party's credentials and user mapping, the IdP server deletes the token and resets the last accessed timestamp when it receives the logout request. This does NOT delete the user's mapping.

Limitations

The current implementation does not support the following use cases.

- Creating a new user mapping between SP users via a user interface or API
- Updating an existing user mapping between SP users via a user interface or API
- Deleting an existing user mapping between SP users via a user interface or API

Federated authentication and partitions

If your Unica environment has multiple partitions, you can set up separate SAML 2.0 based federated authentication per partition. To implement this, on the **Settings > Configuration**

page, you must create a new set of properties in the **Unica Platform | Security | Federated Authentication | partitions | partition[n]** category for each partition.

How to implement federated authentication

Perform the procedures in this section to implement SAML 2.0 based federated authentication with ExperienceOne products.

Creating the data repository

Create two database tables, `TP_MASTER` and `TP_MAPPING`, to hold user mappings. Any schema can be used to create the tables.

The following example SQL scripts are provided in the `scripts` directory in the `idp-server.war` file.

- `DatabaseScript_DB2.sql`
- `DatabaseScript_Oracle.sql`
- `DatabaseScript_SQL.sql`

The following tables describe the fields in the database tables that the scripts create.

Table 32. Fields in the `TP_MASTER` table

Field	Description
<code>TP_ID</code>	Primary key. The unique ID for a registered Service Provider.
<code>TP_NAME</code>	The Service Provider name.
<code>TP_INFO</code>	A description of the Service Provider.
<code>KEY_ALIAS</code>	Unique key. The alias name of the Service Provider keystore. Enforces a unique alias name. You can drop the UNIQUE constraint if you want to use the same keystore alias for multiple Service Providers.

Table 33. Fields in the TP_MAPPING table

Field	Description
TP_CLIENT_ID	<p>Foreign key. The TP_ID of the requesting Service Provider.</p> <p>Part of a composite primary key comprised of four columns to ensure that there is no duplicate mapping in this table.</p>
TP_FOR_USER_ID	<p>The ID of the user making the request from the requesting Service Provider.</p> <p>Part of a composite primary key comprised of four columns to ensure that there is no duplicate mapping in this table.</p> <p>Must be a minimum of 4 characters and up to 24 characters long, and contain only alphanumerics, hyphen and underscore: [a-zA-Z0-9_-]</p>
TP_SP_ID	<p>Foreign key. The TP_ID of the serving Service Provider.</p> <p>Part of a composite primary key comprised of four columns to ensure that there is no duplicate mapping in this table.</p> <p>Must be a minimum of 4 characters and up to 24 characters long, and contain only alphanumerics, hyphen and underscore: [a-zA-Z0-9_-]</p>
TP_MAPPED_USER_ID	<p>The ID of the user in the serving Service Provider.</p> <p>Part of a composite primary key comprised of four columns to ensure that there is no duplicate mapping in this table.</p>
SAML_TOKEN	<p>Unique key. ID of the SAML token.</p> <p>Enforces unique token generation. You can drop the UNIQUE constraint if you want to use the same token for multiple Service Providers.</p>
LAST_REQUEST	<p>Timestamp of the last successful request.</p>

Configuring the IdP data source in the web application server

Tomcat, WebSphere®, and WebLogic are supported web application servers for the IdP server. After the IdP server is deployed on the web application server, configure a JNDI data source to connect the IdP server with the data repository.

See the documentation for your web application server for details on how to configure a JNDI data source.

For example, the following configuration is required to create the data source for an Oracle database in a Tomcat server. In the `conf/context.xml` file under your Tomcat installation, define a new resource.

```
<Resource name="idp_datasource"
auth="Container"
type="javax.sql.DataSource"
maxActive="100" maxIdle="30" maxWait="10000"
username="your_username" password="your_password"
driverClassName="com.microsoft.sqlserver.jdbc.SQLServerDriver"
url="jdbc:sqlserver://localhost:1433;DatabaseName=IdPServer" />
```

Register this resource in the `conf/web.xml` file under your Tomcat installation.

```
<resource-ref>
<description>SQL Server Datasource example</description>
<res-ref-name>idp_datasource</res-ref-name>
<res-type>javax.sql.DataSource</res-type>
<res-auth>Container</res-auth>
</resource-ref>
```

Setting up the classpaths for the IBM® IdP client façade

If you want to use the IBM® IdP client façade, you must add JAR files in the classpath of your IdP server and the SPs.

1. Obtain the required JAR files as described below, and place these JAR files on your IdP server and the servers that host your SPs.

- Locate the `unica.war` file in the Unica Platform installation directory. Extract the `unica.war` file, navigate to the `WEB-INF\lib` directory and copy the following JARs.

- `bcprov-jdk15.jar`
- `esapi-2.0.1.jar`
- `jersey-core-1.17.jar`
- `jersey-server-1.17.jar`
- `jersey-servlet-1.17.jar`
- `joda-time-2.2.jar`
- `opensaml-2.6.1.jar`
- `openws-1.5.1.jar`
- `xmlsec-1.5.6.jar`
- `xmltooling-1.4.1.jar`

- `asm-3.1.jar`

Download from <http://mvnrepository.com/artifact/asm/asm/3.1>.

- `jcl-over-slf4j-1.7.5.jar`

Download from <http://mvnrepository.com/artifact/org.slf4j/jcl-over-slf4j/1.7.5>.

- `slf4j-api-1.7.5.jar`

Download from <http://mvnrepository.com/artifact/org.slf4j/slf4j-api/1.7.5>.

2. Add the JAR files you obtained in the previous step in the classpath of your IdP server and in the classpath of each of your SPs.

3. For each SP that you want to include in the federation, also add this Client façade JAR file the classpath: : `idp-client.jar`

This JAR file is provided with your Unica Platform installation.

Deploying the IdP server

The `IdP-Server.war` file can be deployed along with the Unica Platform WAR file in the same server, or it can be deployed separately. There is no direct dependence between these two WAR files.

Configuring the IdP server

The IdP server stores its keystore in its configuration to assert the SAML token coming from SPs. The configurations are stored in the `IdPServerConfig.properties` file under the `conf` folder of the web application server where the IdP server is deployed.

The queries shown in this section are generic. If you need to modify the query for your database type, use one of the following suffixes in the key and enter your new query as the value.

- `Sql`
- `Oracle`
- `db2`

For example, to modify the query in the `com.ibm.ocm.idp.server.query.token.create` property for DB2®, change the property as follows.

```
com.ibm.ocm.idp.server.query.token.create.db2 = new query
```



Note: The sequence and number of columns in your modified query must be the same as in the original query.

Reference: IdPServerConfig.properties file

This section lists the default values of properties in the configuration file, and all supported values for the properties.

`com.ibm.ocm.idp.server.keystore.path`

The absolute path of the keystore file on the web application server host machine.

Default value: `path/idp.jks`

`com.ibm.ocm.idp.server.keystore.passkey`

Passkey of the keystore.

Default value: `idp001`

com.ibm.ocm.idp.server.keystore.alias

Alias of the keystore.

Default value: `idp`

com.ibm.ocm.idp.server.certificate.issuer

Certificate issuer's URL.

Default value: `http://localhost:8080/idp/`

com.ibm.ocm.idp.server.token.validity

Token validity period in seconds.

Default value: `3600`

com.ibm.ocm.idp.server.enable

Logger for IdP server.

Default value: `True`

com.ibm.ocm.idp.server.dao.class

Database specific data access object implementation.

Supported DAOs are:

`com.ibm.ocm.idp.server.dao.IdPServerSQLDAO`

`com.ibm.ocm.idp.server.dao.IdPServerOracleDAO`

`com.ibm.ocm.idp.server.dao.IdPServerDB2DAO`

Default value: `com.ibm.ocm.idp.server.dao.IdPServerSQLDAO`

com.ibm.ocm.idp.server.datasource.name

JNDI data source name defined in the application server.

Default value: `idp_datasource`

com.ibm.ocm.idp.server.query.token.create

Query to create token.

Default value:

```

UPDATE TP_MAPPING
SET SAML_TOKEN = ?, LAST_REQUEST = ?
WHERE TP_CLIENT_ID = ?
AND TP_FOR_USER_ID = ?
AND TP_SP_ID = ?

```

com.ibm.ocm.idp.server.query.token.get

Query to get token.

Default value:

```

SELECT SAML_TOKEN,
LAST_REQUEST FROM TP_MAPPING
WHERE TP_CLIENT_ID = ?
AND TP_FOR_USER_ID = ?
AND TP_SP_ID = ?

```

com.ibm.ocm.idp.server.query.mapping.validate

Query to validate a user mapping.

Default value:

```

SELECT TP_MAPPED_USER_ID FROM TP_MAPPING
WHERE TP_CLIENT_ID = ?
AND TP_FOR_USER_ID = ?
AND TP_SP_ID = ?

```

com.ibm.ocm.idp.server.query.token.delete

Query to delete token.

Default value:

```


```

```
UPDATE TP_MAPPING SET SAML_TOKEN = null,
LAST_REQUEST = null
WHERE TP_CLIENT_ID = ?
AND TP_FOR_USER_ID = ?
AND TP_SP_ID = ?
```

com.ibm.ocm.idp.server.query.client.get

Query to get client details.

Default value:

```
SELECT TP_ID, TP_NAME, TP_INFO, KEY_ALIAS
FROM TP_MASTER
WHERE TP_ID = ?
```

Obtaining keystores and importing them into the IdP server

To establish the trusted party assertion, individual keystores are required for each integrating application and the IdP server.

Obtain keystores for the IdP server and for all SPs you want to include in the federation. You can generate the keystores using the Java™ keytool utility, or you can obtain them from a certificate authority.

If you generate keystores using the keytool utility, here is a typical workflow for this task, with example commands. In the examples, the Java™ 6 keytool path is `C:\Program Files (x86)\Java\jre7\bin\keytool`.

- The IdP administrator generates a keystore for the IdP server and exports the certificate.

```
# Generate IdP JKS from keytool
c:\temp> "keytool_path\keytool" -genkey -keyalg RSA -alias idp
-keystore idp.jks -storepass idp001 -validity 360 -keysize 2048
```

```
# Export IdP certificate from JKS
c:\temp> "keytool_path\keytool" -export -alias idp -file idp.cer
-keystore idp.jks
```

- An SP administrator generates a keystore and exports it.

```
# Generate Service Provider JKS from keytool
c:\temp> "keytool_path\keytool" -genkey -keyalg RSA -alias SP_1
-keystore SP_1.jks -storepass SP001 -validity 360 -keysize 2048
# Export Service Provider certificate from JKS
c:\temp> "keytool_path\keytool" -export -alias SP_1 -file SP_1.cer
-keystore SP_1.jks
```

The SP administrator then sends the certificate to the IdP administrator.

- The IdP administrator imports the SP certificate into the IdP server.

```
# Import Service Provider certificate into IdP JKS
c:\temp> "keytool_path\keytool" -import -alias SP_1
-trustcacerts -file SP_1.cer -keystore idp.jks
```

Setting configuration properties on the Configuration page

Set configuration properties on the **Settings > Configuration** page to configure federated authentication in Unica.

Set configuration properties under the following categories.

- **Unica Platform | Security | Federated Authentication**
- **Unica Platform | Security | Federated Authentication | partitions | partition[n]**

See each property's context help or the related topic links in this section for instructions on setting the values.

Onboarding Service Providers and users

The IdP server administrator must make one-time entries in the `TP_MASTER` table to onboard SPs and users.

Here is example SQL for onboarding an SP.

```
INSERT INTO TP_MASTER
(TP_ID, TP_NAME, TP_INFO, KEY_ALIAS)
VALUES
('SP_Id', 'SP display name', 'SP description', 'keystore alias name')
```

After the trusted parties are registered with the IdP server, the IdP server administrator can map users to participate in federated single sign-on.

The user mapping must be strictly one-to-one between two SPs. For example, User1 from SP_A must be mapped ONLY to any one user in SP_B. However, User1 from SP_A can be mapped with another user in SP_C in the same federation.

Here is an example query for adding users in the `TP_MAPPING` table.

```
INSERT INTO TP_MAPPING
(TP_CLIENT_ID, TP_FOR_USER_ID, TP_SP_ID, TP_MAPPED_USER_ID, SAML_TOKEN)
VALUES
('SP1_Id', 'SP1_user_Id', 'SP2_Id', 'SP2_user_id', 'dummy1')
```



Note: The entries for `TP_SP_ID` and `TP_FOR_USER_ID` must be a minimum of 4 characters and up to 24 characters long, and contain only alphanumeric, hyphen and underscore characters: `[a-zA-Z0-9_-]`. Insert unique dummy entries for the `SAML_TOKEN` column, as this column does not allow nulls and duplicates.

Using the IdP client façade to generate tokens and pass them to Service Providers

When a user is authenticated and wants to access the services of another SP, call the following code on the SP side.

The code generates the federated token.

```
// One time properties to initialize the IdP client.
Properties properties = new Properties();
properties.put(IdPClient.IDP_SERVER_URL, "URL");
properties.put(IdPClient.IDP_CLIENT_CERTIFICATE_ISSUER, "URL");
properties.put(IdPClient.IDP_CLIENT_KEYSTORE_PATH, "JKS file path");
properties.put(IdPClient.IDP_CLIENT_KEYSTORE_PASSKEY, "JKS passkey");
properties.put(IdPClient.IDP_CLIENT_KEYSTORE_ALIAS, "Certificate alias");
// Get the IdP client factory singleton instance
//with the specified parameters.
IdPClientFactory clientFactory = IdPClientFactory.getInstance(properties);
// Get the partition specific client facade to do the assertion.
IdPClientFacade clientFacade = clientFactory.getIdPClientFacade(partition);
// Establish SSO Login with the IdP server
IdPClientToken token = clientFacade.doIdPLogin(clientId, forUserId, spId);
```

After the token is obtained, it can be passed to target SPs to access their resources based on the mapped user's roles and permissions.

```
// Security token is validated at Service Provider side.
IdPClientAssertion assertion = spFacade.assertIdPToken(clientId, forUserId,
    spId,
    token.getTokenId());
// Retrieve the principal from the assertion, if there is no exception.
String principal = assertion.getMappedUser();
```

The client facade is multi-tenant aware and can be used to configure each partition separately. To use this feature, append the client ID to each property name. For example:

```
properties.put(IdPClient.IDP_CLIENT_KEYSTORE_PATH +
".partition1", "JKS file path");
properties.put(IdPClient.IDP_CLIENT_KEYSTORE_PASKEY +
".partition1", "JKS passkey");
properties.put(IdPClient.IDP_CLIENT_KEYSTORE_ALIAS +
".partition1", "Certificate alias");
```

Reference: RESTful services

Use this information to troubleshoot issues when you use the client facade, or to develop your own SAML 2.0 implementation with the IdP server provided by IBM.

The REST APIs are implemented using an XML data payload. The SAML assertion is directly passed to the POST methods with digital signatures.

Only the POST method is supported for all verbs to ensure unified method access and to enforce security assertions, based on the XML payload. Other methods, such as GET, PUT, and DELETE, return an error message. The following table represents the verbs that implement the supported use cases.

Table 34. Supported verbs

Resource	Post
<code><idp>/saml/token/clientId/forUserId/spId/create</code>	Generate new SAML token.
<code><idp>/saml/token/clientId/forUserId/spId/validate</code>	Validate existing SAML token.
<code><idp>/saml/token/clientId/forUserId/spId/delete</code>	Delete existing SAML token.

Related concepts

This section provides general information about the technologies used in the ExperienceOne implementation of SAML 2.0 based federated single sign-on.

Security Assertion Markup Language 2.0 (SAML 2.0)

SAML 2.0 is a version of the SAML standard for exchanging authentication and authorization data between security domains. SAML 2.0 is an XML-based protocol that uses security tokens containing assertions to pass information about a principal (usually an end user) between a SAML authority, that is, an identity provider, and a SAML consumer, that is, an SP. SAML 2.0 enables web-based authentication and authorization scenarios including cross-domain single sign-on (SSO), which helps reduce the administrative overhead of distributing multiple authentication tokens to the user. For more information, see http://en.wikipedia.org/wiki/SAML_2.0.

Identity Provider (IdP)

Also known as Identity Assertion Provider, the IdP issues identification information for all SPs that interact or provide services within the system. This is achieved via an authentication module that verifies a security token as an alternative to explicitly authenticating a user within a security realm. In perimeter authentication, a user needs to be authenticated only once (single sign-on) and pass along a security token which is processed by an Identity Assertion Provider for each system it needs to access. For more information, see http://en.wikipedia.org/wiki/Identity_provider.

Public-key cryptography

Also known as asymmetric cryptography, a cryptographic algorithm that requires two separate keys, one of which is secret (or private) and one of which is public. Although different, the two parts of this key pair are mathematically linked. The public key is used to encrypt plaintext or to verify a digital signature; whereas the private key is used to decrypt ciphertext or to create a digital signature. For more information, see http://en.wikipedia.org/wiki/Public-key_cryptography.

SAML 2.0 single sign-on

Unica Platform supports SAML 2.0 based single sign-on.

In this mode, Unica users can be authenticated against any external or corporate identity provider that follows the standard SAML 2.0 protocol. Identity providers generate the SAML assertion, which is then used by Unica Platform to allow users to log in. Therefore, a fully functional SAML 2.0 IdP server is a prerequisite for this integration.


After you set up the required configuration properties and a metadata file, users who attempt to log in through the Unica Platform login page are authenticated through your organization's SAML 2.0 Identity Provider (IdP) server.

A configuration property, **Add authenticated users to Platform**, enables automatic creation of a Unica Platform account for any authenticated user who does not have a Unica Platform account. These users are automatically added to a default user group, **ExternalUsersGroup**, which has only the **PlatformUser** role initially. Alternatively, you can specify a custom group to which users are added.

If the **Add authenticated users to Platform** property is not enabled, users must have a Unica Platform account to log in.

A Unica Platform administrator can manage group memberships and roles to configure access to Unica products for the automatically created users.

The following diagram illustrates the SAML 2.0 based single sign-on mode in Unica.



Behavior when SAML 2.0 single sign-on is implemented

The implementation of SAML 2.0 single sign-on in Unica has the following behavior.

Logout

When logged-in users log out, they are redirected to the standard Unica logout page. A message instructs users to close the browser window to complete the log out process.

Session timeout

If logged-in users are idle for more than 30 minutes they are redirected to the standard Unica logout page. A message instructs users to close the browser window to complete the log out process.

This time out period can be configured in your application server.

Incorrect SAML configuration

If an error occurs due to incorrect SAML configuration when users attempt to log in, the users are redirected to an error page with the message "Login Failed: Bad Credential. Please close the browser window and try again."

User not provisioned in Platform but is a valid IDP user

When the **Add authenticated users to Platform** property is disabled, users who log in with credentials that are valid for the IdP server but who do not have a Unica Platform account are redirected to an error page with the message "Login Failed: Bad Credential. Please close the browser window and try again."

User exists in both IDP and Unica Platform but their Unica Platform password has expired or been reset

When user's password is expired or reset in Unica Platform, the user is redirected to an error page with the message "Login Failed: Bad Credential. Please close the browser window and try again."

Configuration process roadmap: SAML 2.0 single sign-on

Use this configuration process roadmap to scan the tasks required to implement SAML 2.0 single sign-on in Unica. Where applicable, the Task column provides links to the topics that describe the tasks in detail.

Table 35. Configuration process roadmap: SAML 2.0 single sign-on

Task	Information
Add Unica Platform as a service provider in your IdP server. See your IdP server documentation for details.	<ul style="list-style-type: none"> • Make a note of the application ID assigned to Unica Platform in your IdP server, as you will use it as the value of a configuration property.

Table 35. Configuration process roadmap: SAML 2.0 single sign-on (continued)

Task	Information
	<ul style="list-style-type: none"> • Make a note of password of the key store file, as you will use it as the value of the password in the data source you create.
Setting up the metadata file (on page 137)	Set up the XML metadata file generated by your SAML 2.0 IdP server.
Setting SAML 2.0 configuration properties (on page 137)	Set required configuration properties on the Settings > Configuration page .
Setting up a data source for SAML single sign-on (on page 138)	Set up the a data source to hold the password of the keystore file.

Setting up the metadata file

Your IdP server generates a metadata file that contains configuration and integration details for SAML 2.0 single sign-on.

Copy the IdP server metadata file and place it on the server where Unica Platform is installed. Make a note of the following information, which you need when you set configuration property values.

- The location of the metadata file on the Unica Platform server.
- The value of *entityID* in the XML declaration at the top of the metadata file.

Setting SAML 2.0 configuration properties

To configure SAML 2.0 single sign-on, set properties on the **Configuration > Settings** page.

Set the following properties.

- Set the value of the **Login method** property to **SAML 2.0**.

This property is located under the **Unica Platform | Security** node.

Stop and restart the Unica Platform web application so that this change takes effect.

- Set properties located under the **Unica Platform | Security | Login method details | SAML 2.0** node as required.

See the context help for these properties for details.

Setting up a data source for SAML single sign-on

Save the password of the key store file in a data source in Unica Platform.

1. Log in to Unica as an Admin user and navigate to the Settings > Users page.
2. Select or create a user and configure a data source for this user as follows.
 - **Data Source** - Enter the value set for the **Key store credential data source** property under **Unica Marketing Platform | Security | Login method details | SAML 2.0** on the **Settings > Configuration** page.
 - **Data Source Login** - Enter the value set for the **Key store credential holder** property under **Unica Platform | Security | Login method details | SAML 2.0** on the **Settings > Configuration** page.
 - **Data Source Password** - Enter the password of the key store file used for Unica Platform in your IdP server.


If you have multiple partitions, you must perform this task in every partition where you have users who should have single sign-on. Alternatively, you can use the platform_admin user account for this step. Because this user is a member of all partitions, the data source is available in all partitions

Sample SAML 2.0 IdP assertion

This section provides examples of the SAML 2.0 request and response.

Example of the SAML 2.0 request generated by Unica Platform

Unica Platform generates the SAML 2.0 request shown in this section, and encodes it using OpenSAML Base64 APIs. The request is compatible with any other standard Base64 decoder. The encoded request is posted to the IdP server.



```

<saml2p:AuthnRequest
  xmlns:saml2p="urn:oasis:names:tc:SAML:2.0:protocol"
  AssertionConsumerServiceURL="http://example.com"
  Destination="http://example.com"
  ForceAuthn="false"
  ID="_0ff13d123291170422ff5e945e9a209e25f3404916451a4aaf"
  IsPassive="false"
  IssueInstant="2015-09-02T14:10:24.376Z"
  ProtocolBinding="urn:oasis:names:tc:SAML:2.0:bindings:HTTP-POST"
  Version="2.0">
  <saml2:Issuer
xmlns:saml2="urn:oasis:names:tc:SAML:2.0:assertion">
    IdP_ID
  </saml2:Issuer>
  <saml2p:NameIDPolicy
    AllowCreate="true"

Format="urn:oasis:names:tc:SAML:2.0:nameid-format:transient"
    SPNameQualifier="SERVICE_PROVIDER_ID"/>
  <saml2p:RequestedAuthnContext
    Comparison="exact">
    <saml2:AuthnContextClassRef

xmlns:saml2="urn:oasis:names:tc:SAML:2.0:assertion">
      urn:oasis:names:tc:SAML:2.0:ac:classes:
      PasswordProtectedTransport
    </saml2:AuthnContextClassRef>
  </saml2p:RequestedAuthnContext>
</saml2p:AuthnRequest>

```

Example of the SAML 2.0 response generated by the IdP server

```

<samlp:Response
  xmlns:samlp="urn:oasis:names:tc:SAML:2.0:protocol"
  Destination="http://serviceprovider.com/location"
    ID="id-wmpfMj-fMh0ihGYJ73rXPTEq7o8-"
  InResponseTo="s2e211c5bfc0200fc48819f381f17d56ca0b5c780f"
  IssueInstant="2015-09-02T14:10:24.376Z"
  Version="2.0">
  <saml:Issuer xmlns:saml="urn:oasis:names:tc:SAML:2.0:assertion"
    Format="urn:oasis:names:tc:SAML:2.0:nameid-format:entity">
    Identity Provider
  </saml:Issuer>
  <samlp:Status>
    <samlp:StatusCode Value="urn:oasis:names:tc:
      SAML:2.0:status:Success" />
  </samlp:Status>
  <saml:Assertion xmlns:saml="urn:oasis:names:tc:SAML:2.0:assertion"
    ID="idzQO7U5TzPLLL4dlqTqRt9VIOlYg-"
    IssueInstant="2015-09-02T14:10:24.376Z"
    Version="2.0">
    <saml:Issuer Format="urn:oasis:names:tc:SAML:2.0:
      nameid-format:entity">
      Identity Provider
    </saml:Issuer>
    <dsig:Signature
  xmlns:dsig="http://www.w3.org/2000/09/xmldsig#">
    <dsig:SignedInfo>
      <dsig:CanonicalizationMethod
  Algorithm="http://www.w3.org/2001/10/xmlexc-c14n#" />
      <dsig:SignatureMethod
  Algorithm="http://www.w3.org/2000/09/xmldsig#

```

```

        rsa-shal" />
    <dsig:Reference URI=
        "#id-zQO7U5TzPLLL4dlqTqRt9VIOlYg-" />
    <dsig:Transforms>
        <dsig:Transform Algorithm=
"http://www.w3.org/2000/09/xmldsig#
        enveloped-signature" />
        <dsig:Transform Algorithm=
"http://www.w3.org/2001/10/xml-exc-c14n#" />
    </dsig:Transforms>
    <dsig:DigestMethod Algorithm=
"http://www.w3.org/2000/09/xmldsig#sha1" />
        <dsig:DigestValue>
            XXX=
        </dsig:DigestValue>
    </dsig:Reference>
</dsig:SignedInfo>
    <dsig:SignatureValue>xxx</dsig:SignatureValue>
</dsig:Signature>
<saml:Subject>
    <saml:NameID Format=
        "urn:oasis:names:tc:SAML:2.0:nameid-format:
            transient"
        NameQualifier="Test Identity Provider"
        SPNameQualifier="TEST">
        id-N2EIOvbwaVflUP-cKTzgv8dGYLg-
    </saml:NameID>
    <saml:SubjectConfirmation
        Method="urn:oasis:names:tc:SAML:2.0:cm:bearer">

```

```

        <saml:SubjectConfirmationData
            InResponseTo=

"s2e211c5bfc0200fc48819f381f17d56ca0b5c780f"

            NotOnOrAfter="2015-09-02T14:10:24.376Z"

Recipient="http://serviceprovider.com/location" />
        </saml:SubjectConfirmation>
    </saml:Subject>
    <saml:Conditions
        NotBefore="2015-09-02T14:10:24.376Z"
        NotOnOrAfter="2015-09-02T14:10:49.376Z">
        <saml:AudienceRestriction>
            <saml:Audience>TEST</saml:Audience>
        </saml:AudienceRestriction>
    </saml:Conditions>
    <saml:AuthnStatement
        AuthnInstant="2015-09-02T14:10:24.376Z"
        SessionIndex="id-lFTYalkjaVTWwHrFRkIREvHfAxk-"
        SessionNotOnOrAfter="2015-09-02T14:10:38.376Z">
        <saml:AuthnContext>
            <saml:AuthnContextClassRef>
                urn:oasis:names:tc:SAML:2.0:ac:classes:
                PasswordProtectedTransport
            </saml:AuthnContextClassRef>
        </saml:AuthnContext>
    </saml:AuthnStatement>
    <saml:AttributeStatement xmlns:x500=
        "urn:oasis:names:tc:SAML:2.0:profiles:
        attribute:X500"
        xmlns:xs="http://www.w3.org/2001/XMLSchema"
        xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance">

```

```

        <saml:Attribute
            Name="UserIdentifier"
            NameFormat="urn:oasis:names:tc:SAML:2.0:
                attrnameformat:basic">
            <saml:AttributeValue xsi:type="xs:string">
                user@example.com
            </saml:AttributeValue>
        </saml:Attribute>
    </saml:AttributeStatement>
</saml:Assertion>
</samlp:Response>

```

Sample IdP metadata

This section provides an example of the metadata file produced by the IdP server

Example of the metadata file generated by the IdP server

The IdP server generates a metadata file that contains configuration and integration details for SAML 2.0 single sign-on. This file is used by Unica Platform. Place a copy of the file generated by your IdP server on the Unica Platform server.

```

<?xml version="1.0" encoding="UTF-8"?>
    <md:EntityDescriptor
        xmlns:md="urn:oasis:names:tc:SAML:2.0:metadata"
        entityID="ENTITY_ID">
        <md:IDPSSODescriptor
            WantAuthnRequestsSigned="false"

            protocolSupportEnumeration="urn:oasis:names:tc:SAML:2.0:
                protocol">
            <md:KeyDescriptor use="signing">

```

```

        <KeyInfo
xmlns="http://www.w3.org/2000/09/xmldsig#">
            <X509Data>
                <X509Certificate>
                    __certificate__
                </X509Certificate>
            </X509Data>
        </KeyInfo>
    </md:KeyDescriptor>
    <md:KeyDescriptor use="encryption">
        <KeyInfo
xmlns="http://www.w3.org/2000/09/xmldsig#">
            <X509Data>
                <X509Certificate>
                    __certificate__
                </X509Certificate>
            </X509Data>
        </KeyInfo>
        <md:EncryptionMethod
            Algorithm=
"http://www.w3.org/2001/04/xmlenc#rsa-1_5"/>
    </md:KeyDescriptor>
    <md:ArtifactResolutionService
Binding="urn:oasis:names:tc:SAML:2.0:bindings:SOAP"
            Location="__location__" index="0"
            isDefault="true"/>
    <md:ArtifactResolutionService
Binding="urn:oasis:names:tc:SAML:2.0:bindings:SOAP"

```

```

        Location="__location__" index="1"/>
    <md:SingleLogoutService
Binding="urn:oasis:names:tc:SAML:2.0:bindings:HTTP-POST"
        Location="__location__"/>
    <md:SingleLogoutService Binding=
        "urn:oasis:names:tc:SAML:2.0:bindings:SOAP"
        Location="__location__"/>
    <md:ManageNameIDService
Binding="urn:oasis:names:tc:SAML:2.0:bindings:HTTP-POST"
        Location="__location__"/>
    <md:ManageNameIDService
Binding="urn:oasis:names:tc:SAML:2.0:bindings:SOAP"
        Location="__location__"/>
    <md:NameIDFormat>urn:oasis:names:tc:SAML:2.0:
        nameid-format:persistent
    </md:NameIDFormat>
    <md:NameIDFormat>urn:oasis:names:tc:SAML:2.0:
        nameid-format:transient
    </md:NameIDFormat>
    <md:NameIDFormat>
        urn:oasis:names:tc:SAML:1.1:
        nameid-format:emailAddress
    </md:NameIDFormat>
    <md:NameIDFormat>urn:oasis:names:tc:SAML:2.0:
        nameid-format:encrypted</md:NameIDFormat>
    <md:SingleSignOnService
Binding="urn:oasis:names:tc:SAML:2.0:
        bindings:HTTP-POST" Location="__location__"/>
</md:IDPSSODescriptor>

```

```

    <md:Organization>
      <md:OrganizationName xml:lang="en">
        organization_name
      </md:OrganizationName>
      <md:OrganizationDisplayName xml:lang="en">
        organization_display_name
      </md:OrganizationDisplayName>
      <md:OrganizationURL xml:lang="en"/>
    </md:Organization>
    <md:ContactPerson contactType="technical">
      <md:Company>
        company
      </md:Company>
      <md:GivenName/>
      <md:SurName/>
      <md:EmailAddress/>
      <md:TelephoneNumber/>
    </md:ContactPerson>
  </md:EntityDescriptor>

```

Configuring JWT authentication between applications

JSON web token (JWT) authentication is used for Journey Designer+Unica Campaign. JWT authentication allows single sign-on between applications.

A request that comes from a calling application contains the JWT token. Unica Platform validates the request by calling the public key service (PKS). After the JWT token is validated, the request is authenticated and allowed.

This procedure applies only when the 10.0.0.1 FixPack is applied. In version 10.0.0.0, JWT authentication does not use PKS.

Use this procedure to import certificates and set configuration properties to enable JWT authentication.

1. Retrieve the certificate from the public key service (PKS) site.
2. Use the Java keytool to import the certificate into the application server JVM. If your applications are running on different JVMs, import the certificate on each application server JVM.

For example,

```
/keytool -import -file PKS_Certificate.cer -alias PKS_alias -keystore  
AppServer_JRE_home/lib/security/cacerts
```

Provide a password. The default keytool password is `changeit`.

3. Set JWT configuration properties on the **Settings > Configuration** page under **Unica Platform | Security | JWT authentication**.

Single sign-on between Unica and IBM Digital Analytics

If your organization uses IBM Digital Analytics, you can enable single sign-on between Digital Analytics and Unica.

Single sign-on allows users to navigate to Digital Analytics reports from within the Unica user interface without being prompted to log in.

Also, if Digital Analytics reports are referenced in Unica dashboards, single sign-on allows users to view these reports (if they have access to them in Digital Analytics).

Two options for enabling single sign-on between Unica and IBM Digital Analytics

You can choose between two options for enabling single sign-on.

- You can configure Digital Analytics to automatically create an Digital Analytics user account the first time an Unica user navigates to Digital Analytics.

You might want to choose this option if you want all of your Unica users to have single sign-on with Digital Analytics.

- You can configure Unica user accounts for single sign-on by adding each user's existing Digital Analytics login name to his or her detail page in Unica.

When you choose this option, users who require access to Digital Analytics must have an Digital Analytics account.

You might want to choose this option if you want a subset of your Unica users to have single sign-on with Digital Analytics.

Permissions in Digital Analytics for single sign-on users

When the automatic account creation option is **not** selected in Digital Analytics, single sign-on users have the permissions in Digital Analytics that they would have if they log in to Digital Analytics directly.

When the automatic account creation option is selected in Digital Analytics, single sign-on users have permissions in Digital Analytics as follows.

- By default, users have the permissions granted to the Digital Analytics group the administrator has configured for all automatically created users.

Administrators can modify the permissions associated with this group.

- In addition, the administrator can override automatic account creation for users who already have a Digital Analytics account. If the override is in place for a user, that user has the permissions he or she would have when he or she logs in to Digital Analytics directly.

Server clock coordination

The clock on the server on which Unica Platform is deployed must match the time on the Digital Analytics server clock. For single sign-on, the Digital Analytics server allows for up to 15 minutes of difference (900 seconds) between server clock times.

As a best practice, you should synchronize server clocks. To ensure synchronization, you should use the Network Time Protocol (NTP).

If you cannot synchronize your server clock, and there might be at least 15 minutes of difference between the clocks, you can set the **Clock skew adjustment (seconds)** configuration property under the Coremetrics® category in Unica Platform to a number that reflects the difference between the clocks.

Setting up single sign-on between Unica and Digital Analytics using automatic user account creation

Use this procedure to set up single sign-on between Unica and Digital Analytics using automatic user account creation.

1. Determine the Digital Analytics Client ID you want to use for single sign-on between Unica and Digital Analytics.

Make a note of the Client ID, as you will need it in a later step.

2. Log in to Digital Analytics as an Admin user with access to the Client ID you selected in the previous step, click the Admin link, and navigate to the Global User Authentication page.

- In the **Enterprise Marketing Management Shared Secret** field, enter a string that conforms to the rules stated in the instructions next to the field.

Make a note of this string, as you will need it in a later step.

- Under Automatic User Account Creation, click **Enabled**.
- Select a user group to which you want all automatically created users to belong.

This group should have at least the following Web Analytics permissions.

- Dashboards > View Standard Dashboards
- Reports > Site Metrics
- Reports > Insights

3. Log in to Unica as an Admin user and navigate to the **Settings > Users** page.
4. Select or create a user and configure a data source for this user as follows.

- **Data Source** - Enter a name.
- **Data Source Login** - Enter the Client ID you noted in step 1.
- **Data Source Password** - Enter the Shared Secret you noted in step 2.

If you have multiple partitions, you must perform this task in every partition where you have users who should have single sign-on.

Alternatively, you can use the platform_admin user account for this step. Because this user is a member of all partitions, the data source is available in all partitions.

5. In Unica Platform, navigate to the **Settings > User groups** page and do the following.

- Create a new group and add the CMUser role to that group.
- Make each user who should have single sign-on a member of that group.

If you have multiple partitions, you must perform this task in every partition where you have users who should have single sign-on.

6. In Unica Platform, navigate to the **Settings > Configuration** page and set configuration properties as follows.

Table 36. Configuration properties for enabling single sign-on with Digital Analytics

Property	Value
Digital Analytics Enable IBM Digital Analytics	True
Digital Analytics Integration partitions partition[n] Platform user for IBM Digital Analytics account	Enter the login name for the Unica Platform user account that you used in step 4.
Digital Analytics Integration partitions partition[n] Datasource for IBM Digital Analytics account	Enter the name of the data source you created in step 4.

If you have multiple partitions, you must use the **Digital Analytics | Integration | partitions | partitionTemplate** to create a set of configuration properties for every partition where you have users who should have single sign-on.

The name of the category you create with the template must exactly match the name of the corresponding Unica Campaign partition.

7. For any user for whom you want to override automatic account creation, do the following.
 - In Unica Platform, navigate to the **Settings > Users** page.
 - Enter the user's Digital Analytics login name in the **Digital Analytics Username** field on the user's detail page.

This works only for users who already have an Digital Analytics account.



Note: If an account does not exist in Digital Analytics with this login name, an account will be created for this user with the name you enter here, rather than with the user's Unica Platform login name.

8. Configure you web application server for single sign-on with Digital Analytics.

Setting up single sign-on between Unica and Digital Analytics using manual user account creation

Use this procedure to set up single sign-on between Unica and Digital Analytics using manual user account creation.

1. Determine the Digital Analytics Client ID you want to use for single sign-on between Unica and Digital Analytics.

Make a note of the Client ID, as you will need it in a later step.

2. Log in to Digital Analytics as an Admin user with access to the Client ID you selected in the previous step, click the Admin link, and navigate to the Global User Authentication page.

- In the **Enterprise Marketing Management Shared Secret** field, enter a string that conforms to the rules stated in the instructions next to the field.

Make a note of this string, as you will need it in a later step.

- Under Automatic User Account Creation, click **Disabled**.

3. Log in to Unica as an Admin user and navigate to the **Settings > Users** page.

4. Select or create a user and configure a data source for this user as follows.

- **Data Source** - Enter a name.
- **Data Source Login** - Enter the Client ID you noted in step 1.
- **Data Source Password** - Enter the Shared Secret you noted in step 2.

If you have multiple partitions, you must perform this task in every partition where you have users who should have single sign-on.

Alternatively, you can use the platform_admin user account for this step. Because this user is a member of all partitions, the data source is available in all partitions.

5. In Unica Platform, navigate to the **Settings > User groups** page and do the following.

- Create a new group and add the DMUser role to that group.
- Make each user who should have single sign-on a member of that group.

If you have multiple partitions, you must perform this task in every partition where you have users who should have single sign-on.

6. In Unica Platform, navigate to the **Settings > Configuration** page and set configuration properties as follows.

Table 37. Configuration properties for enabling single sign-on with Digital Analytics

Property	Value
Digital Analytics Enable IBM Digital Analytics	True
Digital Analytics Integration partitions partition[n] Platform user for IBM Digital Analytics account	Enter the login name for Unica Platform user account that you used in step 4.
Digital Analytics Integration partitions partition[n] Datasource for IBM Digital Analytics account	Enter the name of the data source you created in step 4.

If you have multiple partitions, you must use the **Digital Analytics | Integration | partitions | partitionTemplate** to create a set of configuration properties for every partition where you have users who should have single sign-on.

The name of the category you create with the template must exactly match the name of the corresponding Unica Campaign partition.

7. In Unica Platform, navigate to the **Settings > Users** page.
8. For each user for whom you want to enable single sign-on, enter that user's Digital Analytics login name in the **IBM Digital Analytics user name** field on the user's Edit properties page.



Note: If a user has exactly the same login names in both Unica and Digital Analytics, you do not have to perform this step.

9. Configure your web application server for single sign-on with Digital Analytics.

Configuring WebLogic for single sign-on between Digital Analytics and Unica

Perform the procedure below in the WebLogic domain where Unica Platform is deployed to ensure that users can view Digital Analytics reports in dashboards without having to log in.

1. Open the `setDomainEnv` script, located in the `bin` directory under your WebLogic domain directory.
2. Add `-Dweblogic.security.SSL.ignoreHostnameVerification=true` to `JAVA_OPTIONS`.

Configuring WebSphere® for single sign-on between Digital Analytics and Unica

Perform the procedure below in WebSphere® cell and node where Unica Platform is deployed to ensure that users can view Digital Analytics reports in dashboards without having to log in.

1. Log in to the WebSphere® administrative console.
2. Expand **Security** and click **SSL certificate and key management**.
3. Under **Configuration settings**, click **Manage endpoint security configurations**.
4. Navigate to the outbound configuration for the cell and node where the Unica Platform is deployed.
5. Under **Related Items**, click **Key stores and certificates** and click the **NodeDefaultTrustStore** key store.
6. Under **Additional Properties**, click **Signer certificates** and **Retrieve From Port**.

Complete fields as follows.

- **Host name:** `welcome.coremetrics.com`
- **Port:** 443
- **Alias:** `coremetrics_cert`


Digital Analytics integration with Websense using a custom proxy

Unica Platform provides a custom proxy to enable integration between Unica Campaign hosted on premises and Digital Analytics in the cloud when Websense is a required component of the environment.

The custom proxy is supported with the WebSphere application server only.

After the custom proxy is installed, you can configure single sign-on and integration between Digital Analytics and Unica Campaign.

The custom proxy is a Java servlet implementation that acts as a forward proxy. It is injected between the Unica Campaign listener and Digital Analytics. The custom proxy acts as an end point for the Unica Campaign listener to invoke Digital Analytics APIs. Internally, the custom proxy authenticates itself with the Websense content gateway and then securely invokes the APIs outside the network.



Deploying the custom proxy on WebSphere

Perform this procedure to install the custom proxy. This custom proxy is supported with the WebSphere application server only.

Note that you can deploy ProxyServer application in the same WebSphere Profile where you deployed Unica Campaign, or you can use different WebSphere profile.

1. Copy the `ProxyServer.war` file to a location that can be accessed from the WebSphere server.

You can find the `ProxyServer.war` file in the `tools\lib` directory under your Unica Platform installation.

2. Deploy the `ProxyServer.war` file, following these guidelines.
 - Select the **Detailed - Show all installation options and parameters** path for installation.
 - You can provide any application name.
 - You do not have to select **Precompile JavaServer Pages files**.
 - On the Initialize parameters for servlets page, complete the fields as shown below.
 - **proxy_host** - Host URL or IP address of the Websense server
 - **proxy_port** - Port number of the Websense server
 - **proxy_username**- User name for Websense authentication
 - **Proxy_password** - Password for Websense authentication
 - **target_url** - End point URL of Digital Analytics, already configured in Unica Campaign
 - On the Map context roots for Web modules page, set the Context Root to `proxy`.
 - When deployment is complete, access the ProxyServer application in a browser at `http://WebSphere_host:Port/proxy`.

You should receive a message: IBM OCM Secure Proxy Server V.x

Importing the Digital Analytics certificate when WebSphere does not have outbound access

Use this procedure when WebSphere does not have outbound access to the Digital Analytics server.

1. Retrieve the Digital certificate from the Digital Analytics site.

To retrieve the certificate, go to the Digital Analytics URL and click the lock icon in your browser's address field. Your browser opens a window where you can download the certificate.

2. Import the certificate into the WebSphere JVM using java keytool.

For example (line breaks added):

```
/keytool -import -file DA_Certificate.cer  
-alias da_alias  
-keystore WebSphere_JRE_home/lib/security/cacerts
```

Provide the password. The default keytool password is changeit.

3. In the WebSphere administrative console, add the following custom properties.
 - javax.net.ssl.trustStore: *WebSphere_JRE_home/lib/security/cacerts*
 - javax.net.ssl.trustStorePassword: *your_password*
 - javax.net.ssl.trustStoreType: jks

Importing the Digital Analytics certificate when WebSphere has outbound access

Use this procedure when WebSphere has outbound access to the Digital Analytics server.

1. In the WebSphere administrative console, expand **Security**, click **SSL certificate and key management**.
2. Under **Configuration settings**, click **Manage endpoint security configurations**.
3. Select the appropriate outbound configuration to navigate to the **(cell):..Node0xCell:(node):..Node0x** management scope.

4. Under **Related Items**, click **Key stores and certificates** and click the **NodeDefaultTrustStore** (or the KeyStore you have used in WebSphere application server) key store.
5. Under **Additional Properties**, click **Signer certificates** and **Retrieve from port**.
 - a. In the **Host** field, enter the Digital Analytics server name.
For example, `export.coremetrics.com`.
 - b. In the **Port** field, enter 443
 - c. In the **Alias** field, enter an alias name.
6. Click **Retrieve Signer Information** and verify that the certificate information is for a certificate that you can trust. .
7. Apply and save your configuration.

Next steps

After you install the custom proxy server and import the Digital Analytics certificate, your next steps are to enable single sign-on and configure integration between Digital Analytics and Unica Campaign.

To finish setting up your environment, perform the following procedures.

- Set up single sign on as described in the *Unica Platform Administrator's Guide*, in the chapter titled "Single sign-on between Unica and Digital Analytics."
- Set up integration as described in the *Unica Campaign Administrator's Guide*, in the chapter titled "Unica Campaign integration with other products."



Important: The integration procedure includes setting the `ServiceURL` configuration property under **Campaign | partitions | partition[n] | Coremetrics**. When you use the custom proxy, you must set this property to `http://WebSphere_host:Port/proxy`, and restart the Unica Platform web application.

Integration between Unica and Windows™ Active Directory

Unica Platform can be configured to integrate with Windows™ Active Directory server or another LDAP (Lightweight Directory Access Protocol) server. By integrating Unica with a directory server, you can maintain users and groups in one centralized location. Integration provides a flexible model for extending the enterprise authorization policies into Unica applications. Integration reduces support costs and the time needed to deploy an application in production.

See the Recommended Software Environments and Minimum System Requirements document for a list of supported directory servers.

Active Directory integration features

Unica Platform integration with Windows™ Active Directory provides the features described in this section.

Authentication with Active Directory integration

Unica applications query Unica Platform for user authorization information.

- Previous versions of Unica Platform supported NTLMv1 based Microsoft Windows Integrated login. With the arrival of Microsoft Windows 2008 Server and Microsoft Windows 7, the default minimum standard has changed and requires the NTLMv2 protocol. NTLMv2 is not natively supported by Unica Platform.

However, you can configure NTLMv2 authentication, so that users are authenticated to all Unica applications when they log in to the corporate network, and no password is required to log in to Unica applications. User authentication is based on their Windows™ login, bypassing the applications' login screens.

To configure NTLMv2 authentication, you perform the steps described in this chapter.

- If NTLMv2 authentication is not enabled, users must still log in on the Unica login screen, using their Windows™ credentials.

Managing internal and external users

When NTLMv2 authentication is enabled, all users are created and maintained in the Active Directory server. (You do not have the option of creating some users in Unica Platform, which are known as internal users in this guide). If you require the ability to create internal users, do not enable NTLMv2 authentication.

When integration is configured, you cannot add, modify, or delete the imported user accounts in Unica Platform. You must perform these management tasks on the LDAP side, and your changes are imported when synchronization occurs. If you modify imported user accounts in Unica Platform, users may encounter problems with authentication.

Any user accounts you delete on the LDAP side are not deleted from Unica Platform. You should disable these accounts manually in Unica Platform. It is safer to disable these deleted user accounts rather than deleting them, because users have folder ownership privileges in Unica Campaign, and if you delete a user account that owns a folder, objects in that folder will no longer be available.

Synchronization

When Unica is configured to integrate with an Active Directory server, users and groups are synchronized automatically at pre-defined intervals.

Automatic synchronization has limited functionality.

- Automatic synchronization updates user attributes only. Because group membership changes such as adding, removing, or changing members in a group require administrator oversight, import of these changes is confined to the manual synchronization process by default.
- Users deleted from the LDAP server are not deleted during automatic synchronization.

You can force a full synchronization of all users and groups by using the Synchronize function in the Users area of Unica. Alternatively, you can contact Services to request that they set a hidden configuration property that causes the automatic synchronization to perform a full synchronization.

Importing users based on groups or attributes

You can choose one of two types of filtering to select the user accounts that are imported from the LDAP server into Unica Platform.

You must choose between group based or attribute based import; multiple methods are not supported simultaneously.

Group based import

Unica Platform imports groups and their users from the directory server database through a periodic synchronization task that automatically retrieves information from the directory server. When Unica Platform imports users and groups from the server database, group memberships are not changed. To pick up these changes, you must perform a manual synchronization.

You can assign Unica privileges by mapping an Active Directory group to an Unica group. This mapping allows any new users added to the mapped Active Directory group to assume the privileges set for the corresponding Unica group.

A subgroup in Unica Platform does not inherit the Active Directory mappings or user memberships assigned to its parents.

Details for configuring group based import are provided in the remainder of this chapter.

Attribute based import

If you do not want to create groups in your Active Directory server that are specific to Unica products, you have the option to control the users who are imported by specifying attributes. To achieve this, you would do the following during the configuration process.

1. Determine the string used in your Active Directory server for the attribute on which you want to filter.
2. Set the **Unica Platform | Security | LDAP synchronization | LDAP user reference attribute name** property to `DN`.

This indicates to Unica Platform that the synchronization is not based on a group with member references but is based on an Org Unit or an Org.

3. When you configure the **LDAP reference map** property, set the Filter portion of the value to the attribute on which you want to search. For the Filter, use the string you determined in step 1.

When you use attribute based synchronization, the periodic synchronization is always a full synchronization, instead of a partial synchronization, which is done for group based synchronization. For attribute based synchronization, you should set the **LDAP sync interval** property to a high value, or set it to 0 to turn off automatic synchronization and rely on manual full synchronization when users are added to the directory.

Follow the instructions provided in the remainder of this chapter to configure integration, using the instructions above in the steps where you set configuration properties.

About Active Directory and partitions

In multi-partition environments, user partition membership is determined by the group to which the user belongs, when that group is assigned to a partition. A user can belong to only one partition. Therefore, if a user is a member of more than one Active Directory group, and these groups are mapped to Unica groups that are assigned to different partitions, the system must choose a single partition for that user.

You should try to avoid this situation. However, if it occurs, the partition of the Unica group most recently mapped to an Active Directory group is the one that the user belongs to. To determine which Active Directory group was most recently mapped, look at the LDAP group mappings displayed in the Configuration area. They are displayed in chronological order, with the most recent mapping listed last.

Special characters in login names

Only three special characters are allowed in login names: dot (.), underscore (_), and hyphen (-). If any other special characters (including spaces) are present in the login name of a user you plan to import into Unica Platform from your Active Directory server, you must change the login name so that the user does not encounter issues when logging out or performing administrative tasks (if the user has administration privileges).

Active Directory integration prerequisites

To take advantage of the Windows™ Active Directory integration features, Unica applications must be installed on a supported operating system.

In addition, to implement NTLMv2 authentication, users accessing Unica applications must:

- Use a system running a supported Windows™ operating system.
- Log in as a member of the Windows™ Active Directory domain against which Unica is authenticating.
- Use a supported browser.

Configuration process roadmap: Active Directory integration

Use this configuration process roadmap to scan the tasks required to integrate Unica with Windows™ Active Directory. The Topic column provides links to the topics that describe the tasks in detail.

Table 38. Configuration process roadmap: Active Directory integration

Topic	Information
Obtaining required information (on page 164)	Obtain information about your Windows™ Active Directory server, which is required for integration with Unica.
Group membership, mapping, and application access (on page 165)	If you are using group based synchronization, identify or create the groups in Unica Platform to which you will map your Active Directory groups.
Storing directory server credentials in Unica Platform (on page 166)	If your directory server does not allow anonymous access (the most common configuration), configure an Unica user account to hold a directory server administrator user name and password.

Table 38. Configuration process roadmap: Active Directory integration (continued)

Topic	Information
<ul style="list-style-type: none"> • Setting LDAP login method connection properties in Unica (on page 168) • Setting LDAP synchronization properties (on page 168) • Setting user attributes map properties (on page 169) • Mapping LDAP groups to Unica groups (on page 171) 	Configure the Unica Platform for integration by setting values on the Configuration page.
Testing synchronization (on page 171)	Verify that users are imported as expected, and if you are using group based synchronization, verify that users and groups are synchronizing properly.
Setting up an Active Directory user with PlatformAdminRole permissions (on page 172)	Set up administrator access to Unica Platform, required when NTLMv2 authentication is enabled.
Setting the security mode to enable NTLMv2 authentication (on page 172)	Set the security mode values on the Configuration page.
Configuring Internet Explorer (on page)	Set a custom security level in every instance of Internet Explorer that is used to access Unica. This is required with NTLMv2 authentication, to prevent users from being presented with the Unica login screen.
Restarting the web application server (on page 173)	This step is required to ensure that all of your changes are applied.
Testing login as an Active Directory user (on page 173)	Verify that you can log in to Unica as an Active Directory user.

Obtaining required information

Obtain the required information about the directory server with which you want to integrate.

You use this information during the configuration process, to store directory server credentials and to set configuration property values.

Obtain the following information.

- Obtain the server host name and port.
- Identify a user who has search permissions on the directory server, and gather the following information about the user.
 - login name
 - password
 - Distinguished Name (DN)
- Obtain the following for the directory server.
 - Fully qualified host name or IP address
 - The port on which server listens
- Determine the string that your directory server uses for the user attribute in the Group object. Typically, this value is `uniquemember` in LDAP servers and `member` in Windows™ Active Directory servers. You should verify this on your directory server.
- Obtain the following required user attributes.
 - Determine the string that your directory server uses for the user login attribute. This string is always required. Typically, this value is `uid` in LDAP servers and `sAMAccountName` in Windows™ Active Directory servers. Verify this string on your directory server.
 - Only if Unica Campaign is installed in a UNIX™ environment, determine the string that your directory server uses for the alternate login attribute.
- If you are using attribute based synchronization, obtain the strings used for the attributes (one or more) that you want to use for this purpose.
- If you want Unica Platform to import additional (optional) user attributes stored in your directory server, determine the strings that your directory server uses for the following.
 - First name
 - Last name

- User title
- Department
- Company
- Country
- User email
- Address 1
- Work phone
- Mobile phone
- Home phone

About Distinguished Names

To enable directory server integration in Unica, you must determine the Distinguished Name (DN) for a user and for groups. The DN of an object on the directory server is the complete path through the directory server tree structure to that object.

DNs are made up of these components:

- **Organizational Unit (OU).** This attribute is used to specify a namespace based on organizational structure. An OU is usually associated with a user-created directory server container or folder.
- **Common Name (CN).** This attribute represents the object itself within the directory server.
- **Domain Component (DC).** A Distinguished Name that uses DC attributes has one DC for every domain level below root. In other words, there is a DC attribute for every item separated by a dot in the domain name.

Use your directory server's Administration console to determine an object's Distinguished Name.

Group membership, mapping, and application access

When you plan how to map your directory server groups to Unica Platform groups, follow the guidelines described here.

- Identify or create the directory server groups whose members you want to import into the Unica Platform. When these groups are mapped to Unica Platform groups, members of these groups are automatically created as Unica users.

Members of your directory server's subgroups are not imported automatically. To import users from subgroups, you must map the subgroups to Unica Platform groups or subgroups.

You must map only static directory server groups; dynamic or virtual groups are not supported.

- Identify or create the groups in the Unica Platform to which you will map directory server groups.
- Assign appropriate application access to the groups you plan to map.

Storing directory server credentials in Unica Platform

If your directory server does not allow anonymous access, you must configure an Unica user account to hold the user name and password of a directory server user, as described in the following procedure.

1. Log in to Unica as a user with Admin access.
2. Select or create an Unica user account to hold the directory server credentials of an LDAP user with read access over all of the user and group information in the LDAP server. Follow these guidelines.
 - In a later step, you will set the value of the `Unica Platform user for LDAP credentials` configuration property to the user name for this Unica user account. The default value of this property is `asm_admin`, a user that exists in every new Unica Platform installation. You can use the `asm_admin` account to hold the directory server credentials.
 - The user name of this Unica user account must not match the user name of any directory server user.
3. Add a data source for this Unica user account to store the credentials that Unica Platform uses to connect with the LDAP server. Follow these guidelines.

Table 39. Data source fields for storing credentials

Field	Guideline
Data Source Name	<p>You can enter any name, but note that in a later step, the value of the <code>Data source for LDAP credentials</code> configuration property must match the data source name you use. To match the default value of this property so that you do not have to set the value, name your data source <code>LDAPServer</code>.</p>
Data Source Login	<p>Enter the Distinguished Name (DN) of the administrative user with read access over all of the directory server user and group information that will be synchronized with Unica. The DN resembles the following:</p> <pre>uidcn=user1,ou=someGroup,dc=systemName,dc=com</pre> <p>Alternatively, you can use the root user account that has access to all groups on your LDAP server. The default root user and how to specify this user for the supported directory servers are as follows.</p> <ul style="list-style-type: none"> • The root user for Active Directory Server is Administrator. You can specify this user as follows. <pre>domain\ldap_admin_username</pre> • The root user for Oracle Directory Server is Directory Manager. You can specify this user as follows. <pre>cn=Directory Manager</pre> • The root user for IBM Security Directory Server is root. You can specify this user as follows. <pre>cn=root</pre>
Data Source Password	<p>Enter the password of the administrative user whose login name you entered in the Data Source Login field.</p>

Setting LDAP login method connection properties in Unica

LDAP login method properties specify connection details the system uses to connect to the directory server.

1. Click **Settings > Configuration** and navigate to the **Unica Platform | Security | Login method details | LDAP** category.
2. Set values of the following configuration properties.

See the related reference for details on how to set each property.

- LDAP server host name
- LDAP server port
- User search filter
- Use credentials stored in Unica Platform
- Unica Platform user for LDAP credentials
- Data source for LDAP credentials
- Base DN
- Require SSL for LDAP connection

Setting LDAP synchronization properties

LDAP synchronization properties specify details that the system uses to log into the directory server and identify users to import. Some of these properties also control the frequency and other details of the automatic synchronization process.

1. Click **Settings > Configuration** and navigate to the **Platform | Security | LDAP Synchronization** category.
2. Set values of the following configuration properties in the **LDAP properties** section.

See each property's context help or the related topic link in this section for instructions on setting the values.

- LDAP sync enabled
- LDAP sync interval
- LDAP sync delay
- LDAP sync timeout

- LDAP sync scope
- LDAP provider URL
- Require SSL for LDAP connection (optional)
- LDAP config Unica Platform group delimiter
- LDAP reference config delimiter
- Unica Platform user for LDAP credentials
- Data source for LDAP credentials
- LDAP user reference attribute name
- LDAP BaseDN periodic search disabled
- User login
- Various user attributes such as department, country, and user title (optional)

Setting user attributes map properties

These properties specify the user attributes that the system imports from the directory server.

1. Click **Settings > Configuration** and navigate to the **Platform | Security | LDAP Synchronization** category.
2. Set values in the **User attributes map** section to map the listed Unica user attributes to the user attributes in your directory server.

If you are using group based synchronization, the only property you are required to map is `User login`. Typically, this value is `uid` in LDAP servers and `sAMAccountName` in Windows™ Active Directory servers. Use the value you verified as described in "Obtaining required information."

If you are using attribute based synchronization, map the attributes on which you want to search.

Note the following.

- The properties that you map here are replaced for the imported users each time Unica Platform synchronizes with your directory server.
- Unica Platform requires that email addresses conform to the definition stated in [RFC 821](#). If the email addresses on your directory server do not conform to this standard, do not map them as attributes to be imported.
- If your directory server database allows an attribute to have more characters than is allowed in the Unica Platform system tables, as shown in the following table, the attribute value is truncated to fit.

Table 40. Number of characters allowed for user attributes

Attribute	Allowed length
User login (required)	256
First name	128
Last name	128
User title	128
Department	128
Company	128
Country	128
User email	128
Address 1	128
Work phone	20
Mobile phone	20
Home phone	20
Alternate login (required on UNIX™)	256

Mapping LDAP groups to Unica groups

Users who belong to the directory server groups you map here are imported and made members of the Unica Platform group or groups specified here.



Important: Do not map any of the groups that have the `asm_admin` user as a member.

1. Click **Settings > Configuration** and navigate to the **Unica | Unica Platform | Security | LDAP Synchronization | LDAP reference to Unica Platform group map** category.
2. For each directory server group you want to map to a Unica Platform group, create an **LDAP reference to Unica Platform group** category by selecting the *(LDAP reference to Unica Platform group map)* template. Set the following properties.
 - New category name
 - LDAP reference map
 - Unica Platform group

For example, the following values map the LDAP`MarketingPlatformUsers` group to the Unica Platform `marketingopsUsers` and `campaignUsers` groups (`FILTER` is omitted).

- LDAP reference: `cn=MarketingPlatformUsers,cn=Users,dc=myCompany,dc=com`
- Unica Platform group: `marketingopsUsers;campaignUsers`

Testing synchronization

Verify that users and groups are correctly synchronized between your servers.

1. Log in to Unica as an Unica user with Admin privileges (not a directory server user).
2. Force synchronization by clicking **Synchronize** on the **Settings > Users** page.
3. Perform the following checks.
 - Verify that users are imported from the LDAP server as expected.
 - If you are using group based synchronization, verify that Unica Platform group memberships match the expected mapping to directory server groups.

Setting up an Active Directory user with PlatformAdminRole permissions

When NTLMv2 authentication is enabled, you can not log in to Unica as `platform_admin`, so you must perform the following procedure in order to have administrator access to Unica Platform.

1. Log in to Unica as an internal user (a user created in Unica Platform rather than a user imported from Active Directory). This must be a user with PlatformAdminRole permissions in the Unica Platform.
2. Create a Unica Platform group and assign the PlatformAdminRole role to it.
3. Ensure that at least one Windows™ Active Directory user is a member of this group.

Setting the security mode to enable NTLMv2 authentication

Only if you want to enable NTLMv2 authentication, set configuration properties as described in this procedure.

Configure NTLMv2 authentication.

Click **Settings > Configuration** and set configuration properties as shown in the following table.

Table 41. Configuration property values for NTLMv2

Property	Value
Platform Security Login method	Select the <code>web access control</code> option.
Platform Security Login method details Web access control Web access control header variable	Enter the variable name as specified in the re-write rules.
Platform Security Login method details Web access control Username pattern	Enter <code>\w*</code>
General Navigation Platform URL	Enter the IIS site URL.

Restarting the web application server

Restart the web application server to ensure that all of your configuration changes are applied.

Testing login as an Active Directory user

Verify the configuration by logging in to Unica with an appropriate Windows™ Active Directory user account.

1. Log in to Windows™ as an Active Directory user who is a member of an Active Directory group mapped to a Unica Platform group that has been assigned a role in the Unica Platform.
2. Point your browser to the Unica URL.

If you have enabled NTLMv2 authentication, you should not see the Unica login screen, and you should be allowed to access the Unica user interface.

If you have not enabled NTLMv2 authentication, you should be able to log in with your Windows credentials.

If you cannot log in, see [restoreAccess \(on page 327\)](#).

Integration between Unica and LDAP servers

Unica Platform can be configured to integrate with Windows™ Active Directory server or another LDAP (Lightweight Directory Access Protocol) server. By integrating Unica with a directory server, you can maintain users and groups in one centralized location. Integration provides a flexible model for extending the enterprise authorization policies into Unica applications. Integration reduces support costs and the time needed to deploy an application in production.

See the Recommended Software Environments and Minimum System Requirements document for a list of supported directory servers.

LDAP integration features

Unica Platform integration with LDAP provides the features described in this section.

Authentication with LDAP integration

Unica applications query Unica Platform for user authorization information. When LDAP integration is implemented, users enter their valid LDAP user name and password for authentication to Unica applications.

Managing internal and external users

When integration is configured, you cannot add, modify, or delete the imported user accounts in Unica Platform. You must perform these management tasks on the LDAP side, and your changes will be imported when synchronization occurs. If you modify imported user accounts in Unica Platform, users may encounter problems with authentication.

Any user accounts you delete on the LDAP side are not deleted from Unica Platform. You should disable these accounts manually in Unica Platform. It is safer to disable these deleted user accounts rather than deleting them, because users have folder ownership privileges in Unica Campaign, and if you delete a user account that owns a folder, objects in that folder will no longer be available.

Synchronization

When Unica is configured to integrate with an LDAP server, users and groups are synchronized automatically at pre-defined intervals.

Automatic synchronization has limited functionality.

- Automatic synchronization updates user attributes only. Because group membership changes such as adding, removing, or changing members in a group require administrator oversight, import of these changes is confined to the manual synchronization process by default.
- Users deleted from the LDAP server are not deleted during automatic synchronization.

You can force a full synchronization of all users and groups by using the Synchronize function in the Users area of Unica. Alternatively, you can contact Services to request that they set a hidden configuration property that causes the automatic synchronization to perform a full synchronization.

Importing users based on groups or attributes

You can choose one of two types of filtering to select the user accounts that are imported from the LDAP server into Unica Platform.

You must choose between group based or attribute based import; multiple methods are not supported simultaneously.

Group based import

Unica Platform imports groups and their users from the directory server database through a periodic synchronization task that automatically retrieves information from the directory server. When Unica Platform imports users and groups from the server database, group memberships are not changed. To pick up these changes, you must perform a manual synchronization.



Note: The LDAP groups must have a unique name even if the groups are configured for separate partitions.

You can assign Unica privileges by mapping an LDAP group to an Unica group. This mapping allows any new users added to the mapped LDAP group to assume the privileges set for the corresponding Unica group.

A subgroup in Unica Platform does not inherit the LDAP mappings or user memberships assigned to its parents.

Details for configuring group based import are provided in the remainder of this chapter.

Attribute based import

If you do not want to create groups in your LDAP server that are specific to Unica products, you have the option to control the users who are imported by specifying attributes. To achieve this, you would do the following during the LDAP configuration process.

1. Determine the string used in your LDAP server for the attribute on which you want to filter.
2. Set the **Platform | Security | LDAP synchronization | LDAP user reference attribute name** property to DN.

This indicates to Unica Platform that the synchronization is not based on a group with member references but is based on an Org Unit or an Org.

3. When you configure the **LDAP reference map** property, set the Filter portion of the value to the attribute on which you want to search. For the Filter, use the string you determined in step 1.

When you use attribute based synchronization, the periodic synchronization is always a full synchronization, instead of a partial synchronization, which is done for group based synchronization. For attribute based synchronization, you should set the **LDAP sync interval** property to a high value, or set it to 0 to turn off automatic synchronization and rely on manual full synchronization when users are added to the directory.

About LDAP and partitions

In multi-partition environments, user partition membership is determined by the group to which the user belongs, when that group is assigned to a partition. A user can belong to only one partition. Therefore, if a user is a member of more than one LDAP group, and these groups are mapped to Unica groups that are assigned to different partitions, the system must choose a single partition for that user.

You should try to avoid this situation. However, if it occurs, the partition of the Unica group most recently mapped to an LDAP group is the one that the user belongs to. To determine which LDAP group was most recently mapped, look at the LDAP group mappings displayed in the Configuration area. They are displayed in chronological order, with the most recent mapping listed last.

Support for internal and external users

Unica supports two types of user accounts and groups.

- **Internal** - User accounts and groups that are created within Unica using the Unica security user interface. These users are authenticated through Unica Platform.
- **External** - User accounts and groups that are imported into Unica through synchronization with a supported LDAP server. This synchronization occurs only if Unica has been configured to integrate with the LDAP server. These users are authenticated through the LDAP server.

You may want to have both types of users and groups if, for example, you want to give your customers access to Unica applications without adding them to your LDAP server as full corporate users.

Using this hybrid authentication model requires more maintenance than a pure LDAP authentication model does.

Special characters in login names

Only three special characters are allowed in login names: dot (.), underscore (_), and hyphen (-). If any other special characters (including spaces) are present in the login name of a user you plan to import into Unica Platform from your LDAP server, you must change the login name so that the user does not encounter issues when logging out or performing administrative tasks (if the user has administration privileges).

LDAP integration prerequisites

To take advantage of the LDAP integration features, Unica applications must be installed on a supported operating system.

Configuration process roadmap: LDAP integration

Use this configuration process roadmap to scan the tasks required to integrate Unica with LDAP. The Topic column provides links to the topics that describe the tasks in detail.

Table 42. Configuration process roadmap: LDAP integration

Topic	Information
Obtaining required information (on page 164)	Obtain information about your LDAP server, which is needed for integration with Unica.
Group membership, mapping, and application access (on page 165)	If you are using group based synchronization, identify or create the groups in Unica Platform to which you will map your LDAP groups.
Storing directory server credentials in Unica Platform (on page 166)	If your directory server does not allow anonymous access (the most common configuration), configure an Unica user account to hold a directory server administrator user name and password.
<ul style="list-style-type: none"> • Setting LDAP login method connection properties in Unica (on page 168) • Setting LDAP synchronization properties (on page 168) • Setting user attributes map properties (on page 169) • Mapping LDAP groups to Unica groups (on page 171) 	Configure the Unica Platform for integration by setting values on the Configuration page.
Testing synchronization (on page 171)	Verify that users are imported as expected, and if you are using group based synchronization, verify that groups are synchronizing properly.
Setting the security mode to LDAP (on page 187)	Set the security mode values on the Configuration page.

Table 42. Configuration process roadmap: LDAP integration (continued)

Topic	Information
Restarting the web application server (on page 173)	This step is required to ensure that all of your changes are applied.
Testing login as an LDAP user (on page 187)	Verify that you can log in to Unica as an LDAP user.

Obtaining required information

Obtain the required information about the directory server with which you want to integrate. You use this information during the configuration process, to store directory server credentials and to set configuration property values.

Obtain the following information.

- Obtain the server host name and port.
- Identify a user who has search permissions on the directory server, and gather the following information about the user.
 - login name
 - password
 - Distinguished Name (DN)
- Obtain the following for the directory server.
 - Fully qualified host name or IP address
 - The port on which server listens
- Determine the string that your directory server uses for the user attribute in the Group object. Typically, this value is `uniquemember` in LDAP servers and `member` in Windows™ Active Directory servers. You should verify this on your directory server.
- Obtain the following required user attributes.

- Determine the string that your directory server uses for the user login attribute. This string is always required. Typically, this value is `uid` in LDAP servers and `sAMAccountName` in Windows™ Active Directory servers. Verify this string on your directory server.
- Only if Unica Campaign is installed in a UNIX™ environment, determine the string that your directory server uses for the alternate login attribute.
- If you are using attribute based synchronization, obtain the strings used for the attributes (one or more) that you want to use for this purpose.
- If you want Unica Platform to import additional (optional) user attributes stored in your directory server, determine the strings that your directory server uses for the following.
 - First name
 - Last name
 - User title
 - Department
 - Company
 - Country
 - User email
 - Address 1
 - Work phone
 - Mobile phone
 - Home phone

About Distinguished Names

To enable directory server integration in Unica, you must determine the Distinguished Name (DN) for a user and for groups. The DN of an object on the directory server is the complete path through the directory server tree structure to that object.

DNs are made up of these components:

- **Organizational Unit (OU).** This attribute is used to specify a namespace based on organizational structure. An OU is usually associated with a user-created directory server container or folder.
- **Common Name (CN).** This attribute represents the object itself within the directory server.
- **Domain Component (DC).** A Distinguished Name that uses DC attributes has one DC for every domain level below root. In other words, there is a DC attribute for every item separated by a dot in the domain name.

Use your directory server's Administration console to determine an object's Distinguished Name.

Group membership, mapping, and application access

When you plan how to map your directory server groups to Unica Platform groups, follow the guidelines described here.

- Identify or create the directory server groups whose members you want to import into the Unica Platform. When these groups are mapped to Unica Platform groups, members of these groups are automatically created as Unica users.

Members of your directory server's subgroups are not imported automatically. To import users from subgroups, you must map the subgroups to Unica Platform groups or subgroups.

You must map only static directory server groups; dynamic or virtual groups are not supported.

- Identify or create the groups in the Unica Platform to which you will map directory server groups.
- Assign appropriate application access to the groups you plan to map.

Storing directory server credentials in Unica Platform

If your directory server does not allow anonymous access, you must configure an Unica user account to hold the user name and password of a directory server user, as described in the following procedure.

1. Log in to Unica as a user with Admin access.
2. Select or create an Unica user account to hold the directory server credentials of an LDAP user with read access over all of the user and group information in the LDAP server. Follow these guidelines.
 - In a later step, you will set the value of the `Unica Platform user for LDAP credentials` configuration property to the user name for this Unica user account. The default value of this property is `asm_admin`, a user that exists in every new Unica Platform installation. You can use the `asm_admin` account to hold the directory server credentials.
 - The user name of this Unica user account must not match the user name of any directory server user.
3. Add a data source for this Unica user account to store the credentials that Unica Platform uses to connect with the LDAP server. Follow these guidelines.

Table 43. Data source fields for storing credentials

Field	Guideline
Data Source Name	You can enter any name, but note that in a later step, the value of the <code>Data source for LDAP credentials</code> configuration property must match the data source name you use. To match the default value of this property so that you do not have to set the value, name your data source <code>LDAPServer</code> .
Data Source Login	Enter the Distinguished Name (DN) of the administrative user with read access over all of the directory server user and group information that will be synchronized with Unica. The DN resembles the following: <code>uidcn=user1,ou=someGroup,dc=systemName,dc=com</code> Alternatively, you can use the root user account that has access to all groups on your LDAP server. The default root user and how to specify this user for the supported directory servers are as follows.

Field	Guideline
	<ul style="list-style-type: none"> • The root user for Active Directory Server is Administrator. You can specify this user as follows. <code>domain\ldap_admin_username</code> • The root user for Oracle Directory Server is Directory Manager. You can specify this user as follows. <code>cn=Directory Manager</code> • The root user for IBM Security Directory Server is root. You can specify this user as follows. <code>cn=root</code>
Data Source Password	Enter the password of the administrative user whose login name you entered in the Data Source Login field.

Setting LDAP login method connection properties in Unica

LDAP login method properties specify connection details the system uses to connect to the directory server.

1. Click **Settings > Configuration** and navigate to the **Unica Platform | Security | Login method details | LDAP** category.
2. Set values of the following configuration properties.

See the related reference for details on how to set each property.

- LDAP server host name
- LDAP server port
- User search filter
- Use credentials stored in Unica Platform
- Unica Platform user for LDAP credentials
- Data source for LDAP credentials
- Base DN
- Require SSL for LDAP connection

Setting LDAP synchronization properties

LDAP synchronization properties specify details that the system uses to log into the directory server and identify users to import. Some of these properties also control the frequency and other details of the automatic synchronization process.

1. Click **Settings > Configuration** and navigate to the **Platform | Security | LDAP Synchronization** category.
2. Set values of the following configuration properties in the **LDAP properties** section.

See each property's context help or the related topic link in this section for instructions on setting the values.

- LDAP sync enabled
- LDAP sync interval
- LDAP sync delay
- LDAP sync timeout
- LDAP sync scope
- LDAP provider URL
- Require SSL for LDAP connection (optional)
- LDAP config Unica Platform group delimiter
- LDAP reference config delimiter
- Unica Platform user for LDAP credentials
- Data source for LDAP credentials
- LDAP user reference attribute name
- LDAP BasedN periodic search disabled
- User login
- Various user attributes such as department, country, and user title (optional)

Setting user attributes map properties

These properties specify the user attributes that the system imports from the directory server.

1. Click **Settings > Configuration** and navigate to the **Platform | Security | LDAP Synchronization** category.
2. Set values in the **User attributes map** section to map the listed Unica user attributes to the user attributes in your directory server.

If you are using group based synchronization, the only property you are required to map is `User login`. Typically, this value is `uid` in LDAP servers and `sAMAccountName` in Windows™ Active Directory servers. Use the value you verified as described in "Obtaining required information."

If you are using attribute based synchronization, map the attributes on which you want to search.

Note the following.

- The properties that you map here are replaced for the imported users each time Unica Platform synchronizes with your directory server.
- Unica Platform requires that email addresses conform to the definition stated in [RFC 821](#). If the email addresses on your directory server do not conform to this standard, do not map them as attributes to be imported.
- If your directory server database allows an attribute to have more characters than is allowed in the Unica Platform system tables, as shown in the following table, the attribute value is truncated to fit.

Table 44. Number of characters allowed for user attributes

Attribute	Allowed length
User login (required)	256
First name	128
Last name	128
User title	128
Department	128
Company	128

Attribute	Allowed length
Country	128
User email	128
Address 1	128
Work phone	20
Mobile phone	20
Home phone	20
Alternate login (required on UNIX™)	256

Mapping LDAP groups to Unica groups

Users who belong to the directory server groups you map here are imported and made members of the Unica Platform group or groups specified here.



Important: Do not map any of the groups that have the `asm_admin` user as a member.

1. Click **Settings > Configuration** and navigate to the **Unica | Unica Platform | Security | LDAP Synchronization | LDAP reference to Unica Platform group map** category.
2. For each directory server group you want to map to a Unica Platform group, create an **LDAP reference to Unica Platform group** category by selecting the *(LDAP reference to Unica Platform group map)* template. Set the following properties.
 - New category name
 - LDAP reference map
 - Unica Platform group

For example, the following values map the LDAP`MarketingPlatformUsers` group to the Unica Platform `marketingopsUsers` and `campaignUsers` groups (`FILTER` is omitted).

- LDAP reference: `cn=MarketingPlatformUsers,cn=Users,dc=myCompany,dc=com`
- Unica Platform group: `marketingopsUsers;campaignUsers`

Testing synchronization

Verify that users and groups are correctly synchronized between your servers.

1. Log in to Unica as an Unica user with Admin privileges (not a directory server user).
2. Force synchronization by clicking **Synchronize** on the **Settings > Users** page.
3. Perform the following checks.
 - Verify that users are imported from the LDAP server as expected.
 - If you are using group based synchronization, verify that Unica Platform group memberships match the expected mapping to directory server groups.

Setting the security mode to LDAP

Set security mode properties to allow LDAP users to log in to Unica applications.

1. Log in to Unica, click **Settings > Configuration**, and navigate to **Unica Platform | security**.
2. Set the value of the `Login method` property to `LDAP`.

Restarting the web application server

Restart the web application server to ensure that all of your configuration changes are applied.

Testing login as an LDAP user

Test your configuration by logging in to Unica as an LDAP user who is a member of an LDAP group mapped to a Unica Platform group that has been assigned access to Unica Platform.

Integration with web access control platforms

Organizations use web access control platforms to consolidate their security systems, which provide a portal that regulates user access to web sites. This section provides an overview of Unica integration with web access control platforms.

Authentication

When users access an application through a web access control portal, their authentication is managed through the web access control system. Web access control users who are also members of an LDAP group that is synchronized with Unica are authenticated to all Unica applications when they log in to the web access control system. These users do not see the Unica application login screens.


Authorization

Unica applications query Unica Platform for user authorization information. Unica Platform imports groups and their users from the LDAP database through a periodic synchronization task that automatically retrieves information from the LDAP server. When Unica Platform imports users and groups from the LDAP database, group memberships are maintained. These LDAP users are also exposed to the web access control system, so the web access control system and Unica are referencing a consistent set of users.


Additional authorization controls, including control over the application URLs to which users have access, are also available through most web access control systems.

Web access control integration diagrams

The following figure illustrates how Unica works with SiteMinder and an LDAP directory server to authenticate and authorize users.



The following figure illustrates how Unica works with IBM Security Access Manager and an LDAP directory server to authenticate and authorize users.



About context roots

You must unprotect URLs in your web access control system to enable various features in Unica products. To perform this task, you need to include the product context roots in the URLs.

The following table provides a list of the default context roots for the Unica products mentioned in this chapter. Your installation might use non-default context roots, but typically most installations accept the default.

The examples in this chapter use the default context roots. If your environment uses a non-standard context root, you must change the context root shown in the example URLs to the context root used in your environment.

Table 45. Context roots for Unica products

Product	Context root
Unica Platform	unica
Unica Campaign	Campaign
Unica Optimize	Campaign/optimize
Unica Plan	plan
Unica Collaborate	collaborate
Unica Interact	Campaign/interact

SiteMinder integration prerequisites

The following prerequisites must be met to integrate Unica with Netegrity SiteMinder.

- SiteMinder must be configured to use a web agent and a policy server.
- SiteMinder must be configured to pass the login name as an HTTP variable in the URL request to the Unica application.
- The Unica property **Web access control header variable** must be set to the name of the variable that SiteMinder uses for login names.

The default name for the SiteMinder login name variable is `sm_user`.

- The SiteMinder policy server must be configured to use LDAP as its repository for storing group members and user properties.
- The Unica application URLs provided by the web server hosting SiteMinder and the Java™ application server hosting the Unica application must refer to the same path.

- The web server hosting SiteMinder must be configured to redirect requests to the Unica application URL on the Java™ application server.
- All users who need to access Unica applications must be granted access in SiteMinder to the Unica web applications for HTTP `GET` and `POST` requests through SiteMinder.

See the remainder of this section for settings required to enable specific features or to support certain Unica products.

Configuring SiteMinder for Unica products

Unprotect objects in SiteMinder as described in this procedure to enable correct functioning of your Unica products.

1. Log in to the **Administer Policy Server** area of SiteMinder and click **Domains**.
2. Select the realm that applies to your installations, right-click **unprotecturl**, and select **Properties of Realm**.
3. For each of the applicable URLs as described in the following table, enter the URL in the **Resource Filter** text box, and under **Default Resource Protection**, select **Unprotected**.

Table 46. Un-protected objects required for Unica products

Product or feature	Objects
Unica Campaign	<ul style="list-style-type: none"> • <code>/Campaign/services/CampaignServices30Service</code> • <code>/Campaign/api/campaign/rest</code> • <code>/Campaign/FlowchartNotifyScheduler</code> • <code>/Campaign/OperationMonitor</code> • <code>http://host:port/Campaign/api/campaign/rest/deepsearch/partition</code> <p>Replace partition with the partition name.</p> <p>The following apply when integration with Engage is implemented.</p>

Product or feature	Objects
	<p>In the following URLs, replace partition with the partition name.</p> <ul style="list-style-type: none"> • <code>http://host:port/Campaign/jsp/engage/engageHome.jsp</code> • <code>http://host:port/Campaign/api/campaign/rest/engage/offers</code> • <code>http://host:port/Campaign/api/campaign/rest/engage/offer</code> • <code>http://host:port/Campaign/servlet/EngageUpload</code> • <code>http://host:port/Campaign/api/campaign/rest/engageimportlist/partition</code> • <code>http://host:port/Campaign/api/campaign/rest/engageimportlist/partition/jobid</code> <p>This URL is for checking the status of an import job. Replace jobid with your job ID.</p> <ul style="list-style-type: none"> • <code>http://host:port/Campaign/api/campaign/rest/engageimportlist/partition/schedule</code> • <code>http://host:port/Campaign/api/campaign/rest/engageimportlist/partition/channel/schedule</code> <p>This URL is for sending push or SMS messages. Channel is either <code>sms</code> or <code>push</code>.</p>
Unica Collaborate	<ul style="list-style-type: none"> • <code>/collaborate/affiniumcollaborate.jsp</code> • <code>/collaborate/services/CollaborateIntegrationServices1.0</code> • <code>/collaborate/flowchartRunNotifyServlet</code>

Product or feature	Objects
	<ul style="list-style-type: none"> • /collaborate/js/js_messages.jsp • /collaborate/js/format_symbols.jsp • /collaborate/alertsService
IBM eMessage	/Campaign/emessage/eventSinkServlet
Unica Interact	<ul style="list-style-type: none"> • /Campaign/interact/saveFlowchartAction.udo • /Campaign/interact/flowchartEventPatterns.udo • /Campaign/interact/testRunFlowchart.udo • /Campaign/interact/getProfileDataAction.udo • /Campaign/interact/manageIPB.udo • /Campaign/interact/flowchartRTAttr.udo • /Campaign/initOfferListResolution.udo • /Campaign/getOfferListResolutionStatus.udo
Unica Plan	<ul style="list-style-type: none"> • /plan/errorPage.jsp • /plan/alertsService • /plan/services • /plan/services/collabService • /plan/services/PlanIntegrationServices/1.0 • /plan/affiniumplan.jsp • /plan/invalid_user.jsp • /plan/js/js_messages.jsp • /plan/js/format_symbols.jsp • /unica/servlet/AJAXProxy • /plan/api/plan/flowchartApproval/flowchartApproval/validate

Product or feature	Objects
Unica Optimize	<ul style="list-style-type: none"> • <code>/Campaign/optimize/ext_runOptimizeSession.do</code> • <code>/Campaign/optimize/ext_optimizeSessionProgress.do</code> • <code>/Campaign/optimize/ext_doLogout.do</code>
IBM SPSS Modeler Advantage Enterprise Marketing Management Edition	<code>/unica/rest/spssUser</code>
Unica Platform data filters	<code>/unica/servlet/DataFiltering</code>
Unica notifications	<ul style="list-style-type: none"> • <code>unica/servlet/alertAJAXProxy</code> • <code>unica/notification/alertsCount</code>
Unica Scheduler	<code>/unica/servlet/SchedulerAPIServlet</code>

Enabling single logouts with SiteMinder

To enable a logout of SiteMinder when a user logs out of an Unica application, configure SiteMinder as follows.

1. Log in to the **Administer Policy Server** area of SiteMinder and set the `logoffUri` property to the URI of the Unica logout page.

For example: `/sm_realm/unica/j_spring_security_logout` where `sm_realm` is the SiteMinder security realm and `unica` is the Unica Platform context root.

2. Unprotect the Unica logout page, `/unica/jsp/frameworklogout.jsp` to ensure that SiteMinder does not force the user to sign in again to view the logout page.

IBM Security Access Manager integration prerequisites

The following prerequisites must be met to integrate Unica with IBM Security Access Manager.

- The IBM Security Access Manager WebSEAL junction must be configured to pass the user name (Short, not Full DN) as the HTTP variable in the URL request to the Unica application.
- The Unica property `Web access control header variable` must be set to the name of the variable that Security Access Manager uses for login names.

The default name for the Security Access Manager login name variable is `iv-user`.

- The IBM Security Access Manager policy server must be configured to use LDAP as its repository for storing group members and user attributes.
- The Unica application URLs defined by a WebSEAL junction and the Java™ application server hosting the Unica application must refer to the same path.
- All users who need to access Unica applications must belong to a group added to an Access Control List (ACL) with appropriate permissions. A WebSEAL junction that points to an application server where Unica Platform is deployed must be attached to this ACL.



Note: When users log out of an Unica application, they are not automatically logged out of IBM Security Access Manager. They must close their browser after they log out of an Unica application to log out of IBM Security Access Manager.

Configuring IBM Security Access Manager for Unica products

Unprotect objects in IBM Security Access Manager as described in this procedure to enable correct functioning of your Unica products.

1. Use Web Portal Manager to log in to the domain as a domain administrator.
2. Click **ACL > Create ACL**, complete the **Name** and **Description** fields, and click **Apply**.
3. Click **ACL > List ACL**, and from the Manage ACLs page, click the link for your ACL policy.
4. From the ACL Properties page, click **Create**, and create two entries for your ACL, as follows.

- For the first entry, set the entry type to **unauthenticated** and grant **Trx - Traverse, read, delete and execute** permissions.
 - For the second entry, set the entry type to **Any-other** and grant **Trx - Traverse, read, delete and execute** permissions.
5. On the ACL Properties page of the ACL, on the Attach tab, attach un-protected objects, as required for your product installations.

Use the complete path in IBM Security Access Manager, starting from WebSEAL.

Table 47. Un-protected objects required for Unica products

Product or feature	Objects
Unica Campaign	<ul style="list-style-type: none"> • <code>WebSEAL junction/Campaign/services/CampaignServices30Service</code> • <code>WebSEAL junction/Campaign/api/campaign/rest</code> • <code>WebSEAL junction/Campaign/FlowchartNotifyScheduler</code> • <code>WebSEAL junction/Campaign/initOfferListResolution.udo</code> • <code>WebSEAL junction/Campaign/getOfferListResolutionStatus.udo</code> • <code>WebSEAL junction/Campaign/OperationMonitor</code> • <code>WebSEAL junction/Campaign/api/campaign/rest</code> • <code>http://host:port/Campaign/api/campaign/rest/deepsearch/partition</code> <p>Replace partition with the partition name.</p> <p>The following apply when integration with Engage is implemented.</p> <p>In the following URLs, replace partition with the partition name.</p>

Product or feature	Objects
	<ul style="list-style-type: none"> • <code>http://host:port/Campaign/jsp/engage/engageHome.jsp</code> • <code>http://host:port/Campaign/api/campaign/rest/engage/offers</code> • <code>http://host:port/Campaign/api/campaign/rest/engage/offer</code> • <code>http://host:port/Campaign/servlet/EngageUpload</code> • <code>http://host:port/Campaign/api/campaign/rest/engageimportlist</code> • <code>http://host:port/Campaign/api/campaign/rest/engageimportlist/partition</code> • <code>http://host:port/Campaign/api/campaign/rest/engageimportlist/partition/jobid</code> <p>This URL is for checking the status of an import job. Replace jobid with your job ID.</p> <ul style="list-style-type: none"> • <code>http://host:port/Campaign/api/campaign/rest/engageimportlist/partition/schedule</code> • <code>http://host:port/Campaign/api/campaign/rest/engageimportlist/partition/channel/schedule</code> <p>This URL is for sending push or SMS messages. Channel is either <code>sms</code> or <code>push</code>.</p>
Unica Collaborate	<ul style="list-style-type: none"> • <code>WebSEAL junction/collaborate/affiniumcollaborate.jsp</code> • <code>WebSEAL junction/collaborate/services/CollaborateIntegrationServices1.0</code>

Product or feature	Objects
	<ul style="list-style-type: none"> • <code>WebSEAL junction/collaborate/flowchart-RunNotifyServlet</code> • <code>WebSEAL junction/collaborate/js/js_messages.jsp</code> • <code>WebSEAL junction/collaborate/js/format_symbols.jsp</code> • <code>WebSEAL junction/collaborate/alertsService</code>
IBM eMessage	<code>WebSEAL junction/Campaign/emessage/eventSinkServlet</code>
Unica Interact	<ul style="list-style-type: none"> • <code>WebSEAL junction/Campaign/interact/flowchartEventPatterns.udo</code> • <code>WebSEAL junction/Campaign/interact/saveFlowchartAction.udo</code> • <code>WebSEAL junction/Campaign/interact/testRunFlowchart.udo</code> • <code>WebSEAL junction/Campaign/interact/getProfileDataAction.udo</code> • <code>WebSEAL junction/Campaign/interact/manageIPB.udo</code> • <code>WebSEAL junction/Campaign/initOfferListResolution.udo</code> • <code>WebSEAL junction/Campaign/getOfferListResolutionStatus.udo</code>
Unica Plan	<ul style="list-style-type: none"> • <code>WebSEAL junction/plan/services</code> • <code>WebSEAL junction/plan/errorPage.jsp</code> • <code>WebSEAL junction/plan/alertsService</code> • <code>WebSEAL junction/plan/services/collabService</code>

Product or feature	Objects
	<ul style="list-style-type: none"> • <code>WebSEAL junction/plan/services/PlanIntegrationServices/1.0</code> • <code>WebSEAL junction/plan/affiniumplan.jsp</code> • <code>WebSEAL junction/plan/invalid_user.jsp</code> • <code>WebSEAL junction/plan/js/js_messages.jsp</code> • <code>WebSEAL junction/plan/js/format_symbols.jsp</code> • <code>WebSEAL junction/unica/servlet/AJAXProxy</code> • <code>WebSEAL junction//plan/api/plan/flowchartApproval/flowchartApproval/validate</code>
Unica Optimize	<ul style="list-style-type: none"> • <code>WebSEAL junction/Campaign/optimize/ext_runOptimizeSession.do</code> • <code>WebSEAL junction/Campaign/optimize/ext_optimizeSessionProgress.do</code> • <code>WebSEAL junction/Campaign/optimize/ext_doLogout.do</code>
IBM SPSS Modeler Advantage Enterprise Marketing Management Edition	<code>WebSEAL junction/unica/rest/spssUser</code>
Unica Platform data filters	<code>WebSEAL junction/unica/servlet/DataFiltering.</code>
Unica notifications	<ul style="list-style-type: none"> • <code>WebSEAL junction/unica/servlet/DataFiltering</code> • <code>WebSEAL junction/unica/servlet/alertAJAXProxy</code> • <code>WebSEAL junction/unica/notification/alertsCount</code>

Product or feature	Objects
Unica Scheduler	<code>WebSEAL junction/unica/servlet/Scheduler-APIServlet</code>
Enable a logout of IBM Security Access Manager when a user logs out of an Unica application	<ul style="list-style-type: none"> • <code>WebSEAL junction/unica/j_spring_security_logout</code> • <code>WebSEAL junction/unica/jsp/frameworklogout.jsp</code>
Unica Platform	<code>WebSEAL junctionWebSEAL junction/unica/css/access_control.css</code>

Configuration process roadmap: integrating Unica with a web access control system

Use this configuration process roadmap to scan the tasks required to integrate Unica with a web access control system. The Topic column provides links to the topics that describe the tasks in detail.

Table 48. Configuration process roadmap: integrating Unica with a web access control system

Topic	Information
Performing LDAP integration (on page 201)	Follow instructions for LDAP integration, stopping at the "Test synchronization" step.
Setting web access control connection properties in Unica (on page 201)	Set web access control integration properties on the Configuration page.

Table 48. Configuration process roadmap: integrating Unica with a web access control system (continued)

Topic	Information
Restarting the web application server (on page 173)	This step is required to ensure that all of your changes are applied.
Testing web access control synchronization and Unica login (on page 202)	Verify that users and groups synchronize correctly in your web access control system and that you can log in to Unica.

Performing LDAP integration

Perform all of the steps required for LDAP integration.

Setting web access control connection properties in Unica

To configure web access control integration, you set some configuration properties.

On the **Settings & Configuration** page, set values of the properties as described in the following table.

See the related reference for details on how to set each property.

Table 49. Properties for configuring web access control integration

Property	Value
Unica Unica Platform Security Login method details	Select <code>web access control</code> .
Unica Unica Platform Security Login method details Web	A Java™ regular expression used to extract the user login from the HTTP header variable in web access control software. You must XML-escape any XML characters in the regular expression. The

Property	Value
access control User-name pattern	recommended value for SiteMinder and IBM Security Access Manager is <code>\w*</code>
Unica Unica Platform Security Login method details Web access control Web access control header variable	The HTTP header variable configured in the web access control software, which is submitted to the web application server. By default, SiteMinder uses <code>sm_user</code> , and IBM Security Access Manager uses <code>iv-user</code> . For IBM Security Access Manager, set this value to the user name component of the IBM® Raw string, not the IBM® HTTP string.
Unica General Navigation Unica Platform URL	Set to <code>http://sm_host:sm_port/sm_realm/unica</code> where <ul style="list-style-type: none"> • <code>sm_host</code> is the name of the machine on which SiteMinder is installed • <code>sm_port</code> is the SiteMinder port number • <code>sm_realm</code> is the SiteMinder realm

Restarting the web application server

Restart the web application server to ensure that all of your configuration changes are applied.

Testing web access control synchronization and Unica login

Follow this procedure to test your integration.

1. Log in to your web access control system with an LDAP account that has been synchronized into your web access control system and has access to Unica Platform.
2. Verify that:
 - Users are imported as expected
 - Groups are imported as expected
 - Unica group memberships match the expected mapping to LDAP groups
3. Point your browser to the Unica Platform URL and log in.

You should be able to access Unica without being presented with the Unica login screen.

4. Use the following guidelines to resolve problems when your web access control software is Netegrity SiteMinder.
 - If you see an Unica login screen, the user account with which you logged in might not have been synchronized into SiteMinder.
 - If you are not able to access Unica, check that your SiteMinder configuration is correct. You can use the SiteMinder TestTool to verify that the user account with which you logged in has been authorized and granted access to Unica URLs in SiteMinder.
 - If you can access Unica, but navigation is not working correctly or images are not displaying, check to be sure that the web server hosting SiteMinder and the Java™ application server hosting Unica Platform use the same path to refer to Unica Platform.

Configuring integration with an SSL type of WebSEAL junction

Follow this procedure to configure Unica Platform integration with IBM Security Access Manager using an SSL type of WebSEAL junction.

For details on these procedures, see the documentation provided with IBM Security Access Manager and your web application server.

1. Generate or purchase SSL certificates and configure your web application server to use them.
2. Create a webSEAL certificate and configure IBM Security Access Manager to use it.
3. Import your webSEAL certificate into your web application server.
4. Import your web application server certificate into IBM Security Access Manager.
5. Create an SSL type of WebSEAL junction in IBM Security Access Manager.

If you install multiple Unica products, create a separate junction for each product.

6. Set the navigation URL configuration property on the **Settings & Configuration** page for each installed product.

The value should reflect the webSEAL junction used for that product. Follow this pattern:

```
https://machine_name_or_IP_address.domain_name:port_number/  
webSEAL_junction/context-root
```

To access Unica, use a URL such as the following:

```
https://machine_name_or_IP_address.domain_name:port_number/  
webSEAL_junction//unica
```

7. Unprotect URLs in IBM Security Access Manager as described elsewhere in this guide.

Alert and notification management

Unica Platform provides support for system alerts and user notifications sent by Unica products.

System alerts and user notifications sent by products appear in the user interface, as follows.

- **Alerts** contain information about system events. They appear in a pop-up window when a user logs in.

Examples are planned or unplanned server shutdowns.

- **Notifications** contain user-specific information about changes made to items in which the user has an interest, or tasks the user must perform. The user can view them by clicking the envelope icon in the top right of the window.

Examples are updates to a flowchart or mailing list, or reminders about a deadline for an assigned task.

Users can also subscribe to receive alerts and notifications by email, if Unica Platform has been configured to send them.

Within Unica Platform, the Unica Scheduler uses the notification feature.

Alert and notification subscriptions

Users can choose to have system alerts and notifications delivered in emails, if Unica Platform is configured to send them. They can also select the level to which they subscribe.

For example, they can choose to receive only Critical system alerts, and receive all notifications. The subscription levels differ depending on the product that is sending the system alerts and notifications.



Note: All system alerts are always delivered in pop-up windows when users log in to Unica. Users cannot control these by changing their subscriptions.

When users log in to Unica, the **System alerts** window is displayed only if there are any new or unread alerts. Users can mark an alert as read by selecting the alert and clicking **Mark as read** in the **System alerts** window.

Setting system alert and notification subscriptions

Non-administrative users can set their own subscriptions for system alerts and notifications by following this procedure

1. Log in to Unica and select `Settings > Users`.

Your account detail page opens.

2. Click **Notification Subscription** on your account detail page.
3. Use the checkboxes to select the level of notifications you want to receive, and whether to receive them in the user interface, by email, in both places, or not at all.
4. Click **Submit** to save your changes.

Configuring email notifications in Unica

Follow this procedure to configure the Unica Platform to send system alert and notification emails to users. You must have an email server set up before you start.

Obtain the following information about your mail server.

- The protocol used by your mail server.
- The port on which the mail server listens.
- The name of the machine that hosts your mail server.
- Whether your mail server requires authentication.
- If your mail server requires authentication, an account name and password on the mail server.

 **Tip:** See the related references if you need additional details about performing this procedure.

1. If your mail server requires authentication, save a mail server account name and password as a data source in a Unica Platform user account.

Use an internal Unica Platform user account, not a user imported from an LDAP server.

Make a note of the Unica Platform user name and the data source name, as you will use them in step 3.

2. Log in to Unica as a user with administrative privileges in Unica Platform.
3. On the **Settings > Configuration** page, set the configuration properties in the following categories.

- `General | Communication | Email`
- `Platform | Notifications`

Use the information you obtained about your mail server to set values.

Implementation of one-way SSL

This section describes one-way SSL in Unica.

Any communication that needs to be secured between two applications connecting over a network can be transmitted using the Secure Sockets Layer (SSL) protocol.

SSL provides secure connections by:

- Allowing an application to authenticate the identity of another application
- Using a private key to encrypt and decrypt data transferred over the SSL connection

When applications are configured for SSL, web traffic is over HTTPS instead of HTTP as reflected in the URLs.

When processes communicate with each other, the process making a request acts as the client and the process responding to a request acts as the server. For complete security, SSL should be implemented for all forms of communication with Unica products.

SSL can be configured one-way or two-way. With one-way SSL, the server is required to present a certificate to the client but the client is not required to present a certificate to the server. To successfully negotiate the SSL connection, the client must authenticate the server. The server accepts a connection from any client.

Overview of SSL certificates

Read this section to understand SSL certificates in general.

What is a certificate?

A certificate is a digital signature that identifies the server as some named entity. Certificates can be signed by a certificate authority (CA) that vouches for the identity of the server, or they can be self-signed. Verisign or Thawte are examples of CAs. A self-signed certificate is one where the CA is the same entity that the certificate claims to identify.

Server-side certificates

Every server that is intended to provide SSL communication, whether it is an application server or an Unica application such as the Unica Campaign listener, needs to serve up a certificate.

Client side truststores

When the client receives the server certificate, it is up to the client to determine whether to trust the certificate. A client trusts a server certificate automatically if the certificate exists in the client truststore. A truststore is a database of trusted certificates.

Modern browsers have a truststore loaded with the common certificates endorsed by CAs. This is why you are not prompted when entering the secured site at major merchant web sites - they use certificates signed by a CA. But, when you log in to a HCL application that serves up a self-signed certificate, you see the prompt.

Browsers check that the host name of the server matches the subject name in the certificate (the subject name is the Common Name used in the Distinguished Name, which you supply when you request a certificate). The browser may issue a warning if these two names do not match.

When a browser accesses a HCL application secured with a certificate it does not recognize (for example, a self-signed certificate), a dialog window opens, asking if the user wants to continue. If the user chooses to install the certificate to the local truststore, the prompt does not appear again.

Client and server roles in Unica

Unica application components can act as either the client or the server in a communication, depending on the situation.


Most Unica applications consist of two parts.

- The web application. The web application is the component that users access through a browser.
- The server (for example, the Unica Campaign listener and the Unica Platform API server). This component is accessed programmatically.

The following examples and diagrams illustrate the roles played by HCL components in various communications.


Example 1 - Communication between a browser and an Unica web application

When users communicate with Unica web applications through a browser, the browser is the client and the Unica web application is the server.




Example 2 - Communication between components of one Unica application

The two components of a single Unica application can also communicate with each other programmatically. For example, when the Unica Campaign web application sends a request to the Unica Campaign listener, the Unica Campaign web application is the client and the listener is the server.



Example 3 - Unica components playing both roles

An Unica application component can communicate as a client in some exchanges and as a server in others. An example of these relationships is shown in the following diagram.



SSL in Unica

Many application components can act as both server and client during normal operations, and some components are written in Java™ and some in C++. These facts determine the format of the certificates you use. You specify the format when you create a self-signed certificate or purchase one from a CA.

applications do not require a truststore when they act as a client making one-way SSL requests to an server component.

Java™ component acting as a server

For applications written in Java™, using the JSSE SSL implementation, and deployed on an application server, you must configure the application server to use your certificate. The certificate must be stored in JKS format.

You cannot use the default certificate provided with the application server.

You can create JKS certificates for your Java applications using Java keytool.

C++ component acting as a server

The Campaign listener, Optimize server component are written in C++, and require a certificate generated by OpenSSL.

Java™ component acting as a client

For applications written in Java™ and deployed on an application server, no truststore is needed. For ease of configuration, Java™ applications acting as a client do not authenticate the server during one-way SSL communications. However, encryption does take place.

C/C++ components acting as a client

For applications written in C/C++ and using the OpenSSL implementation, no truststore is required. The Campaign listener fall into this category.

How many certificates?

Ideally, you should use a different certificate for every machine that hosts an component acting as a server.

If you do not want to use multiple certificates, you can use the same certificate for all the components acting as servers. If you use one certificate for all applications, when users access applications for the first time, the browser asks whether they want to accept the certificate.

Configuration process roadmap: implementing SSL in Unica

Use this configuration process roadmap to scan the tasks required to implement SSL in Unica. The Topic column provides links to the topics that describe the tasks in detail.

Table 50. Configuration process roadmap: implementing SSL in Unica

Topic	Information
Obtain certificates (<i>on page 219</i>)	Obtain or create certificates if you prefer not to use the default certificates provided by HCL and your application server.
Configure your web application servers for SSL (<i>on page 220</i>)	Enable an SSL port in every application server where a HCL application is deployed. If you are not using the application server default certificate, configure it to use your certificate.
Configure HCL Unica for SSL (<i>on page 222</i>)	Set configuration properties in Unica.
Verifying your SSL configuration (<i>on page 235</i>)	Log in to each of your Unica applications.

Certificates for SSL

This procedure describes how to create and configure your own certificates. Perform a similar procedure for every Unica you configure to use SSL. If you are configuring the Unica Campaign + Engage integration, see the Unica Campaign and Engage Integration Guide for IBM Marketing Cloud.

You can obtain or create certificates in several ways. You can create self-signed certificates or you can obtain certificates from a certificate authority (CA).

Self-signed certificates

You can create self-signed certificates.

For C++ components acting as a server, use openSSL to create a `.pem` certificate. The Campaign listener implements SSL using the HCL openSSL library. The openSSL is installed with Campaign and it includes a command-line program called `openSSL` that can create a certificate file.

For Java components acting as a server, use Java keytool to create a JKS certificate.

Certificates from the certificate authority

You can obtain certificates from a certificate authority (CA).

You can use the openSSL to create requests that you can then send to a CA to create signed certificates. Or, you can obtain signed certificates entirely provided by the CA.

Consult your certificate authority documentation for instructions on how to obtain a signed certificate.

Obtain or create certificates

Complete the following procedures to create self-signed certificate files and use with HCL Unica.

1. Create a certificate for a C++ application HCL Unica components.
2. Create a certificate for a C++ application Java Unica components.

Create a certificate for a C++ application HCL Unica components

The Campaign listener implements SSL using the OpenSSL library. The OpenSSL distribution includes a command-line program called `openssl` that can create a certificate file. For details on using this program, see the OpenSSL documentation. You can also access the help by entering `-help`, when you run the program.

Complete the following steps to create a self-signed certificate and configure a C++ HCL Unica component for SSL.

1. Run `openssl` at the command line. This program and its associated configuration file, `openssl.cnf`, are included in the bin directory of the Campaign installation. It is also available with the OpenSSL distribution.
2. Generate a key. Here is a sample command that creates a key named `key.pem`.

```
set OPENSSL_CONF=CAMPAIGN_HOME\bin\openssl.cnf

openssl genrsa -out key -4096
```

3. Generate a request. Here is a sample command that creates a key named `request.pem`.

```
openssl req -config openssl.cnf -new -key key.pem -out request.pem
```

The tool asks you a series of questions. If you enter a period (.) the field is left blank. For a self-signed certificate, you must at least enter the Common Name.

If you are using the `openssl` tool from the `Campaign/bin` directory, add the `-config` parameter with a value that points to the `openssl.cnf` file in the same directory.

For example: `openssl req -config openssl.cnf -x509 -key key.pem -in request.pem -days 1000 -out certificate.pem`

4. Generate a certificate. The following sample command creates a certificate named `certificate.pem` with an expiration of 10,000 days from the day it was created, using the `request.pem` and `key.pem` files.

```
openssl req -x509 -key key.pem -in request.pem -days 10000 -out certificate.pem
```

If you are using the `openssl` tool from the `Campaign/bin` directory, add the `-config` parameter with a value that points to the `openssl.cnf` file in the same directory. For example:

```
openssl req -config openssl.cnf -x509 -key key.pem -in request.pem -days 10000 -out certificate.pem
```

5. Create new certificate file example `campaign.pem`.
6. Copy `key.pem` and `certificate.pem` content into this file separated by new line.

Create a certificate for Java HCL Unica components

HCL Unica web application components written in Java use the JSSE library. The Sun JDK includes a program called `keytool`, which can create a certificate file. For details on using this program, see the Java documentation. You can also access the help by entering `-help` when you run the program.

Complete the following steps to create a self-signed certificate and configure a Java HCL Unica component for SSL.

1. Run `keytool` at the command line. This program is included in the bin directory of the Sun Java JDK.
2. Generate an identity keystore. The following sample command creates a keystore named `UnicaClientIdentity.jks`.

```
keytool -genkey -alias UnicaClientIdentity -keyalg RSA -keystore
UnicaClientIdentity.jks -keypass clientPwd -validity 1000 -dname
"CN=hostName, O=myCompany" -storepass clientPwd
```

Note the following:

- Make a note of the `-storepass` value (`clientPwd` in the example) as you require it when you configure the application server.
 - Make a note of the `-alias` value (`UnicaClientIdentity` in the example) as you require it for the rest of this procedure.
 - The common name (CN) in the distinguished name must be the same as the host name used to access HCL Unica. For example, if the URL for HCL Unica is `https://hostName.companyDomain.com:7002/unica/jsp`, then the CN must be `hostName.companyDomain.com`. The CN portion of the distinguished name is the only required portion; Organization (O) and Organizational Unit (OU) are not required.
 - For WebSphere 6.0, the keystore password and key password must be the same.
3. Generate a certificate based on the identity keystore you created. The following sample command creates a certificate named `UnicaCertificate.cer`. The value of

`-alias` is the alias that you set for the identity keystore (UnicaClientIdentity in the example).

```
keytool -export -keystore UnicaClientIdentity.jks -storepass clientPwd-
alias UnicaClientIdentity -file UnicaCertificate.cer
```

4. Generate a trusted keystore based on the certificate you created. The following sample command creates a trusted keystore named `UnicaTrust.jks`.

```
keytool -import -alias UnicaClientIdentity -file UnicaCertificate.cer-
keystore UnicaTrust.jks -storepass trustPwd
```

Note the following:

- Type `y` when prompted to trust the certificate.
- The value of `-alias` is the alias you set for the identity keystore (UnicaClientIdentity in the example).
- Make a note of the `-storepass` value (trustPwd in the example) as you require it when you configure the application server.

Import Open SSL certificate into java key store

```
keytool -import -alias ListenerKey -file CAMPAIGN_HOME\bin\certificate.pem
-keystore PlatformClientIdentity.jks -storepass password
```

```
keytool -import -file CAMPAIGN_HOME\bin\certificate.pem -alias ListenerKey
-keystore <APP_SERVER_JAVA>\jre\lib\security\cacerts
```

How to obtain signed certificates

You can either use the OpenSSL and keytool programs to create requests to send to a CA to create signed certificates or you can obtain signed certificates entirely provided by the CA.



Note:

- For HCL Unica applications written in C++, obtain a certificate in PEM format.
- For all other HCL Unica applications, obtain a certificate in JKS format.

Consult your certificate authority documentation for instructions on how to obtain a signed certificate.

Creating and configuring certificates for a clustered environment

This procedure describes how to create and configure your own certificates for a clustered environment.

The Campaign web application must be configured for SSL by using default certificates.

The following procedure describes how to create and configure self-signed certificates for Unica Campaign and Unica Platform.

In a clustered environment where there is an IBM HTTP Server in front of the Unica Campaign web application and Campaign listener, follow these steps to configure the Campaign listener in SSL.

You can use these steps as a guide for configuring certificates for other Unica products.

This procedure is applicable for the default certificates that are provided by the IBM WebSphere Application Server. If you are using custom security certificates, you must follow the steps for the custom certificates used by the IBM WebSphere Application Server.

To configure the IBM HTTP Server in SSL, complete the following steps.

1. Use GSKit to generate SSL certificates as follows.

- a. Create and initialize a new key database.

For example:

```
gsk8capicmd_64 -keydb -create -populate -db IHS.kdb -pw password  
-stash
```

The `-stash` option is required for Unica Campaign.

- b. Use GSKit to generate a self-signed certificate for Unica Campaign and store it in the key database, as follows.

For example:

```
gsk8capicmd_64 -cert -create -db IHS.kdb -dn "CN=*.in.ibm.com"
-expire 3650 -pw password -size 1024 -label key -default_cert yes
```

c. Extract the public part of the certificate to a file.

For the clients to trust a certificate, its public part needs to be distributed to the clients and stored in their key databases. In this step, you export the public part of the Unica Campaign certificate. You import it in a later step.

For example:

```
gsk8capicmd_64 -cert -extract -db IHS.kdb -stashed -label key
-target IHS.arm
```

d. Enable the following module in the `httpd.conf` file.

For example:

```
LoadModule ibm_ssl_module modules/mod_ibm_ssl.so

Listen 443
<VirtualHost *:443>
SSLEnable
</VirtualHost>
KeyFile /data/webservers/IBM/IHS/ssl/IHS.kdb
SSLStashFile /data/webservers/IBM/IHS/ssl/IHS.sth
SSLDisable
```

e. Provide the key file path in the `httpd.conf` file.

f. Restart the IBM HTTP server.

2. Generate keystore database files for the server that hosts the Unica Campaign listener.

- a. On the server that hosts the Unica Campaign listener, run the following commands from any location and note the path.

```
gsk8capicmd_64 -keydb -create -populate -db Key.kdb -pw password
-stash
gsk8capicmd_64 -cert -create -db Key.kdb -dn "CN=*.in.ibm.com"
-expire 3650 -pw password -size 1024
-label key -default_cert yes
gsk8capicmd_64 -cert -extract -db Key.kdb -stashed -label key
-target Key.arm
```

- b. Verify that the following files are generated in the location from where you ran the above commands.

- `Key.arm`
- `Key.crl`
- `Key.kdb`
- `Key.rdb`
- `Key.sth`

3. Import the `Key.arm` and `HIS.arm` files into the application server where the Campaign web application is deployed.

- a. Copy the `Key.arm` and `HIS.arm` files to the Campaign web application server.

- b. Add the `Key.arm` and `HIS.arm` files in the **NodeDefaultTrustStore** of the WebSphere Application Server by completing the following steps:

- i. Click **Security > SSL Certificate and key management > Key stores and certificates**.
- ii. Click **NodeDefaultTrustStore > Signer certificates**.
- iii. Click **Add** and provide the **Alias** and the path where the `Key.arm` and `HIS.arm` files are copied.
- iv. Click **OK**.

4. Extract the Personal and Signer certificates for the IBM WebSphere Application Server

- a. Click **Security > SSL Certificate and key management > Key stores and certificates**.
 - b. Click **NodeDefaultTrustStore > Personal Certificates**.
 - c. Select the default certificate.
 - d. Add the Personal Certificate file name along with the valid path in the Unica Campaign web application server. For example, `/opt/HCL/HCLUnica101/ClientPersonal.cer`.
 - e. Click **OK**.
 - f. Click **NodeDefaultTrustStore > Signer Certificates**.
 - g. Select the default certificate.
 - h. Add the Signer Certificate file name along with the valid path in the Unica Campaign web application server. For example, `/opt/HCL/HCLUnica101/ClientSigner.cer`.
 - i. Navigate to the folder and verify the both certificates are present in the folder.
5. Import the Personal and Signer certificates into the Unica Campaign listener and HCL HTTP Server keystore databases.
- a. Copy the `ClientPersonal.cer` and `ClientSigner.cer` certificates to the listener server. You can use the same location where the `key.kdb` file was created.
 - b. Import the Personal and Signer certificates to the listener keystore database by using the `gsk8capicmd_64` command from the location where the listener keystore database (`key.kdb`) was created.

```
gsk8capicmd_64 -cert -add -db Key.kdb -stashed -label  
ClientPersonalKey -file ClientPersonal.cer  
gsk8capicmd_64 -cert -add -db Key.kdb -stashed -label  
ClientSignerKey -file ClientSigner.cer
```

- c. Copy the `ClientPersonal.cer` and `ClientSigner.cer` certificates to the HCL HTTP Server. You can use the same location where the `IHS.kdb` file was created.
 - d. Import the Personal and Signer certificates to the listener keystore database by using the `gsk8capicmd_64` command from the location where the HCL HTTP Server keystore database (`IHS.kdb`) was created.
6. Import the Campaign listener key in the HCL HTTP Server keystore database and import the HCL HTTP Server key in the Campaign keystore database.
- a. Copy the HCL HTTP Server key (`IHS.arm`) to the listener server.
 - b. Import the HCL HTTP Server key to the listener keystore database by using the `gsk8capicmd_64` command from the location where the Campaign listener keystore database (`key.kdb`) was created.

```
gsk8capicmd_64 -cert -add -db Key.kdb -stashed -label IHSKey  
-file IHS.arm
```

- c. Copy the Campaign listener key (`Key.arm`) to the listener server.
- d. Import the Campaign listener key to the HCL HTTP Server keystore database by using the `gsk8capicmd_64` command from the location where the HCL HTTP Server keystore database (`IHS.kdb`) was created.

```
gsk8capicmd_64 -cert -add -db IHS.kdb -stashed -label IHSKey  
-file Key.arm
```

7. Restart the HCL Campaign application server, the HCL HTTP server and then start the Unica Campaign Listener.

Configure your web application servers for SSL

On every application server on which an Unica application is deployed, configure the web application server to use the certificates you have decided to employ.

See your web application server documentation for details on performing these procedures.

Ensuring cookie security

Some cookies may not be properly secured in the client browser. Not securing cookies leaves the application vulnerable to man-in-the-middle and session hijacking attacks. To fix this issue, take the following precautions.

- Enforce the use of SSL at all times to reduce the risk of cookies being intercepted on the wire.
- In the web application server, set the `secure` and `httponly` flags on all cookies.
 - The `secure` flag tells the browser to send the cookie only over an HTTPS connection. You must enable SSL on all applications that communicate with each other if you set this flag.
 - The `httponly` flag prevents cookies from being accessed through a client side script.

Setting the flags for SSL in WebSphere®

To set the `secure` and `httponly` flags in WebSphere®, use the following procedure.

You set the `secure` and `httponly` flags in the WebSphere® administrative console.

 **Tip:** See the WebSphere® documentation for complete details.

1. At the application level for Unica Platform, navigate to **Session Management** and click **Enable cookies**.
2. Check **Restrict cookies to HTTPS sessions** and **Set session cookies to HTTPOnly to help prevent cross-site scripting attacks**.
3. Save and apply your changes.
4. Stop and re-start the Unica Platform application.

Setting the flags for SSL in WebLogic

To set the `secure` and `httponly` flags, use the following procedure.

 **Tip:** See the WebLogic documentation for complete details.

1. If Unica Platform is deployed and running, stop and undeploy it.
2. Extract the Unica Platform WAR file.
3. Edit the `weblogic.xml` file to set the `secure` and `httponly` flags.
4. Recreate the Unica Platform WAR file, redeploy, and re-start.

Configure HCL Unica for SSL

To configure Unica applications to use SSL, you must set some configuration properties. Use the procedures in this section that are appropriate for your installation of Unica products and the communications that you want to secure using SSL.

When you access your Unica installation over a secure connection, and when you set navigation properties for applications as described in the following procedures, you must use `https` and the secure port number in the URL. The default SSL port is `7002` for WebLogic and `8002` for WebSphere®.

Configuring SSL in Unica Platform

Follow this procedure to configure SSL in Unica Platform.

1. Log in to Unica and click **Settings > Configuration**.
2. Set the value of the `General | Navigation | Unica Platform URL` property to Unica Platform URL.

For example: `https://host.domain:SSL_port/unica`

where:

- `host` is the name or IP address of the machine on which Unica Platform is installed
- `domain` is your company domain in which your Unica products are installed
- `SSL_Port` is the SSL port in the application server on which Unica Platform is deployed

Note `https` in the URL.

3. Locate the properties under the `Navigation` category for each of your installed Unica products where you set the HTTP and HTTPS ports. The names of the properties might vary by product, but their purpose should be obvious. For each product, set these values to the HTTP and HTTPS port in the application server on which the product is deployed.
4. If you have implemented LDAP integration, perform the procedure described in "Configuring SSL in Unica Platform with LDAP integration."
5. If you plan to use the data filtering feature, perform the procedure described in "Configuring SSL in Unica Platform with data filters."

Configuring SSL in Platform for a clustered environment

Follow this procedure to configure SSL in Platform in a clustered environment.

1. Log in to HCL Unica and click **Settings > Configuration**.
2. Under `Affinium | Manager | Navigation`, set **Unica Platform URL** to the Unica Platform URL.

For example: `https://<IHS_Host>/unica`.
3. Under `Affinium | Campaign | Navigation`, set **serverURL** to the Unica Campaign URL.

For example: `https://<IHS_Host>/Campaign`.
4. Under `Affinium | Campaign | server`, set **fullContextPath** to the Unica Campaign URL.

For example: `https://<IHS_Host>/Campaign`.
5. Under `Affinium | Campaign | unicaACLlistener`, set **serverhost** to the `<IHS Host>` and set **useSSL** to `True`.

Configuring SSL in Unica Platform with LDAP integration

Follow this procedure to configure SSL in Unica Platform.

1. Perform the procedure described in "Configuring SSL in Unica Platform" if you have not done so already.
2. Log in to Unica and click **Settings > Configuration**.

The Configuration page appears.

3. Navigate to the Unica | Unica Platform | Security | Login Method details | LDAP category and set the value of the Require SSL for LDAP connection property to `true`.

This setting requires Unica Platform to connect to the LDAP server using SSL when users log in.

4. Navigate to the Unica | Unica Platform | Security | LDAP synchronization category and set the following values.

- Set the value of the LDAP provider URL property to:

```
ldaps://host.domain:SSL_Port
```

where:

- *host* is the name or IP address of the LDAP server
- *domain* is the domain of the LDAP server
- *SSL_Port* is the SSL port of the LDAP server.

For example: `ldaps://LDAPMachine.myCompany.com:636`

Note the `ldaps` in the URL.

The default SSL port for LDAP servers is `636`.

- Set the value of the Require SSL for LDAP connection property to `true`.

This setting requires Unica Platform to connect to the LDAP server using SSL when it synchronizes with the LDAP server.

Configuring SSL in Unica Platform with data filters

When Unica Platform is deployed with SSL and you plan to use the data filtering feature, you must perform this procedure to add the SSL options that perform hand shaking.

1. Perform the procedure described in "Configuring SSL in Unica Platform" if you have not done so already.
2. Obtain the following.
 - A copy of the certificate file you created in Obtaining or creating certificates (*on page*)
 - The certificate password
3. Place the certificate file in the `JAVA_HOME/jre/lib/security` directory, where `JAVA_HOME` is the Java™ directory specified in the `tools/bin/setenv` script under your Unica Platform installation.

The `setenv` script specifies the Java™ instance used by Unica Platform utilities.

4. Use the `keytool` program to import the certificate into the `cacerts` file for your Java™ instance.

You can use the following example command as a guide.

```
keytool -import -trustcacerts -file name_of_your_certificate.cer
-keystore cacerts
```

Enter the certificate password when prompted.

Configuring SSL in Unica Plan

Follow this procedure to configure SSL in Unica Plan.

1. Log in to Unica and click **Settings > Configuration** .
2. Set the value of the `Marketing Operations | navigation | serverURL` property to the URL of the Unica Plan web application.

For example: `serverURL=https://host:SSL_port/plan`

where:

- `host` is the name or IP address of the machine on which Unica Plan is installed.
- `SSL_Port` is the SSL port of the Unica Plan web application

Note the `https` in the URL.

3. Open the `plan_config.xml` file in a text or XML editor.

The `plan_config.xml` file is located in the `conf` directory under your Unica Plan installation.

4. Set the `UAPInitParam notifyPlanBaseURL` property for your SSL connection.

For example: `<UAPInitParam notifyPlanBaseURL="https://host:SSL_Port/plan/affiniumplan.jsp"/>`

where:

- `host` is the name or IP address of the machine on which Unica Plan is installed.
- `SSL_Port` is the SSL port of the Unica Plan web application

Note the `https` in the URL.

5. To enable Adobe™ Acrobat Online Markup functionality to work with Unica Plan over HTTPS, set the `markupServerURL` property for your SSL connection.

For example: `<UAPInitParam markupServerURL="https://host:SSLport/plan/services/collabService?WSDL">`

where:

- `host` is the name or IP address of the machine on which Unica Plan is installed
- `SSL_Port` is the SSL port of the Unica Plan web application

Note the `https` in the URL.

6. Save and close the `plan_config.xml` file.

Configuring SSL in Unica Campaign

Follow this procedure to configure SSL in Unica Campaign.



Note: If you are configuring SSL in Unica Campaign, you must also configure the Campaign Listener in SSL. If you do not set the Campaign Listener in SSL the schedule flowchart status might be shown as `Unknown`.

1. Open the `config.xml` file in a text or XML editor.

The `config.xml` file is in the `conf` directory under your Unica Campaign installation.

2. Set the following values in the `config.xml` file.

- `unicaServerSSLFile = PATH_TO_OPENSSL_PEM/campaign.pem`

3. Save and close the `config.xml` file.

4. Log in to Unica Platform and click **Settings > Configuration**.

The Configuration page appears.

5. Set the value of the `Campaign | unicaACLlistener | useSSL` property to `yes`.

6. If you deployed the web application on an SSL port, set the value of the `Campaign | navigation | serverURL` property to the web application URL. For example:

```
serverURL=https://host:SSL_port/Campaign
```

where:

- `host` is the name or IP address of the machine on which the web application is installed
- `SSL_Port` is the SSL port of the web application

Note the `https` in the URL.

7. If you are using the operational monitor, configure it for SSL by setting the value of the `Campaign | monitoring | serverURL` property to use HTTPS. For example:

```
serverURL=https://host:SSL_port/Campaign/OperationMonitor
```

where:

- `host` is the name or IP address of the machine on which the web application is installed
- `SSL_Port` is the SSL port of the web application

Note the `https` in the URL.

Configuring cipher list in Unica Campaign

Prerequisite: Unica Campaign must be configured with SSL.

If Unica Campaign application and Listener are configured with SSL options as `TRUE`, then by default 98 ciphers are supported to enable the SSL communication between Unica Campaign application(Server) and listener.

To disallow weak ciphers from this default cipher list, users can use `<SSLCipherList>` tag or property in config.xml file.

To remove support of weak ciphers, users must add the following line in config.xml file.

It specifies that support to default ciphers excludes `AES256-SHA`, `CAMELLIA256-SHA`, `AES128-SHA`, `SEED-SHA`, `CAMELLIA128-SHA`, `DES-CBC3-SHA`, `IDEA-CBC-SHA`.

```
<property name="SSLCipherList"><value>DEFAULT:!AES256-SHA:!CAMELLIA256-SHA:!
AES128-SHA:!SEED-SHA:!CAMELLIA128-SHA:!DES-CBC3-SHA:!IDEA-CBC-SHA</value></
property>
```

This disables the above-mentioned ciphers, which are included in `<SSLCipherList>` tag of config.xml file.

If clients or users do not mention the SSLCipherList tag in config.xml file, then the default cipher list is considered and 98 ciphers are supported.



Note: The listener will not start and the following errors are generated in unica_aclsnr.log file, if users or clients disable any cipher which is required by certificate or browser.

```
Error enabling SSL connection.
```

```
SOCKET BIND port=4664: ERRNO 10048: Unknown error
```

Configuring SSL in Unica Campaign for a clustered environment

Follow this procedure to configure SSL in Unica Campaign listener server in a clustered environment.

1. Open the `config.xml` file for the listener server in a text or XML editor.

The `config.xml` file is in the `conf` directory under your Unica Campaign installation.

2. Set the following values in the `config.xml` file.

- Set **configurationServerBaseURL** to the Campaign SSL URL. This is the HCL HTTP Server URL.
- Set **unicaServerSSLFile** to the path where the Password file is saved.
- Set **unicaServerSSLFilePwd** to the path where the Password file is saved.

For example:

```
<configuration name="bootstrap">
  <category name="bootstrap">
    <property name="suiteName"><value>Affinium</value></property>
    <property name="clientType"><value>HTTP</value></property>
    <!-- configurationServerBaseURL value will be set by
AffiniumSuite assembly installer -->
    <property
name="configurationServerBaseURL"><value>https://<IHS_Host>/Campaign<
/value></property>
    <property
name="trustedApplication"><value>>false</value></property>
    <property name="unicaClientKeystore"><value></value></property>
    <property
name="unicaClientKeystorePwd"><value></value></property>
    <property
name="unicaServerSSLFile"><value>/PATH_TO_OPENSSL_PEM/campaign.pem</v
alue></property>
    <property name="unicaServerSSLFilePwd"><value></value></property>
  </category>
</configuration>
```

3. Save and close the `config.xml` file.

Configuring Campaign in SSL and Campaign Listener in non-SSL

If your setup has Campaign in SSL and the Campaign Listener in the non-SSL mode, you must configure settings for the applications to work seamlessly.

The Campaign web application must be configured in SSL by using the default certificates.

All configurations are applicable to the WebSphere Application Server for Campaign. Multiple steps are involved to configure the SSL and non-SSL setup. Each step might have more substeps to be completed.

To configure Campaign in SSL and Campaign Listener in non-SSL, complete the following steps:

Complete the following steps.

Table 51. Configuring Campaign in SSL and Campaign Listener in non-SSL

#	Step	Substeps
1	Generate and use <code>.pem</code> (certificate) file.	<p>Run the following commands from and location and note the paths. Create new certificate file example campaign.pem (copy key.pem and certificate.pem content into this file separated by new line)</p> <pre data-bbox="548 926 1393 1255">set OPENSSL_CONF=CAMPAIGN_HOME\bin\openssl.cnf openssl genrsa -out key.pem 4096 openssl req -config openssl.cnf -new -key key.pem -out request.pem openssl req -config openssl.cnf -x509 -key key.pem -in request.pem -days 1000 -out certificate.pem</pre> <p>The following files are generated at the location from where you ran the commands.</p> <ul data-bbox="594 1430 818 1619" style="list-style-type: none"> • key.pem • request.pem • certificate.pem • campaign.pem

#	Step	Substeps
2	Import the <code>cam-campaign.pem</code> file into the application server where the Campaign web application is deployed.	<p>a. Copy the <code>campaign.pem</code> file to the Campaign web application server.</p> <p>b. Add the <code>campaign.pem</code> file in the NodeDefaultTrustStore of the WebSphere Application Server by completing the following steps:</p> <ol style="list-style-type: none"> i. Click Security > SSL Certificate and key management > Key stores and certificates. ii. Click NodeDefaultTrustStore > Signer certificates. iii. Click Add and provide the Alias and the path where the <code>campaign.pem</code> file is copied. iv. Click OK. <p>The listener key is added to the application server.</p>
3	Modify <code>config.xml</code> file on the listener server.	<p>Provide the following information:</p> <ul style="list-style-type: none"> • configurationServerBaseURL: Provide the Campaign SSL URL. • unicaServerSSLFile: Provide the <code>PATH_TO_OPENSSL_PEM/campaign.pem</code> file path. • unicaServerSSLFilePwd: Provide the corresponding <code>password</code> file path. <pre data-bbox="548 1402 1395 1877"> <configuration name="bootstrap"> <category name="bootstrap"> <property name="suiteName"><value>Affinium</value></property> > <property name="clientType"><value>HTTP</value></property> <!-- configurationServerBaseURL value will be set by AffiniumSuite assembly installer --> </pre>

#	Step	Substeps
		<pre> <property name="configurationServerBaseURL"> <value>https://eagle191.hcl.com:9447/Campaign</val ue> </property> <property name="trustedApplication"><value>>false</value></pr operty> <property name="unicaClientKeystore"><value></value></proper ty> <property name="unicaClientKeystorePwd"><value></value></pro perty> <property name="unicaServerSSLFile"> <value>PATH_TO_OPENSSL_PEM/campaign.pem</value> </property> <property name="unicaServerSSLFilePwd"> <value> password </value> </property> </category> </configuration> </pre>
4	In the unica-ACLlistener settings set useSSL to TRUE .	-

#	Step	Substeps
5	Restart the Campaign Application Server and the Campaign Listener.	-

Configuring SSL in Unica Optimize

Follow this procedure to configure SSL in Unica Optimize.

1. Open the `config.xml` file found in the `conf` directory of your Unica Optimize installation directory in a text or XML editor.
2. Set the value of `unicaServerSSLFile` to the full path of the certificate you are using.
3. Save and close the `config.xml` file.
4. Set the value of the `Campaign | unicaACOListener | useSSL` configuration property to `yes`.
5. If you are using the Unica Optimize command-line tool `ACOOptAdmin`, perform the following steps.
 - a. Obtain the following.
 - A copy of the certificate file you created in Obtaining or creating certificates (on page)
 - The certificate password
 - b. Place the certificate file in the `JAVA_HOME/jre/lib/security` directory, where `JAVA_HOME` is the Java™ directory specified in the `ACOOptAdmin` script.
 - c. Use the `keytool` program to import the certificate into the `cacerts` file for your Java™ instance.

You can use the following example command as a guide.

```
keytool -import -trustcacerts -file name_of_your_certificate.cer
-keystore cacerts
```

Enter the certificate password when prompted.

Configuring SSL in Unica Interact

You can configure SSL communication for Unica Interact in three areas, although there is a significant performance cost if you do this.

The areas in that can use SSL are as follows.

- Design environment as the client and Runtime environment as the server.

Use https in the URL referencing the Unica Interact runtime server. For example, `set Campaign | partitions | partition[n] | Interact | ServerGroups | [serverGroup] | instanceURLs | [instanceURL] | instanceURL to https://myserver.domain.com:7007/interact.`

- Runtime environment as the client and Unica Platform as the server.
- Your touchpoint as the client and the Runtime environment as the server.

Specify the HTTPS URL with the `getInstance` method. If using a load balancer, you might need to configure your load balancer for SSL as well.

- If the Unica Interact design server and Runtime server are on separate hosts using SSL, import the security certificates on the two servers to enable the SSL handshake to take place.



Important: There is a performance cost if you configure any part of Unica Interact to communicate using SSL. It is not recommended to configure Unica Interact to use SSL.

Configuring SSL in Unica Collaborate

After Unica Campaign is configured to use SSL, no additional configuration is required to configure Unica Collaborate for SSL.

Configuring SSL in Reports

Follow this procedure to configure SSL in Reports.

1. Configure Cognos® with SSL as described in the Cognos® documentation.
2. Configure Apache with SSL as described in the Apache documentation.
3. Register the Cognos® certificate with Unica as described in the Cognos® documentation.
4. Register the Unica certificates with Cognos® as described in the Cognos® documentation.

Configuring SSL in Digital Analytics for On Premises

Digital Analytics for On Premises does not accept any requests: it always acts as the client in HTTP and HTTPS communications to resolve page titles on the web site being analyzed. If you need to resolve page titles for a site that uses SSL, you only need to ensure that the URL entered in the profile options for the website or clustered servers being analyzed is correct and that the URL includes the HTTPS protocol.

SDigital Analytics for On Premises does not communicate with Unica Platform.

Verifying your SSL configuration

Follow this procedure to verify your SSL configuration.

1. Start each of your Unica applications.
2. Log in to Unica and access each of your installed Unica web applications.
3. For Unica Interact runtime servers only, test the connection using the URL
`https://host:port/interact/jsp/admin.jsp`.
4. If you are using a self-signed certificate, point your browser to each of the Unica server components and verify that the certificate information you receive is as expected.

For example, if the Unica Campaign listener is running on port 4664 on a host named `campaignHost`, point your browser to `https://campaignHost:4664`

Your browser opens a window asking if you want to accept the certificate, and you can view certificate details.

Useful links for SSL

These links provide more information on the tasks required to implement SSL in Unica.

- OpenSSL Documentation - <https://www.openssl.org/>
- Java keytool documentation - <http://docs.oracle.com/javase/7/docs/technotes/tools/solaris/keytool.html>
- List of certificate authorities - https://curlie.org/Computers/Security/Public_Key_Infrastructure/PKIX/Tools_and_Services/Third_Party_Certificate_Authorities/

Quality of protection (QoP) settings for WebLogic

You must set the QoP settings when you configure HCL Unica applications to use SSL.

The following QoP settings are supported for WebLogic:

- TLS11
- TLS12

To change the QoP settings, complete the following steps:

Append the following option to the `JAVA_OPTIONS` variable:

- For TLS11- `-Dweblogic.security.SSL.protocolVersion=TLSv1.1`
- For TLS12- `-Dweblogic.security.SSL.protocolVersion=TLSv1.2`

Quality of protection (QoP) settings for WebSphere

You must set the QoP settings when you configure HCL Unica applications to use SSL.

The following QoP settings are supported for WebSphere:

- SSL_TLS
- SSL
- TLS
- TLSv1
- SSL_TLSv2
- TLSv1.1
- TLSv1.2

To change the QoP settings, complete the following steps:

1. Go to **Security > SSL Certificate and key management > SSL configurations**
2. Select the required SSL configuration.
3. Under **Additional Properties**, click **Quality of protection (QoP) settings**.
4. In the **Quality of protection (QoP) settings** pane, select the required QoP settings from the drop-down list for **Protocol**.
5. Click **Save**.
6. In the `ssl.client.props` file located in the `WAS_install\profiles` `\AppSrv01\properties` folder, update the following:

```
com.ibm.ssl.protocol=<Specify required QoP settings>
```

7. Restart the application server.

Security framework for Unica APIs

Unica Platform provides the security framework for the APIs implemented by Unica products.

A set of configuration properties on the **Settings > Configuration** page enables developers to set the following security for the APIs provided by Unica products.

- For a specific product API, you can block access to the product.
- For a specific product API, you can require HTTPS for communication between the specified API and the product.
- For a specific product API, you can require authentication for communication between the specified API and the product.

The configuration properties that control API security are located under the **Unica Platform | Security | API management** category. Each product has a configuration property template that you can use to create new security settings for the APIs provided by that product.

You can set and change the security settings for an API as appropriate for unit testing or deployment or during the overall lifecycle of APIs.

The security framework currently supports APIs for Unica Campaign only.

The Unica Platform security framework supports the following two authentication options for accessing protected APIs. You can use either one, depending on your environment.

- Internal users who are registered with Unica Platform can be authenticated using their Unica Platform login credentials to obtain a secure token.
- External users who are part of a federation that Unica Platform is set up to use can be authenticated through the Identity Provider server.

Internal user authentication with the Unica Platform login API

To authenticate internal users in client applications, use the Unica Platform `login` API to generate secure tokens. You can then invoke any protected APIs by passing the required parameters in the request header, in addition to the parameters expected by the API itself.

The security filter intercepts these protected requests, validates them, and then passes them through for processing.

After the Unica Platform user is authenticated, the Unica Platform security filter adds the user's login name to the request as an attribute of the `USER_NAME_STRING` key before passing it to the product for processing.

The secure tokens have a default life span of 15 seconds. After the life span of the token expires, it cannot be used to invoke a protected API. Each time the Unica Platform `login` API is invoked for a user, all previous security tokens for that user are invalidated.

You can change the life span of secure tokens by setting the value of the **Token lifetime** property located on the **Settings > Configuration** page under the **General | Miscellaneous** category.

Example URL

```
http[s]://host:port/unica/api/manager/authentication/login/
```

Header parameters

Table 52. Header parameters for the login API with internal users

Parameter	Description
<code>m_user_name</code>	The internal user's Unica Platform login name.
<code>m_user_password</code>	The internal user's Unica Platform password in plain text.

Response

When login succeeds, the response is HTTP 200 with the following JSON data.

- `m_tokenId` - randomly generated token
- `m_user_name` - user name of the logged in user
- `createDate` - timestamp in the format that is shown in the following example, where the time zone is IST:

```
Mon Jul 06 18:23:35 IST 2015
```

When login fails with bad credentials, the response is HTTP 401 (unauthorized). When the `login` API is configured to be blocked, the response is 403 (forbidden). When the `login` API is configured to use HTTPS and if it is invoked on HTTP, the response is 403 (forbidden).

To log out internal users, use the Unica Platform `logout` API.

Internal user logout with the Unica Platform logout API

Use the Unica Platform `logout` API to log out internal users and delete the secure token.

The `logout` API is protected by default. The authentication parameters are expected in the request header against pre-defined keys.

Example URL

```
http[s]://host:port/unica/api/manager/authentication/logout/
```

Header parameters

Table 53. Header parameters for the logout API

Parameter	Description
<code>m_user_name</code>	The internal user's Unica Platform login name.
<code>m_tokenId</code>	The secure token obtained through authentication.
<code>api_auth_mode</code>	Use the value <code>manager</code> for internal users.

Response

When authentication succeeds, the response is `HTTP 200`, and the secure token is deleted. If the response is `HTTP 200`, the client application should confirm the logout.

When authentication fails, the response is `HTTP 401`.

External user authentication and logout through a federation

When Unica Platform is integrated with a supported federation, users can log in to their own system, and the client application gets a token through the Identity Provider (IdP) server provided by Unica Platform.

After a federated user is authenticated, their corresponding Unica Platform login name is added to the request as an attribute of the `USER_NAME_STRING` key.

Log out should be done at the IdP server.

Header parameters

The following table describes the header parameters to use when authenticating through the IdP server provided by Unica Platform.

Table 54. Header parameters with a federation

Parameter	Description
f_userId	User ID in the federation.
f_clientId	Client ID in the federation.
f_spld	Service provider ID in the federation.
f_tokenId	Single sign-on token from the IdP server.
api_auth_mode	Use the value <code>f_sso</code> for federated authentication.

Response

The response is `HTTP 200`, with additional items depending on the API.

Data filter creation and management

Data filters make it possible to restrict the customer data that an Unica user can view and work with in Unica applications. You can think of the data you secure with a data filter as a data set defined by the fields in your customer tables that you specify.

The various Unica applications use data filters in different ways. See the documentation for the individual products to determine whether the product uses data filtering, and if so, the details of how data filtering works within that product.

Overview of data filter creation

Unica Platform provides the following features that Unica administrators use to set up data filters.

- A utility for defining data filters.
- A user interface for assigning users and groups to data filters and for viewing assigned data filters.

Data filter associations to restrict user access

To restrict data access for individual users or groups of users, you assign them to data filters. All Unica users and groups are available for assignment to data filters.

You can assign multiple users and groups to a single data filter, and you can also assign a user or a group of users to multiple data filters.



Note: Groups do not acquire the data filter assignments of their subgroups.

A user who is assigned to multiple data filters sees all of the records allowed by all of the data filters.

Two ways to create data filters: automatic generation and manual specification

Unica Platform provides a utility, `datafilteringScriptTool`, that processes XML to create the data filters in the Unica Platform system tables. Depending on how you write the XML, you can use this utility in two ways: automatic generation and manual specification.

Automatic generation

The `datafilteringScriptTool` utility can automatically generate data filters from a database table or view accessible using JDBC. The utility automatically creates data filters based on unique combinations of values in fields that you specify in the XML (one data filter for each unique combination).

You might want to use this method if you must create many data filters based on unique combinations of values in different fields.

Manual specification

The `datafilteringScriptTool` utility can create data filters one by one, based on field values that you specify.

You might want to use this method if you want to create a set of data filters that does not include every unique combination of field values.

Two ways to assign users and groups: in the user interface and in the XML

You have two options for assigning users and groups to data filters: through the user interface or in the XML you use to create the data filters. Assigning users in the XML is a useful method when you have many users, each of whom requires a separate filter.

Assigning users in the XML is available only when you create data filters using **manual specification**. When you assign users in the XML, you need the data filter IDs to specify the assignment, and these IDs are available only when you specify data filters using manual specification, not with automatic specification.

Details about using both methods for assigning users and groups are provided in this chapter.

Data filter concepts

To understand how to set up data filters, you need to be familiar with some concepts used in the data filter feature, in databases in general, and in Unica Campaign in particular (if you are setting up data filters that will be used in an application in the Unica Campaign family).

- **data configuration** - A data configuration groups a set of data filters. All data filters that secure related data are associated with the same data configuration.
- **audience** - The field or fields in customer tables designated in Unica Campaign as an audience level. Typical audience levels are household and individual.
- **physical field name** - The physical names of fields in a database table are the names you see when you view the tables directly in the database client. When the data filter is in use, it uses the physical name when querying the customer database.
- **logical field name** - When you define data filters, you assign logical names to physical fields. If you are setting up data filters that will be used in an application in the Unica Campaign family, these logical names must be the same as names assigned to fields in Unica Campaign. This name is used by the utility when it generates data filters.

Configuration process roadmap: creating data filters

Use this configuration process roadmap to scan the tasks required to configure data filters.

The Topic column provides links to the topics that describe the tasks in detail.

Table 55. Data filter configuration process roadmap

Topic	Information
<ul style="list-style-type: none"> • Planning your data filter criteria: automatic generation (on page 245) • Planning your data filter criteria: manual generation (on page 246) 	Decide what customer data you want to secure.
Obtaining the JDBC driver for your database: automatic generation only (on page 247)	For automatic generation only: obtain the Type 4 JDBC driver that provides connectivity to the database containing the table on which you want to base your data filters.
Obtaining required information (on page 247)	Gather the required database information, and, if you plan to use the data filters with an application in the Unica Campaign family, the Unica Campaign-related information.
Creating the XML to specify data filters (on page 248)	Create the XML file that specifies the customer data used as criteria in each data filter.
Setting required data filter configuration properties (on page 249)	Set configuration properties that enable data filtering.
Populating the data filter system tables (on page 250)	Run the <code>datafilteringScriptTool</code> utility, which uses your XML to populate the Unica Platform system tables that are used for data filters.
Assigning users and groups to data filters (on page 250)	If you do not assign users and groups to data filters within the XML, use the Unica data filter user interface to perform

Table 55. Data filter configuration process roadmap (continued)

Topic	Information
	searches for users, groups, and data filters and then select items from the search results and assign them.

Planning your data filter criteria: automatic generation

Data filter criteria are based on your customer data. Before you can define data filters, you need to decide what customer data you want to secure.

For example, you might want to restrict access to customer data based on the countries, cities, and states where your customers live. If your customer database has a table that contains country, city, and state fields, you might choose to base a group of data filters on these fields. You would then use these values when you specify your data filters.

You should be aware of the following concepts when you plan how to create data filters using automatic generation.

- **profile field** - A field whose value is considered when the data filter generation utility looks for unique combinations of values. The utility creates a data filter for each unique combination of values. When the data filter is in effect in an Unica application, this value is used in a WHERE clause when customer records are queried. Because the clause tests for equality, profile fields must be defined against fields that support a finite set of distinct values.
- **fixed field** - An optional field that limits the records that the data filter generation utility looks at when querying for unique combinations of profile field values. The value you specify is also included in every generated data filter. When the data filter is in effect in an Unica application, this value is used in a WHERE clause when customer records are queried. Because the clause tests for equality, fixed fields must be defined against fields that support a finite set of distinct values.

In the example above, you would probably create a fixed field for a country, and profile fields for city and state. The data filter generation utility creates a data filter for each unique combination of values it finds in these fields.

A Unica user assigned to one or more data filters would be able to view and work with only the data belonging to the customers who live in the countries, cities, and states represented by the assigned data filter(s).

It is possible that your customer tables do not contain every value for which you want to create a data filter. For example, you might not have customers in every country and state, but might want to prepare data filters for every country and state for future use. In that case, you can reference a table that includes every country and state and use it in the `GenerateDataFilters` section of your XML specification. When you have finished using the utility to create your data filters, you can discard this 'dummy' table.

Planning your data filter criteria: manual generation

Data filter criteria are based on your customer data. Before you can define data filters, you need to decide what customer data you want to secure.

For example, you might want to restrict access to customer data based on the geographical sales territory to which the Unica user is assigned. If the `Region` field in your customer database relates to your sales territories, you might choose to base a group of data filters on this field.

You should be aware of the concept of **field constraints**, which you need to understand when you plan how to create data filters using manual specification. A field constraint is a field/value pair used to specify a data filter. This value is used in a `WHERE` clause when customer records are queried. Because the clause tests for equality, field constraints must be defined against fields that support a finite set of distinct values.

In the example, the `Region` field might contain the following values: Asia, Europe, Middle East, North America, and South America. You use these values when you specify field constraints for your data filters. You would set up a different data filter for each of your sales territories, using the values in the `Region` field in your customer tables as field constraints.

A Unica user assigned to one or more data filters would be able to view and work with only the data belonging to the customers who fall within the sales territory or territories represented by the assigned data filter(s).

The data filters you create using the manual method can be assigned to users through the user interface or by making the assignments in the XML.

Obtaining the JDBC driver for your database: automatic generation only

A JDBC driver is required by the data filter generation utility (`datafilteringScriptTool`) when you use it to generate data filters automatically.

1. Obtain the Type 4 JDBC driver that provides connectivity to the database containing the table on which you want to base your data filters.
2. Place the driver on the machine where Unica Platform is installed.
3. Make a note of the class name and path.

Obtaining required information

To create data filters, you need to gather information about your data and the way it is mapped in your Unica products.

For **manual specification** only: Obtain the following information.

- The physical name of the table containing the fields you want to use.
- The finite set of data in the fields you want to use for field constraints.
- If you plan to use the data filters in an application that is a member of the Unica Campaign family, obtain the names assigned in Unica Campaign to the following fields.
 - The audience fields
 - The fields you plan to use for field constraints.

For **automatic generation** only: Obtain the following information.

- For the database that contains the table you want to use in defining your data filters, the database type, the name or IP address, and the port.
- Database credentials (user name and password) that allow you to connect to the database.

- The physical name of the table containing the fields you want to use.
- The physical names of the fields you want to use for profile fields and fixed fields (fixed fields are optional).
- If you plan to use the data filters in an application that is a member of the Unica Campaign family, obtain the names assigned in Unica Campaign to the following fields.
 - The audience fields.
 - The fields you plan to use for fixed and profile fields.



Note: If you are defining data filters that will be used in an application that is a member of the Unica Campaign family of products, the logical names of fields you specify in the XML that defines the data filters must match the names given to these fields in Unica Campaign.

Creating the XML to specify data filters

Create the XML file that specifies the customer data used as criteria in each data filter. In the next step you will run a utility that populates the system tables with these specifications.

To create the data filters, the `datafilteringScriptTool` utility uses an XML representation of the data to insert entries into the Unica Platform system table database.

Here is an overview of the elements in the XML that you create.

- `<Execute Batch>` - Command that initiates the data insertion process. This is repeated several times within the XML.
- `<AddDataConfiguration>` - Defines the data configurations, which are groups of related data filters.
- `<AddLogicalFields>` - Defines the fields on which to filter, and the data type of the fields.
- `<AddDataFilter>` - When you use **manual specification**, references a defined logical field, and specifies the field constraints.

- `<GenerateDataFilters>` - When you use **automatic specification**, references the fields and the values that limit the records considered for unique combinations of values used to define a set of data filters.
- `<AddDataTable>` - Defines the relationship between logical fields and their physical tables and columns. One logical field can apply to different physical tables, which allows one filter to apply to several tables.
- `<addAudiences>` - References a defined logical field, and specifies the audience level as defined in Unica Campaign.
- `<addAudienceTableAssociations>` - Defines the relationship between an audience level and the defined table and the defined data filter configuration.
- `<AddAssignments>` - When you **create assignments within the XML rather than using the user interface**, associates individual users or groups of users with defined data filters.

For additional information, including descriptions of additional elements that are nested within the elements described above, see these topics in this chapter:

- The detailed descriptions of each element in the XML
- The XML provided in the example scenarios

Setting required data filter configuration properties

Set required configuration properties to enable data filtering.

On the **Settings & Configuration** page, navigate to the **General | Data filtering** category and set the following properties.

- Default table name
- Default audience name

See each property's context help or the related topic link in this section for instructions on setting the values.

Optional configuration property to improve data filter performance

You can turn the data filter cache on for better performance.

To improve performance, set the value of the **General | Data filtering | Enable data filter cache** property to **true**. This property specifies whether Unica Platform retrieves data filter definitions from the database or from a cache. When this value is **true**, data filter definitions are stored in the cache and the cache is updated whenever there is any change in the data filter definitions.

You must restart the Unica Platform web application after you make a change in this property value before it can take effect.

Populating the data filter system tables

Run the `datafilteringScriptTool` utility, which uses your XML to populate the data filter system tables.

For details on using the `datafilteringScriptTool` utility, see the full description elsewhere in this guide.



Note: If you need to delete data filters, run the `ManagerSchema_PurgeDataFiltering.sql` script, described elsewhere in this guide.

Assigning users and groups to data filters

If you do not assign users or groups within the XML that you create, use the Unica data filter user interface to perform searches for users, groups, and data filters and then select items from the search results and assign them.

Data filter XML reference

This section describes the XML elements for which you must provide values.

About the IDs in the XML

Some objects require IDs. For example, data configurations, logical fields, and data tables all require that you specify IDs. The IDs you specify must be unique within a category of object.

Some objects reference other objects using IDs. For example, tables reference logical fields. When you need to reference another object, use the ID you specified for the object.

The XML uses the following convention for ID element names. This convention helps you understand when you must create a unique ID and when you must reference another ID within the XML.

- When you must create a unique ID, the element is named `id`.
- When you must reference another object ID, the element is named for the object. For example, the ID element where you reference a logical field is named `logicalFieldId`.

Note that the IDs you assign to an object are not the IDs Unica Platform assigns to the object. The IDs you assign are used only for referencing the object within the XML.

AddDataConfiguration | dataConfiguration

This group of elements is used to define data configurations you use to group related data filters. You should create a data configuration for every set of related data filters.

Table 56. AddDataConfiguration | dataConfiguration

Element	Description	System table
<code>id</code>	Unique ID that you assign to this data configuration.	N/A
<code>name</code>	Name that you assign to this group of data filters.	Table: <code>df_config</code> Field: <code>config_name</code>

AddLogicalFields | logicalFields | LogicalField

This group of elements is used to define the logical fields corresponding to the fields in the customer table that you use to define your data filters. Create one logical field for each field from which you want to create field constraints, and one logical field for each audience.

Table 57. AddLogicalFields | logicalFields | LogicalField

Element	Description	System table
id	Unique ID that you assign to this logical field.	N/A
name	Logical name for this field or audience. If used with an application in the Unica Campaign family, must be the same as the field or audience name used in Unica Campaign.	Table: df_logical_field Field: logical_name
type	Data type of this field in the customer table. Allowed values are: <ul style="list-style-type: none"> • java.lang.String • java.lang.Long • java.lang.Double • java.lang.Boolean • java.lang.Date (The date format is month/day/year, where the month, day, and year are all expressed as numbers.) 	Table: df_logical_field Field: type

GenerateDataFilters

This group of elements is used to generate data filters when you use **automatic generation**.

Table 58. GenerateDataFilters

Element	Description	System table
tableName	Physical name of the table from which you want to generate data filters, including the database schema name. If the database is case-sensitive, must match case used in the database.	Table: df_table Field: table_name
configurationName	Name of the data configuration in the <code>AddDataConfiguration dataConfiguration</code> element with which this set of data filters is associated.	N/A
jdbcUrl	The URL reference for the customer database containing the table on which you want to base the data filters.	N/A
jdbcUser	The user name of an account with access to the customer database.	N/A
jdbcPassword	The password of the account with access to the customer database.	N/A
jdbcDriverClass	The name of the JDBC driver that provides connectivity to the customer database.	N/A
jdbcDriverClass-Path string	The path of the JDBC driver.	N/A

GenerateDataFilters | fixedFields | FixedField

This group of elements is used to specify the optional fields and the values that limit the records considered when the data filter generation utility looks for unique combinations of values to define a set of data filters. Used only when you use **automatic generation**.

Table 59. GenerateDataFilters | fixedFields | FixedField

Element	Description	System table
<code>expression</code>	One item of the data in the field that will be used in a WHERE clause when creating data filters and retrieving data for a user assigned to this filter. If the database is case-sensitive, must match case used in the database.	Table: <code>df_field_constraint</code> Field: <code>expression</code>
<code>logicalFieldName</code>	Name of the logical field in the AddLogicalFields logicalFields LogicalField element. This name appears as a label in the advanced search field in the Data Filter user interface in Unica Platform.	Table: <code>df_logical_field</code> Field: <code>logical_name</code>
<code>physicalFieldName</code>	Physical name of the field. If the database is case-sensitive, must match case used in the database.	N/A

GenerateDataFilters | profileField | ProfileField

This group of elements is used to specify fields whose unique combinations of values are used to define a set of data filters. Used only when you use **automatic generation**.

Table 60. GenerateDataFilters | profileField | ProfileField

Element	Description	System table
logicalFieldName	Name of the logical field in the AddLogicalFields logicalFields LogicalField element.	Table: df_logical_field Field: logical_name
physicalFieldName	Physical name of the field. If the database is case-sensitive, must match case used in the database.	N/A

AddDataTable | dataTable

This group of elements is used to assign IDs to customer tables.

Table 61. AddDataTable | dataTable

Element	Description	System table
id	Unique ID that you assign to this table.	N/A
name	Physical name of the customer table that you want to secure. If the database is case-sensitive, must match case used in the database.	Table: df_table Field: table_name

AddDataFilters | dataFilters | DataFilter

This group of elements is used to create a data filter when you use **manual specification**.

Table 62. AddDataFilters | dataFilters | DataFilter

Element	Description	System table
configId	ID of the data configuration in the AddDataConfiguration dataConfiguration element with which this filter is associated.	N/A
id	Unique ID that you assign.	N/A

AddDataFilters | dataFilters | DataFilter | fieldConstraints | FieldConstraint

This group of elements is used to specify the data in a field used to define a data filter when you use **manual specification**.

Table 63. AddDataFilters | dataFilters | DataFilter | fieldConstraints | FieldConstraint

Element	Description	System table
logicalField-Id	ID of the logical field in the AddLogicalFields logicalFields LogicalField element.	N/A
expression	One item of the data in a field that is used in a <code>WHERE</code> clause when retrieving data for a user assigned to this filter. If the database is case-sensitive, must match case used in the database.	Table: df_fieldconstraint Field: expression

AddDataTable | dataTable | fields | TableField

This group of elements is used to map physical fields in the customer table to logical fields that you have defined.

Table 64. AddDataTable | dataTable | fields | TableField

Element	Description	System table
name	Physical name of the field in the customer table. If the database is case-sensitive, must match case used in the database.	Table: df_table_field Field: physical_name
logicalField-Id	ID of the logical field in the Add-LogicalFields logical-Fields LogicalField element.	N/A

AddAudience | audience

This group of elements is used to specify the name assigned in Unica Campaign to an audience level used in the Unica Campaign family of products.

Table 65. AddAudience | audience

Element	Description	System table
id	Unique ID that you assign to this audience.	N/A
name	Name of the audience as specified in Unica Campaign.	Table: df_audience Field: audience_name

AddAudience | audience | fields | AudienceField

This group of elements is used to specify the field or fields in your customer tables that are used as audience fields.

Table 66. AddAudience | audience | fields | AudienceField

Element	Description	System table
logicalField-Id	ID of the logical field in the Add-LogicalFields logical-Fields LogicalField element. If used with an application in the Unica Campaign family, must be the same logical name used in Unica Campaign.	N/A
fieldOrder	For future use. Set the value to 0.	N/A

addAudienceTableAssociations | addAudienceTableAssociation | audienceTableAssociation

This group of elements is used to associate pairs of audience fields and tables with data configurations. Create an association for every audience field.

Table 67. addAudienceTableAssociations | addAudienceTableAssociation | audienceTableAssociation

Element	Description	System table
audienceId	ID of the audience to be used in this association. Must be an ID value in an AddAudience audience element.	N/A
tableId	ID of the table to be used in this association. Must be an ID value in an AddDataTable dataTable element. The table must be one that contains the audience specified in the audienceID element. If the audience exists in	N/A

Table 67. addAudienceTableAssociations | addAudienceTableAssociation | audienceTableAssociation (continued)

Element	Description	System table
	more than one table, create multiple associations.	
configId	ID of the data configuration to be used in this association. Must be an ID value in an <code>AddDataConfiguration</code> <code>dataConfiguration</code> element.	N/A

AddAssignments | assignments | AssignmentByName

You can use this group of elements to associate users or groups with data filters. Optional. You can also make these assignments through the user interface.

Table 68. AddAssignments | assignments | AssignmentByName

Element	Description	System table
namespaceId	Name of the data configuration in the <code>AddDataConfiguration</code> <code>dataConfiguration</code> element with which this set of data filters is associated.	N/A
dataObjectId	ID of the filter to be used in this association. Must be an ID value in a <code>DataFilter</code> element.	N/A
principalType	The type of assignment.	Table: <code>ols_assignment</code> Field: <code>principal_type</code>

Table 68. AddAssignments | assignments | AssignmentByName (continued)

Element	Description	System table
	<ul style="list-style-type: none"> • 1 is for assigning a data filter to an individual user • 2 is for assigning a data filter to a group of users 	
principalName	<ul style="list-style-type: none"> • If the value used for principalType is 1, set the value to the Unica Platform login of the user you want to assign to the referenced data filter. • If the value used for principalType is 2, set the value to the name of the Unica Platform group whose members you want to assign to the referenced data filter. 	Table: ols_assignment Field: principal_id

Example: Manually specifying data filters

Jim needs to create a set of data filters based on sales territories.

In Unica Campaign, the customer tables have already been mapped and audience levels have been defined.

Obtaining information

Jim determines that the Territory table contains the fields he needs to specify field constraints for the data filters.

The following table illustrates the information Jim obtains about the customer fields and their Unica Campaign mappings.

Table 69. Territory table fields

Fields (physical name)	Fields (name in Unica Campaign)	Data	Data type
cust_region	CustomerRegion	<ul style="list-style-type: none"> • Africa • Asia • Europe • Middle East • North America 	java.lang-String
hh_id	HouseholdID	N/A	java.lang.Long
indiv_id	IndividualID	N/A	java.lang.Long

Jim learns that the audience names used in Unica Campaign are household and individual. He notes that the Territory table contains two audience fields. The hh_id field corresponds to the household audience. The indiv_id field in the Territory table corresponds to the individual audience.

Because Jim must create one logical field for each audience, and one for the field constraint field, he knows he needs a total of three logical fields.

Jim also knows he needs to group the data filters in a data configuration. He decides to name his data configuration Territory.

Jim is now ready to create the XML.

Creating the XML

Here is the XML that Jim creates. Values based on the information he obtained are shown in **bold**.

```
<ExecuteBatch>
    <!-- ***** -->
    <!--          Data configuration          -->
    <!-- ***** -->
```

```

<name>SeedData</name>
<operations>
  <ExecuteBatch>
    <name>DataFilters</name>
    <operations>
      <AddDataConfiguration>
        <dataConfiguration>
          <id>1</id>
          <name>Territory</name>
        </dataConfiguration>
      </AddDataConfiguration>
    </operations>
  </ExecuteBatch>
  <!-- ***** -->
  <!--           Logical fields           -->
  <!-- ***** -->
  <AddLogicalFields>
    <logicalFields>
      <LogicalField>
        <id>1</id>
        <name>CustomerRegion</name>
        <type>java.lang.String</type>
      </LogicalField>
      <LogicalField>
        <id>2</id>
        <name>HouseholdID</name>
        <type>java.lang.Long</type>
      </LogicalField>
      <LogicalField>
        <id>3</id>
        <name>IndividualID</name>
        <type>java.lang.Long</type>
    </logicalFields>
  </AddLogicalFields>

```

```

    </LogicalField>
  </logicalFields>
</AddLogicalFields>
  <!-- ***** -->
  <!-- Territory field constraints -->
  <!-- ***** -->
<AddDataFilters>
  <dataFilters>
    <DataFilter>
      <configId>1</configId>
      <id>1</id>
      <fieldConstraints>
        <FieldConstraint>
          <logicalFieldId>1</logicalFieldId>
          <expression>Africa</expression>
        </FieldConstraint>
      </fieldConstraints>
    </DataFilter>
    <DataFilter>
      <configId>1</configId>
      <id>2</id>
      <fieldConstraints>
        <FieldConstraint>
          <logicalFieldId>1</logicalFieldId>
          <expression>Asia</expression>
        </FieldConstraint>
      </fieldConstraints>
    </DataFilter>
    <DataFilter>
      <configId>1</configId>
      <id>3</id>
      <fieldConstraints>

```

```

        <FieldConstraint>
            <logicalFieldId>1</logicalFieldId>
            <expression>Europe</expression>
        </FieldConstraint>
    </fieldConstraints>
</DataFilter>
<DataFilter>
    <configId>1</configId>
    <id>4</id>
    <fieldConstraints>
        <FieldConstraint>
            <logicalFieldId>1</logicalFieldId>
            <expression>Middle East</expression>
        </FieldConstraint>
    </fieldConstraints>
</DataFilter>
<DataFilter>
    <configId>1</configId>
    <id>5</id>
    <fieldConstraints>
        <FieldConstraint>
            <logicalFieldId>1</logicalFieldId>
            <expression>North America</expression>
        </FieldConstraint>
    </fieldConstraints>
</DataFilter>
</dataFilters>
</AddDataFilters>
    <!-- ***** -->
    <!-- Map physical to logical fields -->
    <!-- ***** -->
</ExecuteBatch>

```

```

<name>addTables</name>
<operations>
  <AddDataTable>
    <dataTable>
      <id>1</id>
      <name>Territory</name>
      <fields>
        <TableField>
          <name>cust_region</name>
          <logicalFieldId>1</logicalFieldId>
        </TableField>
        <TableField>
          <name>hh_id</name>
          <logicalFieldId>2</logicalFieldId>
        </TableField>
        <TableField>
          <name>indiv_id</name>
          <logicalFieldId>3</logicalFieldId>
        </TableField>
      </fields>
    </dataTable>
  </AddDataTable>
</operations>
</ExecuteBatch>
  <!--
***** -->
  <!-- Audience table associations
-->
  <!--
***** -->
<ExecuteBatch>
  <name>addAudiences</name>

```

```

    <operations>
      <AddAudience>
        <audience>
          <id>1</id>
          <name>household</name>
          <fields>
            <AudienceField>
              <logicalFieldId>2</logicalFieldId>
              <fieldOrder>0</fieldOrder>
            </AudienceField>
          </fields>
        </audience>
      </AddAudience>
      <AddAudience>
        <audience>
          <id>2</id>
          <name>individual</name>
          <fields>
            <AudienceField>
              <logicalFieldId>3</logicalFieldId>
              <fieldOrder>0</fieldOrder>
            </AudienceField>
          </fields>
        </audience>
      </AddAudience>
    </operations>
  </ExecuteBatch>

  <!--
***** -->

  <!--          Associate table-audience pairs
-->

```

```

        <!--                with data configuration
-->

        <!--
***** -->

        <ExecuteBatch>
            <name>addAudienceTableAssociations</name>
            <operations>
                <AddAudienceTableAssociation>
                    <audienceTableAssociation>
                        <audienceId>1</audienceId>
                        <tableId>1</tableId>
                        <configId>1</configId>
                    </audienceTableAssociation>
                </AddAudienceTableAssociation>
                <AddAudienceTableAssociation>
                    <audienceTableAssociation>
                        <audienceId>2</audienceId>
                        <tableId>1</tableId>
                        <configId>1</configId>
                    </audienceTableAssociation>
                </AddAudienceTableAssociation>
            </operations>
        </ExecuteBatch>
    </operations>
</ExecuteBatch>

```

Populating the system tables

Jim has named his data filter XML file `regionDataFilters.xml` and saved it in the `tools/bin` directory under his Unica Platform installation. He opens a command prompt and uses the `datafilteringScriptTool` utility to populate the data filter system tables.

Assigning users and groups to the data filters

Finally, Jim logs in to Unica with an account that has Admin access in Unica Platform.

He knows that groups have already been set up in Unica with users assigned by region.

He goes to the Data Filter section and sees that the field constraints from his data filters are available in the advanced search for data filters. He performs a search for a data filter, using Africa as a search criterion. The data filter he set up for the Africa region appears in the search results.

Next, Jim performs a search for the Africa user group, which has been set up in Unica to hold all field marketers who are responsible for marketing to customers in Africa. The Africa group appears in the search results.

Jim then selects the group and the data filter in the search results, and assigns the group to the data filter by clicking the Assign button.

He continues to perform searches for data filters and groups until all assignments are completed.

Example: Automatically generating a set of data filters

Jim needs to create a set of data filters based on countries, cities, and states.

In Unica Campaign, the customer tables have already been mapped and audience levels have been defined.

Obtaining the JDBC driver

Jim knows that his company's customer database is Microsoft™ SQL server. He downloads the appropriate Type 4 driver and places it on the machine where the Unica Platform is installed, making a note of the name and path of the driver.

- JDBC driver class name - `com.microsoft.sqlserver.jdbc.SQLServerDriver`
- JDBC driver path - `C:\tools\Java\MsJdbc\sqljdbc.jar`

Obtaining information

Jim obtains the name, host, and port of the customer database, and the credentials he needs to connect to it.

- Database name - Customers
- Database host name - companyHost
- Database port - 1433
- User name - sa
- Password - myPassword

Jim looks at the data in his company's customer database and sees that customers exist in every country, city, and state for which he wants to create a data filter. He determines that the Geographic table contains the fields he needs to specify fixed fields and profile fields for the data filters.

The following table illustrates the information Jim obtains about the customer fields and their Unica Campaign mappings.

Table 70. Geographic table fields

Fields (Physical name)	Fields (Name in Uni- ca Campaign)	Data	Data type
country	Country	<ul style="list-style-type: none"> • USA • France • Britain 	java.lang- .String
city	City	A finite set of distinct cities	java.lang- .String
state	State	A finite set of distinct states (or otherwise named regions, depending on country)	java.lang- .String

Table 70. Geographic table fields (continued)

Fields (Physical name)	Fields (Name in Unica Campaign)	Data	Data type
hh_id	HouseholdID	N/A	java.lang.Long
indiv_id	IndividualID	N/A	java.lang.Long

Jim learns that the audience names used in Unica Campaign are household and individual. He notes that the Geographic table contains two audience fields.

- The `hh_id` field corresponds to the household audience.
- The `indiv_id` field in the Geographic table corresponds to the individual audience.

Because Jim must create one logical field for each audience, and one for each of the fixed and profile fields, he knows he needs a total of five logical fields.

Jim also knows he needs to group the data filters in a data configuration. He decides to name his data configuration Geographic.

Jim is now ready to create the XML.

Creating the XML

Here is the XML that Jim creates. Values based on the information he obtained or decided to use are shown in `bold`.

```
<ExecuteBatch>
    <!-- ***** -->
    <!--           Data configuration           -->
    <!-- ***** -->
```

```

<name>SeedData</name>
<operations>
  <ExecuteBatch>
    <name>DataFilters</name>
    <operations>
      <AddDataConfiguration>
        <dataConfiguration>
          <id>1</id>
          <name>Geographic</name>
        </dataConfiguration>
      </AddDataConfiguration>
    </operations>
  </ExecuteBatch>
  <!-- ***** -->
  <!--           Logical fields           -->
  <!-- ***** -->
  <AddLogicalFields>
    <logicalFields>
      <LogicalField>
        <id>1</id>
        <name>Country</name>
        <type>java.lang.String</type>
      </LogicalField>
      <LogicalField>
        <id>2</id>
        <name>City</name>
        <type>java.lang.String</type>
      </LogicalField>
      <LogicalField>
        <id>3</id>
        <name>State</name>
        <type>java.lang.String</type>
    </logicalFields>
  </AddLogicalFields>

```

```

    </LogicalField>
    <LogicalField>
        <id>4</id>
        <name>HouseholdID</name>
        <type>java.lang.Long</type>
    </LogicalField>
    <LogicalField>
        <id>5</id>
        <name>IndividualID</name>
        <type>java.lang.Long</type>
    </LogicalField>
</logicalFields>
</AddLogicalFields>
    <!-- ***** -->
    <!--      Generate data filters      -->
    <!-- ***** -->
<GenerateDataFilters>
    <!--
***** -->
        <!-- Specify the table to be scanned for unique
combinations -->
        <!-- of values  from which data filters will be defined.
-->
        <!--
***** -->
        <tableName>Geographic</tableName>
        <!--
***** -->
        <!-- Identify the data configuration  with which
-->
        <!-- generated data filters will be associated.
-->

```

```

    <!--
***** -->
    <configurationName>Geographic</configurationName>
    <!-- Specify the data source connection information. -->
    <jdbcUrl>
        jdbc:sqlserver://localhost:1433;databaseName=Customers
    </jdbcUrl>
    <jdbcUser>sa</jdbcUser>
    <jdbcPassword>myPassword</jdbcPassword>
    <jdbcDriverClass>
com.microsoft.sqlserver.jdbc.SQLServerDriver</jdbcDriverClass>
    <jdbcDriverClassPath>
        <string>C:\tools\Java\MsJdbc\sqljdbc.jar</string>
    </jdbcDriverClassPath>
    <!-- ***** -->
    <!-- Specify the fixed fields -->
    <!-- ***** -->
    <fixedFields>
        <FixedField>
            <expression>USA</expression>
            <logicalFieldName>Country</logicalFieldName>
            <physicalFieldName>country</physicalFieldName>
        </FixedField>
        <FixedField>
            <expression>France</expression>
            <logicalFieldName>Country</logicalFieldName>
            <physicalFieldName>country</physicalFieldName>
        </FixedField>
        <FixedField>
            <expression>Britain</expression>
            <logicalFieldName>Country</logicalFieldName>

```



```

        <logicalFieldId>2</logicalFieldId>
    </TableField>
    <TableField>
        <name>state</name>
        <logicalFieldId>3</logicalFieldId>
    </TableField>
    <TableField>
        <name>hh_id</name>
        <logicalFieldId>4</logicalFieldId>
    </TableField>
    <TableField>
        <name>indiv_id</name>
        <logicalFieldId>5</logicalFieldId>
    </TableField>
</fields>
</dataTable>
</AddDataTable>
</operations>
</ExecuteBatch>
    <!--
***** -->
    <!-- Audience table associations
-->
    <!--
***** -->
<ExecuteBatch>
    <name>addAudiences</name>
    <operations>
    <AddAudience>
        <audience>
            <id>1</id>
            <name>household</name>

```

```

        <fields>
            <AudienceField>
                <logicalFieldId>4</logicalFieldId>
                <fieldOrder>0</fieldOrder>
            </AudienceField>
        </fields>
    </audience>
</AddAudience>
<AddAudience>
    <audience>
        <id>2</id>
        <name>individual</name>
        <fields>
            <AudienceField>
                <logicalFieldId>5</logicalFieldId>
                <fieldOrder>0</fieldOrder>
            </AudienceField>
        </fields>
    </audience>
</AddAudience>
</operations>
</ExecuteBatch>
    <!--
***** -->
        <!--          Associate table-audience pairs
-->
        <!--          with data configuration
-->
        <!--
***** -->
<ExecuteBatch>
    <name>addAudienceTableAssociations</name>

```

```

    <operations>
      <AddAudienceTableAssociation>
        <audienceTableAssociation>
          <audienceId>1</audienceId>
          <tableId>1</tableId>
          <configId>1</configId>
        </audienceTableAssociation>
      </AddAudienceTableAssociation>
      <AddAudienceTableAssociation>
        <audienceTableAssociation>
          <audienceId>2</audienceId>
          <tableId>1</tableId>
          <configId>1</configId>
        </audienceTableAssociation>
      </AddAudienceTableAssociation>
    </operations>
  </ExecuteBatch>
</operations>
</ExecuteBatch>

```

Populating the system tables

Jim has named his data filter XML file `geographicDataFilters.xml` and saved it in `tools/bin` directory under his Unica Platform installation. He opens a command prompt and uses the `datafilteringScriptTool` utility to populate the data filter system tables.

The utility creates many data filters. In each data filter, the criteria are a country (the fixed field) and a unique combination of city and state obtained when the utility queried the database for records containing the fixed field value. All unique combinations of city and state are used for each country specified as a fixed field.

Assigning users and groups to the data filters

Finally, Jim logs in to the Unica Platform with an account that has Admin access in Unica Platform.

He knows that groups have already been set up in Unica Platform with users assigned by city.

He goes to the Data Filter section and sees that the country, city, and state values from his data filters are available in the advanced search for data filters. He performs a search for a data filter, using Boston, a city in the USA, as a search criterion. The data filter for Boston appears in the search results.

Next, Jim performs a search for the Boston user group, which has been set up in Unica Platform to hold all field marketers who are responsible for marketing to customers in Boston. The Boston group appears in the search results.

Jim then selects the group and the data filter in the search results, and assigns the group to the data filter by clicking the Assign button.

He continues to perform searches for data filters and groups until all assignments are completed.

About assigning users and groups in the XML

You can assign users or groups to data filters in the XML, as an alternative to doing this through the user interface. Assigning users and groups to data filters in the XML is available only when you use manual specification to create the data filters.

You can use a wild card, `#user_login#`, that automatically creates data filters based on the user's Unica Platform login name.

You use the `AddAssignments` XML element block to associate users or groups with your data filters.

Scenario used in the example

The example uses the following scenario.

An organization uses Unica Collaborate and wants to create data filters that allow field marketers to see only the customers in the region to which they are assigned. Thus, each user requires his or her own data filter.

In Unica Collaborate the list display and the form templates are set up based on region. This configuration is described in more detail in the Unica Collaborate Administrator's Guide.

The audience level is Customer.

The data filters are created against four tables in the `exampleSchema` database, as described in the following table.

Table 71. Tables and fields used in the examples

Table	Fields
<code>exampleSchema.Corporate_Lists</code>	UserID, State, and RegionID This is the list display table set up in Unica Collaborate. The UserID column contains the Unica Platform login names of the field marketers. This table associates field marketer Unica Platform login names with their assigned region.
<code>exampleSchema.customer_contact</code>	Indiv_ID, Region_ID, and State fields for customers
<code>exampleSchema.lkup_state</code>	A lookup table for the <code>state_name</code> field
<code>exampleSchema.lkup_region</code>	A lookup table for the <code>region_id</code> field

Example: Using the wild card to assign group members to data filters

To create a separate data filter for each member of a specified group, you do the following.

- Create logical fields as usual.
- Create a single data filter with the wild card `#user_login#` in the `expression` element.
- Under the `AssignmentByName` element, set the `principalType` to 2, set the `principalName` element to the group name, and set the `dataObjectId` element to the ID of the wild card data filter.
- Create audience associations as usual.

The following XML illustrates this method, using the scenario described above.



```

<ExecuteBatch>
    <!-- ***** -->
    <!--          Data configuration          -->
    <!-- ***** -->
    <name>SeedData</name>
    <operations>
        <ExecuteBatch>
            <name>DataFiltering</name>
            <operations>
                <AddDataConfiguration>
                    <dataConfiguration>
                        <id>1</id>
                        <name>collaborate</name>
                    </dataConfiguration>
                </AddDataConfiguration>
            </operations>
        </ExecuteBatch>
        <!-- ***** -->
        <!--          Logical fields          -->
        <!-- ***** -->
        <AddLogicalFields>
            <logicalFields>
                <LogicalField>
                    <id>1</id>
                    <name>Customer_ID</name>
                    <type>java.lang.String</type>
                </LogicalField>

                <LogicalField>
                    <id>2</id>
                    <name>AudienceLevel</name>
                    <type>java.lang.String</type>
            </logicalFields>
        </AddLogicalFields>
    </operations>
</ExecuteBatch>

```

```

</LogicalField>

<LogicalField>
  <id>3</id>
  <name>UserID</name>
  <type>java.lang.String</type>
</LogicalField>

<LogicalField>
  <id>4</id>
  <name>State_code</name>
  <type>java.lang.String</type>
</LogicalField>

<LogicalField>
  <id>5</id>
  <name>Region</name>
  <type>java.lang.Long</type>
</LogicalField>
</logicalFields>
</AddLogicalFields>
<!-- ***** -->
<!--      Wild card data filter      -->
<!-- ***** -->
<AddDataFilters>
  <dataFilters>
    <DataFilter><
      <configId>1</configId>
      <id>1</id>
      <fieldConstraints>
        <FieldConstraint>
          <logicalFieldId>3</logicalFieldId>

```

```

        <expression>#user_login#</expression>
    </FieldConstraint>
</fieldConstraints>
</DataFilter>
</dataFilters>
</AddDataFilters>
    <!--
***** -->
    <!--          Add data tables
-->
    <!--
***** -->

<ExecuteBatch>
    <name>addTables</name>
    <operations>
        <!--
***** -->
        <!--          Table exampleSchema.Corporate_Lists
-->
        <!--
***** -->

        <AddDataTable>
            <dataTable>
                <id>1</id>
                <name>exampleSchema.Corporate_Lists</name>
                <fields>
                    <TableField>
                        <tableId>1</tableId>
                        <name>UserID</name>
                        <logicalFieldId>3</logicalFieldId>
                    </TableField>

```

```

        <TableField>
            <tableId>1</tableId>
            <name>State</name>
            <logicalFieldId>4</logicalFieldId>
        </TableField>
    </TableField>
    <TableField>
        <tableId>1</tableId>
        <name>Region_ID</name>
        <logicalFieldId>5</logicalFieldId>
    </TableField>
</fields>
</dataTable>
</AddDataTable>
<!--
***** -->
<!--          Table exampleSchema.customer_contact
-->
<!--
***** -->
<AddDataTable>
    <dataTable>
        <id>2</id>
        <name>exampleSchema.customer_contact</name>
        <fields>
            <TableField>
                <tableId>2</tableId>
                <name>Indiv_ID</name>
                <logicalFieldId>1</logicalFieldId>
            </TableField>
            <TableField>
                <tableId>2</tableId>
                <name>Region_ID</name>

```

```

        <logicalFieldId>5</logicalFieldId>
    </TableField>
    <TableField>
        <tableId>2</tableId>
        <name>State</name>
        <logicalFieldId>4</logicalFieldId>
    </TableField>
</fields>
</dataTable>
</AddDataTable>
<!--
***** -->
<!--          Table exampleSchema.lkup_state
-->
<!--
***** -->
<AddDataTable>
    <dataTable>
        <id>3</id>
        <name>example.schema.lkup_state</name>
        <fields>
            <TableField>
                <tableId>3</tableId>
                <name>state_name</name>
                <logicalFieldId>4</logicalFieldId>
            </TableField>
        </fields>
    </dataTable>
</AddDataTable>
<!--
***** -->

```



```

        <fields>
            <AudienceField>
                <logicalFieldId>2</logicalFieldId>
                <fieldOrder>0</fieldOrder>
            </AudienceField>
        </fields>
    </audience>
</AddAudience>

<AddAudience>
    <audience>
        <id>2</id>
        <name>default</name>
        <fields>
            <AudienceField>
                <logicalFieldId>2</logicalFieldId>
                <fieldOrder>0</fieldOrder>
            </AudienceField>
        </fields>
    </audience>
</AddAudience>
</operations>
</ExecuteBatch>

<ExecuteBatch>
    <name>addAudienceTableAssociations</name>
    <operations>
        <AddAudienceTableAssociation>
            <audienceTableAssociation>
                <audienceId>1</audienceId>
                <tableId>1</tableId>
                <configId>1</configId>
            </audienceTableAssociation>
        </AddAudienceTableAssociation>
    </operations>
</ExecuteBatch>

```

```

        </audienceTableAssociation>
    </AddAudienceTableAssociation>

    <AddAudienceTableAssociation>
        <audienceTableAssociation>
            <audienceId>1</audienceId>
            <tableId>2</tableId>
            <configId>1</configId>
        </audienceTableAssociation>
    </AddAudienceTableAssociation>

    <AddAudienceTableAssociation>
        <audienceTableAssociation>
            <audienceId>2</audienceId>
            <tableId>3</tableId>
            <configId>1</configId>
        </audienceTableAssociation>
    </AddAudienceTableAssociation>

    <AddAudienceTableAssociation>
        <audienceTableAssociation>
            <audienceId>2</audienceId>
            <tableId>4</tableId>
            <configId>1</configId>
        </audienceTableAssociation>
    </AddAudienceTableAssociation>

    </operations>
</ExecuteBatch>

    <!--
***** -->

```

```

        <!--          Link filters (dataObjectId) to group
-->

        <!--
***** -->
        <AddAssignments>
            <assignments>
                <AssignmentByName>
                    <namespaceId>1</namespaceId>
                    <dataObjectId>1</dataObjectId>
                    <principalType>2</principalType>
                    <principalName>FieldMarketer</principalName>
                </AssignmentByName>
            </assignments>
        </AddAssignments>
    </operations>
</ExecuteBatch>

```

About assigning user and groups through the user interface

You can assign users and groups to data filters on the **Settings > Data filters** pages.

To work with data filters on the **Settings > Data filters** pages, the following must be true.

- The data filters must be set up in Unica Platform system tables.
- You must log in as a user with the Unica Platform permission **Administer data filters page**. The pre-configured Unica Platform **AdminRole** role has this permission.

Advanced search

Unica Platform provides a user interface for assigning users and groups to data filters. This user interface relies on an advanced search feature to obtain lists of users, groups, and data filters. You can select users and groups from these lists and assign them to data filters that you select.

Data filter search

The search feature for data filters provides search criteria that are the same as the criteria specified when the data filters were set up. For example, suppose a set of data filters is based on a field containing the following data relating to sales territories.

- Africa
- Asia
- Europe
- Middle East
- North America

The data filter advanced search would provide this data in a drop-down list from which you can select when searching for data filters.

User and group search

The advanced search feature for users and groups provides a text field where you can enter text for the search to match.

When a tab containing the user and group advanced search first loads, there is a wildcard (*) in both the User and Group text fields. A search performed using this wildcard returns all records.

If you delete the wildcard and do not enter any other text, leaving the field blank, no records are returned. For example, if you perform a search with the User text field blank and an asterisk in the Group text field, only groups would be listed in the results.

On the View Assignments tab, if you leave both the User and Group text fields blank, no records are returned regardless of what data filter criteria are selected.

When you enter text in the field, the search matches the characters you enter in the text field, in the order you enter them. For example, to obtain a group named North America, you could enter any letter or group of letters (in order) that occurs in the name. You would obtain North America in the results if you entered "north" or "h", but not if you entered "htron."

The search is not case-sensitive. That is, "North" is the same as "north."

Viewing assigned data filters

Use this procedure to view assigned data filters

1. Log in to Unica as a user with the Unica Platform AdminRole role and click **Data Filtering**.

The Data filters page displays.

2. Click **View assigned data filters**.
3. Perform an advanced search for assigned data filters to obtain search results.

A list of data filters that meet the criteria is displayed.

Assigning users and groups to data filters

Use this procedure to assign users and groups to data filters.

1. Log in to Unica as a user with the Unica Platform AdminRole role and click **Settings > Data filters**.

The Data filters page displays.

2. Click **Assign users or groups**.
3. Perform an advanced search for data filters to obtain a list of data filters.
4. Perform an advanced search for the users, groups, or both to obtain a list of users and groups.
5. From your search results lists, select data filters and the users and groups you want to assign to them.
6. Click **Assign**.

The selected users and groups are assigned to the selected data filters.

Removing data filter assignments

Use this procedure to remove data filter assignments.

1. Log in to Unica as a user with the Unica Platform AdminRole role and click **Settings > Data filters**.

The Data Filters page displays.

2. Click **View assigned data filters**.
3. Perform an advanced search for assigned data filters to obtain search results from which you want to select.
4. From your search results list, select the data filters whose assignments you want to delete.
5. Click **Unassign**.

The selected assignments are deleted. The data filters themselves are not deleted.

Adding data filters after the initial set has been created

You can continue to add data filters after you have created the initial set. For example, you might create a set of data filters based on countries and their city/state combinations, and later decide to create another set based on zip codes.

You can obtain the XML for additional data filters in either of the following ways.

- Modify your original XML file to add new filters. When you seed the database using the `dataFilteringScriptTool` utility, the Unica Platform creates only the new data filters.
- Create an XML file specifying new data filters. When you seed the database using the `dataFilteringScriptTool` utility, existing data filters are not deleted.

After you have created the XML, populate the data filter tables and assign users and groups as described in this guide.

Audit event tracking in Unica

You can configure which audit events are tracked and assign a severity level to each tracked event.

Two kinds of audit events are tracked:

- Security related events such as changes to user status, group memberships, and permissions
- Changes to Unica configuration properties that are managed on the **Settings > Configuration** page

The audit event information is independent of the system log, and configuration you perform for the system log does not affect audit event tracking.

The Audit Events report provides a convenient way to view the tracked events. You can configure the content of the report, filter the information shown in the report, and export report data.

You must have the AdminRole or PlatformAdminRole role in Unica Platform to configure the Audit Events report and audit backups or to view the report.

Limitations on audit event tracking

If you configure tracking for configuration property audit events, these changes are tracked only when they are performed using the **Settings > Configuration** page.

For example, the following configuration property changes are not tracked.

- Changes made using Unica Platform utility `configTool`
- Changes made during installation and upgrade of Unica products

Also, when you manually add default users, roles, and permissions for Unica Platform and Unica Campaign using the Unica Platform `populateDB` utility, these changes are not tracked.

Legacy audit events

Previous releases of Unica Platform saved audit events in the Unica Platform system tables, although no report was available. If you upgrade from a version earlier than 9.1.1, the Audit Events report includes these legacy events.

Legacy audit events are displayed in the report as follows.

- The **Severity** column contains **No severity (Legacy)** to indicate that these audit records were stored before the audit report was available.
- In an environment with just one partition, the **Partition** column contains the ID of the default partition.
- In a multi-partition environment, the **Partition** column contains **-1 (Legacy)** to indicate that the partition to which the event belongs cannot be determined.

The following legacy events may appear after your upgrade.

- User authentication succeeded.
- User authentication failed.
- Authentication failed because a user attempted to log in with too many concurrent sessions.
- User logged off and the corresponding session ended.
- User's password changed.

Legacy audit events are visible in reports only when you access the report with an account that has the PlatformAdminRole role in Unica Platform. The pre-defined platform_admin user has this role.

Retroactive changes

If the first name, last name, or email address of a user account is changed, all audit events tracked for this user reflect the changes. This is true even for events tracked before the user profile changes were made.

Permissions for viewing the Audit Events report in a multi-partition environment

In a multi-partition environment, the partition membership of the administrator viewing the Audit Events report affects the events that are included when the administrator views the report.

For all audit events except configuration events, the report shows only those events that occurred in the partition of the administrator viewing the report. Events that occurred in other partitions are not shown in the report.

The exception is administrators with the PlatformAdminRole role, who can see events that occur in all partitions.

All configuration events are visible to all administrators who can view the report.

Enabling and disabling event auditing

By default, event auditing is disabled. To enable event auditing, you set the **Unica Platform | Audit Events | Is Event Auditing enabled** configuration property to True.

This configuration property affects only the audit events listed under **Unica Platform | Audit Events** on the Configuration page. The events tracked in the system log are not affected.

You can disable event auditing at any time by setting the value of the **Is Event Auditing enabled** configuration property to False.

The Audit Events report does not include the events controlled by the **Is Event Auditing enabled** property that occurred during any period when the property was set to **False**.

Configuring which audit events appear in the report

To specify the audit events that are available in the audit report and their severity, you set properties on the **Settings > Configuration** page.

1. Go to the **Settings > Configuration** page and expand the **Unica Platform | Audit Events | Audit Events Configuration** category.
2. Select the events that you want to track.

The tracked events are available for inclusion in the audit report.

3. Expand the **Unica Platform | Audit Events | Audit events severity configuration** category and click **Edit settings**.
4. Specify the severity level that you want to assign to each of the tracked events.

Select from the following options.

- No severity
- Informational
- Warning
- Critical

The specified severity appears in the audit report, and can be used in filtering the report.

If you want to track the user session event **Record login and logout events for members of the HighSeverityAccounts group**, add the users whose login and logout events you want to track to the **highSeverityAccounts** group. You do this on the **Settings > User groups** page.

This group is created automatically in the default partition during installation. In a multi-partition environment, this group is created automatically when you create a new partition using the Unica Platform `partitionTool` utility.

Modifying the audit report content and display

You can add and remove events and columns, rearrange and sort the columns, set the time span, specify which tracked events are shown in the report, and filter the information.

When you open the audit report without setting any report parameters, the following default settings are used.

- All of the events selected on the **Settings > Configuration** page under the **Unica Platform | Audit Events | Audit Events Configuration** category are shown, on multiple pages if necessary.
- No date criteria are applied.
- Events are sorted as follows: Event Date/Time (Descending), Login Name(Ascending), Severity Level (Ascending)

Use this procedure to modify these settings.

1. Go to **Analytics > Platform**.
2. To change the content of the report, do the following.

- a. Click the **Report Parameters** button.

The Report Parameters window opens.

- b. Complete the fields.

To set the sort order in the report, you can select from pre-defined sort orders in this window. You can also click the column headers in the report to sort on those columns.

- c. Click **Next** to move to a page where you can select which events are shown in the report.

- d. Click **Save and Close** to apply your selections to the report.

3. To filter the report, enter text or numbers in the **Filter** field and click the **Filter** button.

The report displays only those events that contain the filter characters in any of the columns displayed in the report.

To clear the filter, click the **X** in the Filter field.

Fields in the Report Parameters window

Use the fields on the Report Parameters page to configure the way the audit report is displayed.

Table 72. Fields in the Report Parameters window

Field	Description
Sort	<p>Select a sort order from the drop-down menu. Various combinations of column sorting are listed, along with whether the sort is in descending or ascending order.</p> <p>You can also sort columns using controls on the report page.</p>
Time Period	<p>Select from pre-defined time periods in the drop-down list, or enter start and end dates for a custom range.</p>

Table 72. Fields in the Report Parameters window (continued)

Field	Description
Events	Select the optional events that you want to include in the report. For an event to be available in the report, it must be selected in the Unica Platform Audit Events Audit Events Configuration category on the Settings > Configuration page.
Columns	Use the Add and Remove buttons to specify the optional columns you want to appear in the report.

Fields and buttons in the Audit Events report

Fields in the Audit Events report provide details about system and user events in Unica.

Table 73. Fields and buttons in the Audit Event report

Field or button	Description
Filter	To filter the report, enter text or numbers in the Filter field and click the button. The report displays only those events that contain the filter characters in any of the columns displayed in the report.
 Report parameters	Click to open a window where you can change the columns displayed in the report, set a time period, and select from pre-defined sort orders.
 Export	Click to open a window where you can export the report in CSV or text format.
 Refresh	Click to refresh the report data.
Default fields	

Table 73. Fields and buttons in the Audit Event report (continued)

Field or button	Description
Event date/time (short)	The date and time of the event on the server where Unica Platform is deployed.
Event name	The tracked event. Events that are tracked are specified on the Settings > Configuration page.
Event details	Details about the tracked event. When a link is present, you can click it to see full details.
Login name	The login name of the user who performed the action.
Last name, first name	The first and last name of the user who performed the action.
Severity	The severity assigned to the event on the Unica Platform Audit Events Audit Events Severity Configuration page.
Optional fields set in the Report Parameters window	
Browser	The browser used by the person who performed the action.
Host name	The name or IP address of the machine from which the action was performed.
Request from	The URI where the HTTP request originated.
Event date/time (long)	The date and time of the event on the server where Unica Platform is deployed, including the time zone.
User email	The email address of the user who performed the action.
Partition	The partition membership of the user who performed the action.

Archived audit events

You can configure backups of audit events by setting the value of configuration properties in the **Unica Platform | Audit Events | Audit Events Configuration** category on the **Settings > Configuration** page.

The archived data is stored in the `USM_AUDIT_BACKUP` table and can be included in the Audit Events report when you set a custom date range that includes data from the archive. Loading a report that includes archived data can take longer than loading a report that does not include archived data.

The system posts a notification when an audit backup process completes. You can also configure a group of users who receive these notifications in emails.

Set the following properties to configure audit event backups.

- **Enable Audit Backup**
- **Archive data after the number of days specified here**
- **Keep Audit records in primary for number days specified here**
- **Archive start time**
- **Name of group to receive audit backup notifications**

Configuring audit backup notifications

To notify users of the status of audit event backup, make them members of a group that you specify in a configuration property.

1. Determine the group whose members you want to receive email notifications of audit data backups.

You can use an existing group or create a new one on the **Settings > User groups** page.

You can specify only a single group to receive notifications.

2. Go to the **Settings > Configuration** page and expand the **Unica Platform | Audit Events | Audit events configuration** category.
3. Set the value of the **Name of group to receive audit backup notifications** property to the name of the group you selected.

4. Add the users who should receive notifications to the group.
5. The users who you have added to the group must subscribe to the notifications on the **Settings > Users** page.

An administrator can do this for each user, or you can inform the users that they must go to their account, click **Notification subscriptions**, and subscribe to **Audit backup** notifications.

Each time the system backs up audit data, an email notification and user interface notification is generated for the members of the group you specified, if they have subscribed to Audit Event notifications.

Exporting the Audit Events report

You can export the security audit report to a text or comma separated file.

1. Go to **Analytics > Marketing Platform**.
2. Click the **Export** button.
3. In the Audit Report Export window, enter a name for your exported report, and select the export format.

The format options are:

- **CSV** (a comma separated list that Microsoft™ Excel can open)
- **TXT** (text)

If you select text format, you also choose the separator. Options are:

- **#**
- **|**
- **TAB**

4. Click **Export**, specify whether you want to open or save the exported report, and then close the export window.

Optimizing the export of the Audit Events report for large event volumes

If you want to export large audit event reports, for example, reports containing more than 65,000 records matching your audit event report filter criteria, the export can time out. To circumvent this problem, perform the following procedure.

This procedure applies when you use Internet Explorer to access the Audit Event report.

1. Edit the Windows™ registry as follows.

- a. Open the Windows™ registry editor and navigate to `HKEY_CURRENT_USER\Software\Microsoft\Windows\CurrentVersion\Internet Settings`.
- b. If a DWORD entry named `ReceiveTimeout` does not exist, create one.

To create a new DWORD entry, do the following.

- Right-click on `Internet Settings` and select **New > DWORD (32-bit) Value**.
 - Enter `ReceiveTimeout` as the name for the new entry.
- c. Give the existing or new `ReceiveTimeout` entry a value as follows.
 - Right-click on the `ReceiveTimeout` entry and select **Modify**.
 - Under **Base**, select **Decimal**.
 - Specify the timeout interval in milliseconds.

For example, to specify 3 hours, you would enter 10800000, which is 180 minutes * 60 seconds * 1000.

2. Configure Internet Explorer as follows.

- a. Select **Tools > Internet Options** and click the Security tab.
- b. Select the zone where you access Unica Platform. For example, Trusted Sites.
- c. Click **Custom level**.
- d. Under **Downloads**, enable **Automatic prompting for file downloads**.
- e. Restart Internet Explorer.

The Unica Platform system log

You should check the system log first if the Unica Platform application malfunctions. The system log is independent of the security audit information, which is stored in the system tables. While the system log tracks some of the same information contained in the security audit reports, it also contains information useful in troubleshooting Unica Platform.

The system log contains the following information.

- Configuration information and all errors and debugging information for the Unica Platform.
- A record of key events as they occur on the Unica Platform server (requests, grants, revokes, and failures).

About the configuration settings displayed in the system log



Note: If a problem occurs when the system attempts to write to the system log file, the system writes to stdout (command line) instead of to a file.

System log entry format

The system log entries are in the following format.

```
Timestamp | Event severity level | Message
```

- **Timestamp** – The time the event occurred.
- **Event Severity Level** – The logging level of the event.
- **Message** – Description of the event. If the entry is a request to the server, the message typically contains the function called by the request. Response entries record the results of the requests.

System log configuration

You configure the system log using the `log4j.properties` file, located by default in the `conf` directory under your Unica Platform installation. Changes to this file go into effect within 30 seconds after the file is saved.

Configuration you perform on the system log does not affect security audit reports.

Default system log settings

By default, the system log is configured as follows:

- Log file name: `platform.log`
- Log directory: `Unica/Platform/logs`
- Log level: `WARN`
- Number of backups: 1
- Maximum size of log files: 10MB

Note the following.

- If you increase the number of backups or size of the log files, verify that the machine on which the logs are stored has sufficient memory.
- Setting the logging level higher than the default might affect performance.

Logging levels in the system log

The possible logging levels in the system log are as follows, in ascending order.

- `ERROR`
- `WARN`
- `INFO`
- `DEBUG`
- `TRACE`

The higher levels include the information contained in all of the lower levels. For example, setting the level to `DEBUG` enables the `DEBUG`, `INFO`, `WARN` and `ERROR` traces.

If the logging level is set to DEBUG, the response messages include any SQL queries performed against the Unica Platform data store.

Logging level settings for the whole Unica Platform system

You can change the logging level for all components of Unica Platform by uncommenting the desired line in the Examples section of the file. To uncomment a line, remove the # character at the beginning of the line. If you make this change, be sure to add the # symbol to the beginning of the line specifying the previous logging level.

Setting logging levels for Unica Platform components

You can set the logging level in the system log for specific components of the Unica Platform. These components include:

- Localization
- User and group processing
- Data migration
- LDAP integration
- Authentication (server-side processing)
- The Configuration pages
- Database access
- Various third-party libraries (for example, ibatis)

By default, the component-level logging is turned off. To debug a specific module, remove the # character at the start of each line of the module in the `log4j.properties` file.

Where to find more information about log4j

You can find additional information about log4j in the following ways.

- See comments in the `log4j.properties` file.
- See <http://logging.apache.org/log4j/docs/documentation.html>.

Enabling single-user logging

You can enable single-user logging by configuring logging to use the XML file and then editing the XML file.

Logging is configured using one of two files: `log4j.properties` or `log4j.xml`. By default, the `log4j.properties` file is used.

You can enable per-user logging by configuring logging to use the XML file and then editing the XML file. If Unica Platform is configured in a cluster deployment, copy the XML file to each node.



Note: With XML logging enabled, a thread is created that periodically checks if the XML configuration file has been created or modified. If a change or file creation is detected, then the XML file is read to configure log4j. The polling interval is 60 seconds.

1. Configure logging to use `log4j.xml` by setting the following JVM parameter.

```
-DENABLE_PLATFORM_LOG4J_XML_LOGGING=true
```

The value must be set to `true` to enable per-user logging.

If Unica Platform is configured in a cluster deployment, set this JVM parameter in each node of the cluster.

2. To specify the user account to be logged in per-user logging, edit the `log4j.xml` file and add the users in the filter tag. The logs for the users that are added in the filter tag are saved in the file that is mentioned. You can also create an appender without the filter tag.
 - You can add multiple tags in the `log4j.xml` file to create separate log files for specific users. You must add a new appender for each new user specific log file.
 - By default, the log file is created in the `Platform_Home /Platform/logs` folder and is named as `platform.log`. You can specify a different valid path and file name. You must specify the absolute or complete path to generate the log files in the respective folders.

- If both user specific logs and logs for all users are required, add an appender tag with a new name and without the filter tag defined. The appender must have a unique name.
 - Add a corresponding entry under the root tag for this new appender.
3. If Unica Platform is configured in a cluster deployment, copy the edited XML file to each node of the cluster.

You can use a command like the one shown in the following example.

```
-DPLATFORM_LOG4J_XML_FILE=log4j_node1.xml
```

The `log4j_node1.xml` file is a copy of the `log4j.xml` file. You can use any name for the copied file.

Consider the following example where the logs are collected for the user `asm_admin` and also for all other users.

```
<appender name="Console" class="org.apache.log4j.ConsoleAppender">
  <param name="ImmediateFlush" value="true"/>
  <layout class="org.apache.log4j.PatternLayout">
    <param name="ConversionPattern" value="%-5p %c - %m%n"/>
  </layout>
  <filter class="com.unica.manager.logger.UserMatchFilter">
    <param name="StringToMatch" value="asm_admin" />
  </filter>
</appender>

<!-- The following section is for user specific logs for the user asm_admin
-->
<appender name="System" class="org.apache.log4j.RollingFileAppender">
  <param name="File" value="\${UNICA_PLATFORM_LOG_FILE}"/>
  <!-- <param name="Encoding" value="utf-8"/>
  <param name="Append" value="true"/>
  <param name="ImmediateFlush" value="false"/>
-->
```

```

<param name="MaxBackupIndex" value="1"/>
<param name="MaxFileSize" value="10MB"/>
<layout class="org.apache.log4j.PatternLayout">
  <param name="ConversionPattern" value="%d{DATE} - %-5p - %m%n"/>
</layout>
<filter class="com.unica.manager.logger.UserMatchFilter">
  <param name="StringToMatch" value="asm_admin" />
</filter>
</appender>

<!-- The following section is for logs for all the users -->
<appender name="SystemAllUsers"
class="org.apache.log4j.RollingFileAppender">
  <param name="File" value="<LOG_FILE_PATH>"/><!--the absolute path for the
log file-->
  <!-- <param name="Encoding" value="utf-8"/>
  <param name="Append" value="true"/>
  <param name="ImmediateFlush" value="false"/>
  -->
  <param name="MaxBackupIndex" value="1"/>
  <param name="MaxFileSize" value="10MB"/>
  <layout class="org.apache.log4j.PatternLayout">
    <param name="ConversionPattern" value="%d{DATE} - %-5p - %m%n"/>
  </layout>
</appender>

<!-- <logger name="com.unica.manager.configuration.ConfigurationManager">
  <level value="TRACE"/>
</logger>

<logger name="com.unica.suite.scheduler.server.manager.TaskManager">
  <level value="DEBUG"/>
</logger>

```

```
<logger name="org.hibernate.util.JDBCExceptionReporter">
  <level value="ERROR" />
</logger>
-->
<root>
  <level value="WARN" />
  <appender-ref ref="System" />
  <appender-ref ref="Console" />
  <appender-ref ref="SystemAllUsers" />
</root>
```

Unica Platform utilities

This section provides an overview of the Unica Platform utilities, including some details that apply to all of the utilities and which are not included in the individual utility descriptions.

Location of utilities

Unica Platform utilities are located in the `tools/bin` directory under your Unica Platform installation.

List and descriptions of utilities

The Unica Platform provides the following utilities.

- [alertConfigTool \(on page 312\)](#) - registers alerts and configurations for Unica products
- [configTool \(on page 313\)](#) - imports, exports, and deletes configuration settings, including product registrations
- [datafilteringScriptTool \(on page 319\)](#) - creates data filters
- [encryptPasswords \(on page 321\)](#) - encrypts and stores passwords
- [encryptTomcatDBPasswords \(on page 322\)](#) - encrypt the database passwords that the Tomcat Application server uses internally
- [partitionTool \(on page 323\)](#) - creates database entries for partitions

- `populateDb` (on page 327) - populates the Unica Platform database
- `restoreAccess` (on page 327) - restores a user with the `platformAdminRole` role
- `scheduler_console_client` (on page 330) - lists or starts Unica Scheduler jobs that are configured to listen for a trigger.
- `quartzjobtool` (on page) - Update scheduler jobs created in version 11.1 and older versions
- `BIRTdbutil` - Installer places report design files which possesses database connection tokens. You must update them for your system database. You must run `BIRTdbutil.sh/bat` utility to update the same. See the BIRT Installation and Configuration Guide for more details.

Prerequisites for running Unica Platform utilities

The following are prerequisites for running all Unica Platform utilities.

- Run all utilities from the directory where they are located (by default, the `tools/bin` directory under your Unica Platform installation).
- On UNIX™, the best practice is to run the utilities with the same user account that runs the application server on which Unica Platform is deployed. If you run a utility with a different user account, adjust the permissions on the `platform.log` file to allow that user account to write to it. If you do not adjust permissions, the utility is not able to write to the log file and you might see some error messages, although the tool should still function correctly.

Authentication of utilities

Utilities such as `configTool` and other Unica back end utilities are designed to be used by system administrators and require physical access to the host servers for them to be invoked. For this reason, authentication for these utilities has been designed to be independent of the UI authentication mechanism. Access to these utilities is available to users with Unica Platform administrator privileges. Access to these utilities is expected to be locally defined in Unica Platform and authenticated against the same.

Troubleshooting connection issues

All of the Unica Platform utilities except `encryptPasswords` interact with the Unica Platform system tables. To connect to the system table database, these utilities use the following connection information, which is set by the installer using information provided when the Unica Platform was installed. This information is stored in the `jdbc.properties` file, located in the `tools/bin` directory under your Unica Platform installation.

- JDBC driver name
- JDBC connection URL (which includes the host, port, and database name)
- Data source login
- Data source password (encrypted)

In addition, these utilities rely on the `JAVA_HOME` environment variable, set either in the `setenv` script located in the `tools/bin` directory of your Unica Platform installation, or on the command line. The Unica Platform installer should have set this variable automatically in the `setenv` script, but it is a good practice to verify that the `JAVA_HOME` variable is set if you have a problem running a utility. The JDK must be the Sun version (not, for example, the JRockit JDK available with WebLogic).

Special characters

Characters that are designated as reserved characters in the operating system must be escaped. Consult your operating system documentation for a list of reserved characters and how to escape them.

Standard options in Unica Platform utilities

The following options are available in all Unica Platform utilities.

`-l logLevel`

Set the level of log information displayed in the console. Options are `high`, `medium`, and `low`. The default is `low`.

`-L`

Set the locale for console messages. The default locale is en_US. The available option values are determined by the languages into which the Unica Platform has been translated. Specify the locale using the ICU locale ID according to ISO 639-1 and ISO 3166.

-h

Display a brief usage message in the console.

-m

Display the manual page for this utility in the console.

-v

Display more execution details in the console.

Setting up Unica Platform utilities on additional machines

On the machine where the Unica Platform is installed, you can run the Unica Platform utilities without any additional configuration. However, you might want to run the utilities from another machine on the network. This procedure describes the steps required to do this.

Ensure that the machine on which you perform this procedure meets the following prerequisites.

- The correct JDBC driver must exist on the machine or be accessible from it.
- The machine must have network access to the Unica Platform system tables.
- The Java™ runtime environment must be installed on the machine or be accessible from it.

1. Gather the following information about the Unica Platform system tables.

- The fully qualified path for the JDBC driver file or files on your system.
- The fully qualified path to an installation of the Java™ runtime environment.

The default value in the installer is the path to the supported version of the JRE that the installer places under your Unica installation directory. You can accept this default or specify a different path.

- Database type

- Database host
 - Database port
 - Database name/system ID
 - Database user name
 - Database password
2. Run the Unica installer and install the Unica Platform.

Enter the database connection information that you gathered for the Unica Platform system tables. If you are not familiar with the Unica installer, see the Unica Campaign or Unica Plan installation guide.

You do not have to deploy the Unica Platform web application if you are installing the utilities only.

Unica Platform utilities

This section describes the Unica Platform utilities, with functional details, syntax, and examples.

alertConfigTool

Notification types are specific to the various Unica products. Use the `alertConfigTool` utility to register the notification types when the installer has not done this automatically during installation or upgrade.

Syntax

```
alertConfigTool -i -f importFile
```

Commands

```
-i -f importFile
```

Import alert and notification types from a specified XML file.

Example

- Import alert and notification types from a file named `Platform_alerts_configuration.xml` located in the `tools\bin` directory under the Unica Platform installation.

```
alertConfigTool -i -f Platform_alerts_configuration.xml
```

configTool

The properties and values on the **Configuration** page are stored in the Unica Platform system tables. You can use the `configTool` utility to import and export configuration settings to and from the system tables.

When to use configTool

You might want to use `configTool` for the following reasons.

- To import partition and data source templates that are supplied with Unica Campaign, which you can then modify and duplicate by using the **Configuration** page.
- To register (import configuration properties for) Unica products, if the product installer is unable to add the properties to the database automatically.
- To export an XML version of configuration settings for backup or to import into a different installation of Unica.
- To delete categories that do not have the **Delete Category** link. You do this by using `configTool` to export your configuration, then manually deleting the XML that creates the category, and by using `configTool` to import the edited XML.



Important: This utility modifies the `usm_configuration` and `usm_configuration_values` tables in the Unica Platform system table database, which contains the configuration properties and their values. For best results, either create backup copies of these tables, or export your existing configurations by using `configTool` and back up the resulting file so you have a way to restore your configuration if you make an error when you use `configTool` to import.

Syntax

```
configTool -d -p "elementPath" [-o]
```

```
configTool -i -p "parent ElementPath" -f importFile [-o]
```

```
configTool -x -p "elementPath" -f exportFile
```

```
configTool -vp -p "elementPath" -f importFile [-d]
```

```
configTool -r productName -f registrationFile [-o] configTool -u productName
```

Commands

-d -p "elementPath" [o]

Delete configuration properties and their settings, specifying a path in the configuration property hierarchy.

The element path must use the internal names of categories and properties. You can obtain them by going to the **Configuration** page, selecting the wanted category or property, and looking at the path that is displayed in parentheses in the right pane. Delimit a path in the configuration property hierarchy by using the | character, and surround the path with double quotation marks.

Note the following.

- Only categories and properties within an application can be deleted by using this command, not whole applications. Use the `-u` command to unregister a whole application.
- To delete categories that do not have the **Delete Category** link on the **Configuration** page, use the `-o` option.

When you use `-d` with the `-vp` command, the `configTool` deletes any child nodes in the path you specify if those nodes are not included in the XML file you specify.

-i -p "parentElementPath" -f importFile [o]

Import configuration properties and their settings from a specified XML file.

To import, you specify a path to the parent element under which you want to import your categories. The `configTool` utility imports properties under the category you specify in the path.

You can add categories at any level below the top level, but you cannot add a category at same level as the top category.

The parent element path must use the internal names of categories and properties. You can obtain them by going to the **Configuration** page, selecting the required category or property, and looking at the path that is displayed in parentheses in the right pane. Delimit a path in the configuration property hierarchy by using the `|` character, and surround the path with double quotation marks.

You can specify an import file location relative to the `tools/bin` directory or you can specify a full directory path. If you specify a relative path or no path, `configTool` first looks for the file relative to the `tools/bin` directory.

By default, this command does not overwrite an existing category, but you can use the `-o` option to force an overwrite.

```
-x -p "elementPath" -f exportFile
```

Export configuration properties and their settings to an XML file with a specified name.

You can export all configuration properties or limit the export to a specific category by specifying a path in the configuration property hierarchy.

The element path must use the internal names of categories and properties, which you can obtain by going to the **Configuration** page, selecting the wanted category or property, and looking at the path that is displayed in parentheses in the right pane. Delimit a path in the configuration property hierarchy by using the `|` character, and surround the path with double quotation marks.

You can specify an export file location relative to the current directory or you can specify a full directory path. If the file specification does not contain a separator (`/` on UNIX™, `/` or `\` on Windows™), `configTool` writes the file to the `tools/bin` directory under your Unica Platform installation. If you do not provide the `xml` extension, `configTool` adds it.

```
-vp -p "elementPath" -f importFile [-d]
```

This command is used mainly in manual upgrades, to import configuration properties. If you applied a fix pack that contains a new configuration property, and you then upgrade, importing a configuration file as part of a manual upgrade process can override values that were set when the fix pack was applied. The `-vp` command ensures that the import does not override previously set configuration values.



Important: After you use the `configTool` utility with the `-vp` option, you must restart the web application server on which Unica Platform is deployed so the changes are applied.

When you use `-d` with the `-vp` command, the `configTool` deletes any child nodes in the path you specify if those nodes are not included in the XML file you specify.

`-r productName -f registrationFile`

Register the application. The registration file location can be relative to the `tools/bin` directory or can be a full path. By default, this command does not overwrite an existing configuration, but you can use the `-o` option to force an overwrite. The `productName` parameter must be one of those names that are listed above.

Note the following.

- When you use the `-r` command, the registration file must have `<application>` as the first tag in the XML.

Other files can be provided with your product that you can use to insert configuration properties into the Unica Platform database. For these files, use the `-i` command. Only the file that has the `<application>` tag as the first tag can be used with the `-r` command.

- The registration file for the Unica Platform is named `Manager_config.xml`, and the first tag is `<Suite>`. To register this file on a new installation, use the `populateDb` utility, or rerun the Unica Platform installer as described in the *Unica Platform Installation Guide*.
- After the initial installation, to re-register products other than the Unica Platform, use `configTool` with the `-r` command and `-o` to overwrite the existing properties.

The `configTool` utility uses product names as parameters with the commands that register and unregister products. With the 8.5.0 release of Unica, many product names changed. However, the names that are recognized by `configTool` did not change. The valid product names for use with `configTool` are listed below, along with the current names of the products.

Table 74. Product names for configTool registration and unregistration

Product name	Name used in configTool
Unica Platform	Manager
Unica Campaign	Campaign
Unica Collaborate	Collaborate
IBM eMessage	emessage
Unica Interact	interact
Unica Optimize	Optimize
Unica Plan	Plan
Opportunity Detect	Detect
IBM SPSS Modeler Advantage Enterprise Marketing Management Edition	SPSS
Digital Analytics	Coremetrics

-u *productName*

Unregister an application that is specified by *productName*. You do not have to include a path to the product category; the product name is sufficient, and it is required. The process removes all properties and configuration settings for the product.

Options

-o

When used with `-i` or `-r`, it overwrites an existing category or product registration (node).

When used with `-d`, you can delete a category (node) that does not have the **Delete Category** link on the **Configuration** page.

Examples

- Import configuration settings from a file named `Product_config.xml` in the `conf` directory under the Unica Platform installation.

```
configTool -i -p "Affinium" -f Product_config.xml
```

- Import one of the supplied Unica Campaign data source templates into the default Unica Campaign partition, `partition1`. The example assumes that you placed the Oracle data source template, `OracleTemplate.xml`, in the `tools/bin` directory under the Unica Platform installation.

```
configTool -i -p "Affinium|Campaign|partitions|partition1|dataSources" -f
OracleTemplate.xml
```

- Export all configuration settings to a file named `myConfig.xml` in the `D:\backups` directory.

```
configTool -x -f D:\backups\myConfig.xml
```

- Export an existing Unica Campaign partition (complete with data source entries), save it to a file named `partitionTemplate.xml`, and store it in the default `tools/bin` directory under the Unica Platform installation.

```
configTool -x -p "Affinium|Campaign|partitions|partition1" -f
partitionTemplate.xml
```

- Manually register an application named `productName`, by using a file named `app_config.xml` in the default `tools/bin` directory under the Unica Platform installation, and force it to overwrite an existing registration of this application.

```
configTool -r product Name -f app_config.xml -o
```

- Unregister an application named `productName`.

```
configTool -u productName
```

- Run the following command to enable `encodeCSV` feature:

```
configTool -vp -p "Affinium|Plan|umoConfiguration" -f Plan_Home\conf
\Plan_encodeProperty_12.0.xml
```

- Register Unica Interact Settings as configuration menu under `AffiniumWebApps\Campaign\interact\conf\interact_setup_navigation.xml` using

```
configTool.bat -v -i -p "Affinium|suite|uiNavigation|settingsMenu" -f
"interact_setup_navigation.xml"
```

datafilteringScriptTool

The `datafilteringScriptTool` utility reads an XML file to populate the data filtering tables in the Unica Platform system table database.

Depending on how you write the XML, you can use this utility in two ways.

- Using one set of XML elements, you can auto-generate data filters based on unique combinations of field values (one data filter for each unique combination).
- Using a slightly different set of XML elements, you can specify each data filter that the utility creates.

See Unica Platform the Administrator's Guide for information about creating the XML.

When to use datafilteringScriptTool

You must use `datafilteringScriptTool` when you create new data filters.

Prerequisites

The Unica Platform must be deployed and running.

Using datafilteringScriptTool with SSL

When the Unica Platform is deployed using one-way SSL you must modify the `datafilteringScriptTool` script to add the SSL options that perform handshaking. To modify the script, you must have the following information.

- Truststore file name and path
- Truststore password

In a text editor, open the `datafilteringScriptTool` script (`.bat` or `.sh`) and find the lines that look like this (examples are Windows™ version).

```
:callexec

"%JAVA_HOME%\bin\java" -DUNICA_PLATFORM_HOME="%UNICA_PLATFORM_HOME%"

com.unica.management.client.datafiltering.tool.DataFilteringScriptTool %*
```

Edit these lines to look like this (new text is in **bold**). Substitute your truststore path and file name and truststore password for `myTrustStore.jks` and `myPassword`.

```
:callexec

SET SSL_OPTIONS=-Djavax.net.ssl.keyStoreType="JKS"

-Djavax.net.ssl.trustStore="C:\security\myTrustStore.jks"

-Djavax.net.ssl.trustStorePassword=myPassword

"%JAVA_HOME%\bin\java" -DUNICA_PLATFORM_HOME="%UNICA_PLATFORM_HOME%"

%SSL_OPTIONS%

com.unica.management.client.datafiltering.tool.DataFilteringScriptTool %*
```

Syntax

```
datafilteringScriptTool -r pathfile
```

Commands

-r *path_file*

Import data filter specifications from a specified XML file. If the file is not located in the `tools/bin` directory under your installation, provide a path and enclose the `path_file` parameter in double quotation marks.

Example

- Use a file named `collaborateDataFilters.xml`, located in the `C:\unica\xml` directory, to populate the data filter system tables.

```
datafilteringScriptTool -r "C:\unica\xml\collaborateDataFilters.xml"
```

encryptPasswords

The `encryptPasswords` utility is used to encrypt and store either of two passwords that Unica Platform uses internally.

The two passwords that the utility can encrypt are as follows.

- The password that the Unica Platform uses to access its system tables. The utility replaces an existing encrypted password (stored in the `jdbc.properties` file, located in the `tools\bin` directory under your Unica Platform installation) with a new one.
- The keystore password used by the Unica Platform when it is configured to use SSL with a certificate other than the default one supplied with the Unica Platform or the web application server. The certificate can be either a self-signed certificate or a certificate from a certificate authority.

When to use encryptPasswords

Use `encryptPasswords` as for the following reasons.

- When you change the password of the account used to access your Unica Platform system table database.
- When you have created a self-signed certificate or have obtained one from a certificate authority.

Prerequisites

- Before running `encryptPasswords` to encrypt and store a new database password, make a backup copy of the `jdbc.properties` file, located in the `tools/bin` directory under your Unica Platform installation.
- Before running `encryptPasswords` to encrypt and store the keystore password, you must have created or obtained a digital certificate and know the keystore password.

Syntax

```
encryptPasswords -d databasePassword
```

```
encryptPasswords -k keystorePassword
```

Commands

-d *databasePassword*

Encrypt the database password.

-k *keystorePassword*

Encrypt the keystore password and store it in a file named `pfile`.

Examples

- When the Unica Platform was installed, the login for the system table database account was set to `myLogin`. Now, some time after installation, you have changed the password for this account to `newPassword`. Run `encryptPasswords` as follows to encrypt and store the database password.

```
encryptPasswords -d newPassword
```

- You are configuring an Unica application to use SSL and have created or obtained a digital certificate. Run `encryptPasswords` as follows to encrypt and store the keystore password.

```
encryptPasswords -k myPassword
```

encryptTomcatDBPasswords

The `encryptTomcatDBPasswords` utility is used to encrypt the database passwords that the Tomcat Application server uses internally. It is used to encrypt database passwords used in Campaign.xml and unica.xml. This utility can encrypt the Unica application database password. The utility prints the encrypted password in the command line.

When to use encryptTomcatDBPasswords

Use `encryptTomcatDBPasswords` utility when you want to use encrypted password under Tomcat configurations. It can be used when the Campaign or Unica System DB password has expired or changed. You can use this utility and encrypt the password and this will be get replaced in Campaign.xml, unica.xml and plan.xml located at `<instanceHome>\conf\Catalina\localhost`.

Syntax

```
encryptTomcatDBPasswords -d databasePassword
```

Commands

`-d databasePassword`

Encrypt the database password.



Note:

This utility is available only when the user selects Tomcat as the application server while installing Unica Platform.

This utility can be used only in case when the user wants use encrypted passwords instead of plain text passwords, under Tomcat configurations.

Please refer the Tomcat documentation at <https://wiki.apache.org/tomcat/FAQ/Password> which explains more on the security.

partitionTool

Partitions are associated with Unica Campaign policies and roles. These policies and roles and their partition associations are stored in the Unica Platform system tables. The `partitionTool` utility seeds the Unica Platform system tables with basic policy and role information for partitions.

When to use partitionTool

For each partition you create, you must use `partitionTool` to seed the Unica Platform system tables with basic policy and role information.

See the installation guide appropriate for your version of Unica Campaign for detailed instructions on setting up multiple partitions in Unica Campaign.

Special characters and spaces

Any partition description or user, group, or partition name that contains spaces must be enclosed in double quotation marks.

Syntax

```
partitionTool -c -s sourcePartition -n newPartitionName [-u admin_user_name]  
[-d partitionDescription] [-g groupName]
```

Commands

The following commands are available in the `partitionTool` utility.

-c

Replicates (clones) the policies and roles for an existing partition specified using the `-s` option, and uses the name specified using the `-n` option. Both of these options are required with `c`. This command does the following.

- Creates a new Unica user with the Admin role in both the Administrative Roles policy and the global policy in Unica Campaign. The partition name you specify is automatically set as this user's password.
- Creates a new Unica Platform group and makes the new Admin user a member of that group.
- Creates a new partition object.
- Replicates all the policies associated with the source partition and associates them with the new partition.
- For each replicated policy, replicates all roles associated with the policy.
- For each replicated role, maps all functions in the same way that they were mapped in the source role.
- Assigns the new Unica Platform group to the last system-defined Admin role created during role replication. If you are cloning the default partition, partition1, this role is the default Administrative Role (Admin).

Options

-d *partitionDescription*

Optional, used with `-c` only. Specifies a description that appears in the output from the `-list` command. Must be 256 characters or less. Enclose in double quotation marks if the description contains spaces.

-g *groupName*

Optional, used with `-c` only. Specifies the name of the Unica Platform Admin group that the utility creates. The name must be unique within this instance of Unica Platform

If not defined, the name defaults to `partition_nameAdminGroup`.

-n *partitionName*

Optional with `-list`, required with `-c`. Must be 32 characters or less.

When used with `-list`, specifies the partition whose information is listed.

When used with `-c`, specifies the name of the new partition, and the partition name you specify is used as the password for the Admin user. The partition name must match the

name you gave the partition in when you configured it (using the partition template on the Configuration page).

-s *sourcePartition*

Required, used with `-c` only. The name of the source partition to be replicated.

-u *adminUserName*

Optional, used with `-c` only. Specifies the user name of the Admin user for the replicated partition. The name must be unique within this instance of Unica Platform.

If not defined, the name defaults to `partitionNameAdminUser`.

The partition name is automatically set as this user's password.

Examples

- Create a partition with the following characteristics.
 - Cloned from partition1
 - Partition name is `myPartition`
 - Uses the default user name (`myPartitionAdminUser`) and password (`myPartition`)
 - Uses the default group name (`myPartitionAdminGroup`)
 - Description is "ClonedFromPartition1"

```
partitionTool -c -s partition1 -n myPartition -d "ClonedFromPartition1"
```

- Create a partition with the following characteristics.
 - Cloned from partition1
 - Partition name is `partition2`
 - Specifies user name of `customerA` with the automatically assigned password of `partition2`
 - Specifies group name of `customerAGroup`
 - Description is "PartitionForCustomerAGroup"

```
partitionTool -c -s partition1 -n partition2 -u customerA -g
customerAGroup -d "PartitionForCustomerAGroup"
```

populateDb

The `populateDb` utility inserts default (seed) data in the Unica Platform system tables.

The Unica installer can populate the Unica Platform system tables with default data for Unica Platform and for Unica Campaign. However, if your company policy does not permit the installer to change the database, or if the installer is unable to connect with the Unica Platform system tables, you must insert default data in the Unica Platform system tables using this utility.

For Unica Campaign, this data includes security roles and permissions for the default partition. For Unica Platform, this data includes default users and groups, and security roles and permissions for the default partition.

Syntax

```
populateDb -n productName
```

Commands

```
-n productName
```

Insert default data into the Unica Platform system tables. Valid product names are `Manager` (for Unica Platform) and `Campaign` (for Unica Campaign).

Examples

- Insert Unica Platform default data manually.

```
populateDb -n Manager
```

- Insert Unica Campaign default data manually.

```
populateDb -n Campaign
```

restoreAccess

The `restoreAccess` utility allows you to restore access to Unica Platform if all users with `PlatformAdminRole` privileges have been inadvertently locked out or if all ability to log in to the Unica Platform has been lost.

When to use `restoreAccess`

You might want to use `restoreAccess` under the two circumstances described in this section.

PlatformAdminRole users disabled

It is possible that all users with PlatformAdminRole privileges in Unica Platform might become disabled in the system. Here is an example of how the `platform_admin` user account might become disabled. Suppose you have only one user with PlatformAdminRole privileges (the `platform_admin` user). Assume the `Maximum failed login attempts allowed` property in the **General | Password settings** category on the Configuration page is set to 3. Then suppose someone who is attempting to log in as `platform_admin` enters an incorrect password three times in a row. These failed login attempts cause the `platform_admin` account to become disabled in the system.

In that case, you can use `restoreAccess` to add a user with PlatformAdminRole privileges to the Unica Platform system tables without accessing the web interface.

When you run `restoreAccess` in this way, the utility creates a user with the login name and password you specify, and with PlatformAdminRole privileges.

If the user login name you specify exists in Unica Platform as an internal user, that user's password is changed.

Only a user with the login name of PlatformAdmin and with PlatformAdminRole privileges can universally administer all dashboards. So if the `platform_admin` user is disabled and you create a user with `restoreAccess`, you should create a user with a login of `platform_admin`.

Improper configuration of NTLMv2 authentication

If you implement NTLMv2 authentication with improper configuration and can no longer log in, use `restoreAccess` to restore the ability to log in.

When you run `restoreAccess` in this way, the utility changes the value of the `Platform | Security | Login method` property to `Unica Platform`. This change allows you to log in with any user account that existed before you were locked out. You can optionally specify a new login name and password as well. You must restart the web application server on which Unica Platform is deployed if you use the `restoreAccess` utility in this way.

Password considerations

Note the following about passwords when you use `restoreAccess`.

- The `restoreAccess` utility does not support blank passwords, and does not enforce password rules.
- If you specify a user name that is in use, the utility resets the password for that user.

Syntax

```
restoreAccess -u loginName -p password
```

```
restoreAccess -r
```

Commands

-r

When used without the `-u loginName` option, reset the value of the Platform | Security | Login method property to Unica Platform. Requires restart of the web application server to take effect.

When used with the `-u loginName` option, create a PlatformAdminRole user.

Options

-u *loginName*

Create a user with PlatformAdminRole privileges with the specified login name. Must be used with the `-p` option.

-p *password*

Specify the password for the user being created. Required with `-u`.

Examples

- Create a user with PlatformAdminRole privileges. The login name is `tempUser` and the password is `tempPassword`.

```
restoreAccess -u tempUser -p tempPassword
```

- Change the value of the login method to `Platform` and create a user with `PlatformAdminRole` privileges. The login name is `tempUser` and the password is `tempPassword`.

```
restoreAccess -r -u tempUser -p tempPassword
```

scheduler_console_client

Jobs configured in the Unica Scheduler can be listed and kicked off by this utility, if they are set up to listen for a trigger.

What to do if SSL is enabled

When the Unica Platform web application is configured to use SSL, the JVM used by the `scheduler_console_client` utility must use the same SSL certificate that is used by the web application server on which the Unica Platform is deployed.

Take the following steps to import the SSL certificate

- Determine the location of the JRE used by the `scheduler_console_client`.
 - If `JAVA_HOME` is set as a system environment variable, the JRE it points to is the one used by the `scheduler_console_client` utility.
 - If `JAVA_HOME` is not set as a system environment variable, the `scheduler_console_client` utility uses the JRE set either in the `setenv` script located in the `tools/bin` directory of your Unica Platform installation, or on the command line.
- Import the SSL certificate used by the web application server on which the Unica Platform is deployed to the JRE used by `scheduler_console_client`.

The Sun JDK includes a program called `keytool` that you can use to import the certificate. Consult the Java™ documentation for complete details on using this program, or access the help by entering `-help` when you run the program.

- Open the `tools/bin/schedulerconsoleclient` file in a text editor and add the following properties. These differ depending on the web application server on which Unica Platform is deployed.

- For WebSphere®, add these properties to the file.
 - Djavax.net.ssl.keyStoreType=JKS
 - Djavax.net.ssl.keyStore="Path to your key store JKS file"
 - Djavax.net.ssl.keyStorePassword="Your key store password"
 - Djavax.net.ssl.trustStore="Path to your trust store JKS file"
 - Djavax.net.ssl.trustStorePassword="Your trust store password"
 - DisUseIBMSSLSocketFactory=false
- For WebLogic, add these properties to the file.
 - Djavax.net.ssl.keyStoreType="JKS"
 - Djavax.net.ssl.trustStore="Path to your trust store JKS file"
 - Djavax.net.ssl.trustStorePassword="Your trust store password"

If the certificates do not match, the Unica Platform log file contains an error such as the following.

```
Caused by: sun.security.provider.certpath.SunCertPathBuilderException: unable
to find valid certification path to requested target
```

Prerequisites

The Unica Platform must be installed, deployed, and running.

Syntax

```
scheduler_console_client -v -t trigger_name user_name
```

```
scheduler_console_client -s -t trigger_name user_name
```

Commands

-v

List the scheduler jobs configured to listen for the specified trigger.

Must be used with the `-t` option.

-s

Send the specified trigger.

Must be used with the `-t` option.

Options

`-t trigger_name`

The name of the trigger, as configured in the scheduler.

Example

- List jobs configured to listen for a trigger named `trigger1`.

```
scheduler_console_client -v -t trigger1 myLogin
```

- Execute jobs configured to listen for a trigger named `trigger1`.

```
scheduler_console_client -s -t trigger1 myLogin
```

Unica Platform SQL scripts

This section describes the SQL scripts provided with Unica Platform to perform various tasks relating to the Unica Platform system tables.

The Unica Platform SQL scripts are located in the `db` directory under your Unica Platform installation.

The scripts are designed to be run against the Unica Platform system tables, using the database client.

ManagerSchema_DeleteAll.sql

The `ManagerSchema_DeleteAll.sql` script removes all data from the Unica Platform system tables without removing the tables themselves. This script removes all users, groups, security credentials, data filters, and configuration settings from Unica Platform.

When to use ManagerSchema_DeleteAll.sql

You might want to use `ManagerSchema_DeleteAll.sql` if corrupted data prevents you from using an instance of Unica Platform.

Additional requirements

To make Unica Platform operational after running `ManagerSchema_DeleteAll.sql`, you must perform the following steps.

- Run the `populateDB` utility. The `populateDB` utility restores the default configuration properties, users, roles, and groups, but does not restore any users, roles, and groups you have created or imported after initial installation.
- Use the `configTool` utility with the `config_navigation.xml` file to import menu items.
- If you have performed any post-installation configuration, such as creating data filters or integrating with an LDAP server or web access control platform, you must perform these configurations again.
- If you want to restore previously existing data filters, run the `datafilteringScriptTool` utility using the XML originally created to specify the data filters.

ManagerSchema_PurgeDataFiltering.sql

The `ManagerSchema_PurgeDataFiltering.sql` script removes all data filtering data from the Unica Platform system tables without removing the data filter tables themselves. This script removes all data filters, data filter configurations, audiences, and data filter assignments from Unica Platform.

When to use ManagerSchema_PurgeDataFiltering.sql

You might want to use `ManagerSchema_PurgeDataFiltering.sql` if you need to remove all data filters without removing other data in the Unica Platform system tables.



Important: The `ManagerSchema_PurgeDataFiltering.sql` script does not reset the values of the two data filter properties, `Default table name` and `Default audience name`. If these values are no longer valid for the data filters you want to use, you must set the values manually on the Configuration page.

ManagerSchema_DropAll.sql

The `ManagerSchema_DropAll.sql` script removes all Unica Platform system tables from a database. This script removes all tables, users, groups, security credentials, and configuration settings from Unica Platform.



Note: If you run this script against a database containing an earlier version of the Unica Platform system tables, you might receive error messages in your database client stating that constraints do not exist. You can safely ignore these messages.

When to use ManagerSchema_DropAll.sql

You might want to use `ManagerSchema_DropAll.sql` if you have uninstalled an instance of Unica Platform where the system tables are in a database that contains other tables you want to continue using.

Additional requirements

To make the Unica Platform operational after running this script, you must perform the following steps.

- Run the appropriate SQL script to re-create the system tables.
- Run the `populateDB` utility. Running the `populateDB` utility restores the default configuration properties, users, roles, and groups, but does not restore any users, roles, and groups you have created or imported after initial installation.
- Use the `configTool` utility with the `config_navigation.xml` file to import menu items.
- If you have performed any post-installation configuration, such as creating data filters or integrating with an LDAP server or web access control platform, you must perform these configurations again.

SQL scripts for creating system tables

Use the scripts described in the following table to create Unica Platform system tables manually, when your company policy does not allow you to use the installer to create them automatically.

The scripts are shown in the order in which you must run them.

Table 75. Scripts for creating system tables

Datasource Type	Script Names
IBM® DB2®	<ul style="list-style-type: none"> • ManagerSchema_DB2.sql <p>If you plan to support multi-byte characters (for example, Chinese, Japanese, or Korean), use the ManagerSchema_DB2_unicode.sql script.</p> <ul style="list-style-type: none"> • ManagerSchema__DB2_CeateFKConstraints.sql • active_portlets.sql
Microsoft™ SQL Server	<ul style="list-style-type: none"> • ManagerSchema_SqlServer.sql • ManagerSchema__SqlServer_CeateFKConstraints.sql • active_portlets.sql
Informix	<ul style="list-style-type: none"> • ManagerSchema_informix • ManagerSchema_informix_CreateFKConstraints • quartz_informix • active_portlets.sql
MariaDB	<ul style="list-style-type: none"> • ManagerSchema_MariaDB.sql • ManagerSchema_MariaDB_StoredProcedures.sql • ManagerSchema_MariaDB_CreateFKConstraints.sql • active_portlets.sql • quartz_MariaDB.sql
Oracle	<ul style="list-style-type: none"> • ManagerSchema_Oracle.sql • ManagerSchema__Oracle_CeateFKConstraints.sql • active_portlets.sql

If you plan to use the scheduler feature that enables you to configure a flowchart to run at predefined intervals, you must also create the tables that support this feature. To create the scheduler tables, run the appropriate script, as described in the following table.

Table 76. Scripts for enabling the Unica Scheduler

Data Source Type	Script Name
DB2®	quartz_db2.sql
Microsoft™ SQL Server	quartz_sqlServer.sql
Oracle	quartz_oracle.sql
MariaDB	quartz_MariaDB.sql
Informix	quartz_informix.sql

When to use the create system tables scripts

You must use these scripts when you install or upgrade Unica Platform if you have not allowed the installer to create the system tables automatically, or if you have used `ManagerSchema_DropAll.sql` to delete all Unica Platform system tables from your database.

Unica configuration properties

This section describes the configuration properties found on the **Settings & Configuration** page.

Unica Platform configuration properties

This section describes the Unica Platform configuration properties on the Configuration page.

Unica Platform

Properties in this category allow you to set the default locale, and to set flags for whether the installation of Unica Platform is clustered, whether Unica Plan is integrated with Unica Campaign, and whether offer integration is enabled for the integration.

Region

Description

Specifies the locale preference for Unica users. When you set this property on the Configuration page, the setting you apply is the default setting throughout Unica for all users, except those whose locale preference is set individually through the Unica Platform User page. When you set this property for an individual user, the setting you apply for that user overrides the default setting.

This preference setting affects display of the language, time, numbers, and dates in Unica applications.

Availability of locales may vary depending on the Unica application, and not all applications support this locale setting in the Unica Platform. See specific product documentation to determine availability and support for the `Region setting` property.

Default value

English (United States)

Help server

Description

The URL of the server on which hosted online help is installed. If Unica users have internet access, you should not change the default value, which points to the online help server maintained and updated by .

Default value

The URL of the hosted help server.

Valid Values

Any server on which hosted help is installed.

Unica Plan - Unica Campaign integration

Description

A flag indicating whether Unica Plan and Unica Campaign are installed together and integrated. For more information about configuring this integration, see the Unica Plan and Unica Campaign Integration Guide.

Default value

False

Valid Values

True | False

Unica Plan - Offer integration

Description

For systems the integrate Unica Plan with Unica Campaign, this flag indicates whether offer integration is also enabled. Offer integration enables the ability to use Unica Plan to perform offer lifecycle management tasks. For more information about configuring this integration, see the Unica Plan and Unica Campaign Integration Guide.

Default value

False

Valid Values

True | False

Start page

Description

The URL of the page that appears when users log in to Unica. The default is the default dashboard.

Default value

The default dashboard.

Valid Values

Any Unica URL except form submissions pages, edit pages, and search result pages.

Domain name

Description

The name of the domain where Unica is installed. The value is set during installation. If the value is not set during installation, provide the proper domain name. You should not change this unless the domain name changes.

If users access Unica products with the Chrome browser, use the fully qualified domain name (FQDN). If the FQDN is not used, the Chrome browser cannot access the product URLs.

Default value

Not defined

Disable page tagging

Description

When set to the default value of `False`, uses the Site ID code that was entered during Unica Platform installation to gather basic statistics that track overall product usage trends to develop and improve products. sends the information to <http://pt200201.unica.com> over HTTP.

If you do not want to have such information collected, set this property to `True`.

Default value

`False`

Valid values

`True` | `False`

Is this deployment clustered

Description

If you install Unica Platform in a clustered deployment, set this property to `True`. Otherwise, retain the default value of `False`.

If you change this property while Unica Platform is running, you must restart Unica Platform for the changes to take effect.

Default value

`False`

Valid values

`True` | `False`

Apply security on static content for all applications

Description

When this value is set to `Yes`, if an authenticated user attempts to directly access any static content such as an image, a check is performed to verify the user's authentication. If the user is authenticated, the content is rendered. If the user is not authenticated, the user is sent to the login page. This setting applies across all Unica products.

Default value

`No`

Valid values

`Yes` | `No`

HCL Unica | General | Navigation

Properties in this category specify values that are used internally to navigate among Unica products.

TCP port for secure connections

Description

Specifies the SSL port in the web application server on which the Unica Platform is deployed. This property is used internally for communication among Unica products.

Default value

7001

TCP port for standard connections

Description

Specifies the HTTP port in the web application server on which the Unica Platform is deployed. This property is used internally for communication among Unica products.

Default value

7001

Unica Platform URL

Description

Specifies the URL used for Unica Platform. This is set at installation time and normally should not be changed. Note that the URL contains the domain name, as shown in the following example.

```
protocol://machine_name_or_IP_address.domain_name:port_number/  
context-root
```

The machine name should not be `localhost`.

If users access Unica products with the Chrome browser, use the fully qualified domain name (FQDN) in the URL. If the FQDN is not used, the Chrome browser cannot access the product URLs.



Important: If Unica products are installed in a distributed environment, you must use the machine name rather than an IP address in the navigation URL for all of the applications in the suite. Also, if you are on a clustered environment and choose to use ports that are different



from the default ports 80 or 443 for your deployment, do not use a port number in the value of this property.

Default value

Not defined

Example

In an environment configured for SSL, the URL might look like this:

```
https://machineName.companyDomain.com:8080/unica
```

HCL Unica | General | Data filtering

Properties in this category specify values used when data filtering is implemented.

Default table name**Description**

This configuration property is required to enable data filters.

Set the value of this property to exactly match the name used for the

`addTables` | `AddDataTable` | `dataTable` | `name` element in the XML used to create the data filters.

Default value

Undefined

Valid values

Maximum of 50 characters of type varchar.

Default audience name**Description**

This configuration property is required to enable data filters.

Set the value of this property to exactly match the name used for the

`AddAudience` | `audience` | `name` element in the XML used to create the data filters.

Default value

Undefined

Valid values

Maximum of 50 characters of type varchar.

Enable data filter cache**Description**

This property is optional, and can be set to improve data filter performance.

This property specifies whether the Unica Platform retrieves data filter definitions from the database or from a cache. When this value is **true**, data filter definitions are stored in the cache and the cache is updated whenever there is any change in the data filter definitions.

You must restart the Unica Platform web application after you make a change in this property value before it can take effect.

Default value

False

HCL HCL Unica | General | Password settings

Properties in **General | Password Settings** category specify the policies that apply to Unica passwords. Most of these password options apply only to passwords for internal users (created within the Unica Platform), not to external users that are imported from an external system.

The exception is the `Maximum failed login attempts allowed` property, which affects both internal and external users. Also note that this property does not override any similar restriction set in an external system.

Maximum failed login attempts allowed**Description**

Specifies the maximum number of times an invalid password may be entered each time a user logs in. If the maximum is reached, the user is disabled in the Unica system, and no one can log in as that user.

If set to zero or less, the system allows an infinite number of consecutive failures.

Default value

3

Valid values

Any integer

Password history count

Description

Specifies the number of old passwords the system retains for a user. The user is not allowed to reuse any passwords within this list of old passwords. If the value is set to zero or less, then no history is retained, and the user may reuse the same password repeatedly. Note that the password history count does not include the password initially assigned to a user account when it is created.

Default value

0

Valid values

Any integer

Validity (in days)

Description

Specifies the number of days before a user's password expires.

If the value is zero or less, then the password never expires.

If the value is greater than zero, users are required to change their password the first time they log in, and the expiration interval is counted from the date of the first login.

If you change this value after users and passwords have been created, the new expiration date takes effect for existing users the next time they change their password.

Default value

30

Valid values

Any integer

Blank passwords allowed**Description**

Specifies whether the a blank password is allowed.If you set this to true you should also set `Minimum character length=0`.

Default value

true

Valid values

true | false

Allow identical user name and password**Description**

Specifies whether the user's password is allowed to be the same as the user's login name.

Default value

false

Valid values

true | false

Minimum number of numeric characters**Description**

Specifies the minimum number of numbers required in a password. If the value is zero or less, then there is no minimum requirement.

Default value

0

Valid values

Any integer

Minimum number of letter characters

Description

Specifies the minimum number of letters required in a password. If the value is zero or less, then there is no minimum requirement.

Default value

0

Valid values

Any integer

Minimum character length

Description

Specifies the minimum length of a password. If the value is zero or less, then there is no minimum requirement. If you set the value to greater than 0, you should also set `Blank passwords allowed=false`.

Default value

4

Valid values

Any integer

HCL HCL Unica | General | Miscellaneous

Properties in this category specify values that are used internally, as well as a value you may need to set for the locale.

Token lifetime

Description

Specifies the length of time, in seconds, that a token generated by the Unica Platform is valid. It is part of the suite sign-on implementation, and you should not change this value.

Default value

15

Valid values

Any positive integer

Default language

Description

Specifies the default language for the Unica Platform. If you plan to install Unica Campaign, you should set this value to match the locale set for Unica Campaign in the `defaultLocale` property for Unica Campaign.

Default value

English

Valid values

Supported locales

HCL Unica | General | Communication | Email

Properties in this category are used to configure the Unica Platform to send emails to users for system alerts and notifications.

Enable email communication

Description

When set to `True`, the Unica Platform attempts to send emails to users for system alerts and notifications. The other properties in this category must also be set to enable this feature.

Default value

`False`

Email server protocol

Description

Specifies the protocol on the mail server that is used for sending system alerts and notifications to users. This is required for email notifications.

Default value

`smtp`

Email server host

Description

Specifies the name of the mail server used for sending system alerts and notifications to users. This is required for email notifications.

Default value

`localhost`

Email server port

Description

Specifies the port of the mail server used for sending system alerts and notifications to users. This is required for email notifications.

Default value

`25`

'From' address for emails

Description

Specifies the account from which system alert and notification emails are sent. If authentication is required on your mail server, use the email address of the account that you used when you saved a mail server account name and password as a data source in a Unica Platform user account. This is required for email notifications.

Default value

Not defined

Authentication required for mail server?

Description

Specifies whether the mail server requires authentication.

Default value

False

Unica user for email account

Description

Specifies the user name of the Unica Platform account where the email credentials are stored as a data source.

Required for notifications, only if your mail server requires authentication.

Default value

asm_admin

Data source for email account

Description

Specifies the name of the data source in the Unica Platform account where the email credentials are stored.

Required for notifications, only if your mail server requires authentication.

Default value

emailDS

Unica Platform | Scheduler

Properties in this category allow you to enable and tune the performance of the Unica Scheduler.

Client polling interval (ms)

Configuration category

Platform|Scheduler

Description

Unica Campaign polls the Unica Scheduler for jobs at regular intervals, specified in milliseconds by this value. The default value is 60 seconds. Avoid setting this property to any value less than 10000 (10 seconds), because doing so can decrease campaign performance.

Default value

60000

Client initialization delay (ms)

Description

The amount of time, expressed in milliseconds, that the Unica Campaign scheduler thread waits before polling the Unica Scheduler for jobs when Unica Campaign first starts up. Set this value to be at least as long as it takes for Unica Campaign to fully start up on your system. The default value is five minutes.

Default value

300000

Valid Values

Any integer

Maximum unknown status polling count

Description

Specifies the number of times the scheduler checks the status of a scheduled run whose status cannot be determined. After this limit is reached, the run status is listed as Unknown on the **Settings > Schedule management** page.

Default value

5

Valid Values

Any integer

Enable Scheduler

Description

Specifies whether the scheduler is enabled. Set this property to False if you do not want users to be able to use the scheduler. The False setting turns off the scheduler for all products that use it.

You must restart the Unica Platform web application when you enable or disable the scheduler.

Default value

True

Valid Values

True | False

Unica Platform | Scheduler | Recurrence definitions

Properties in this category set the recurrence patterns for the Unica Scheduler. These appear in the dialog box you use if you set a recurrence pattern when you create a schedule. You can use the Recurrence template to create your own recurrence pattern, using any valid Cron expression.

Every hour

Description

The job is triggered every hour.

Default value

0 0 0/1 * * ?

Every day

Description

The job is triggered every 24 hours.

Default value

0 0 0 * * ?

Every [day of week] at 12:00 am

Description

The job is triggered on the specified day of the week at 12:00 am.

Default value

- Monday - 0 0 0 ? * MON
- Tuesday - 0 0 0 ? * TUE
- Wednesday - 0 0 0 ? * WED
- Thursday - 0 0 0 ? * THU
- Friday - 0 0 0 ? * FRI
- Saturday - 0 0 0 ? * SAT
- Sunday - 0 0 0 ? * SUN

[First|Last] day of every month at 12:00 am

Description

The job is triggered on the specified day of the month (first or last) at 12:00 am.

Default value

- First day of every month - 0 0 0 1 * ?
- Last day of every month - 0 0 0 L * ?

[First|Last] day of every quarter at 12:00 am**Description**

The job is triggered on the specified day of the calendar quarter (first or last day) at 12:00 am.

Default value

- First day of every quarter - 0 0 0 1 * JAN, APR, JUL, OCT
- Last day of every quarter - 0 0 0 L * MAR, JUN, SEP, DEC

[First|Last] day of every year at 12:00 am**Description**

The job is triggered on the specified day of the year (first or last) at 12:00 am.

Default value

- First day of every year - 0 0 0 1 ? JAN *
- Last day of every year - 0 0 0 L ? DEC *

Every [month] at 12:00 am**Description**

The job is triggered on the first day of the specified month at 12:00 am.

Default value

- Every January - 0 0 0 1 ? JAN *
- Every February - 0 0 0 1 ? FEB *
- Every March - 0 0 0 1 ? MAR *
- Every April - 0 0 0 1 ? APR *

- Every May - 0 0 0 1 ? MAY *
- Every June - 0 0 0 1 ? JUN *
- Every July - 0 0 0 1 ? JUL *
- Every August - 0 0 0 1 ? AUG *
- Every September - 0 0 0 1 ? SEP *
- Every October - 0 0 0 1 ? OCT *
- Every November - 0 0 0 1 ? NOV *
- Every December - 0 0 0 1 ? DEC *

Unica Platform | Scheduler | Schedule registrations | [Product] | [Object type]

A different category exists for each of the object types that can be scheduled with the Unica Scheduler. Properties in these categories should not normally be changed.

Executor class name

Description

The class that the Unica Scheduler uses to trigger a flowchart or mailing run.

Default value

Status polling interval

Configuration category

`Platform|Scheduler|Schedule registrations|[Product]|
[Object type]`

For Unica Campaign flowcharts, the path for this property is `Platform|
Scheduler|Schedule registrations|Campaign|Flowchart`

Description

The Unica Scheduler polls the product at regular intervals to obtain the run status of scheduled objects (for example, flowcharts or mailings) that have not reported a status. The interval is specified in milliseconds. The default value is 10 minutes. A more frequent polling interval (a smaller value) can

negatively affect system performance. A less frequent polling interval (a larger value) reduces the load on the system. For Unica Campaign, set a less frequent polling interval when you have a large number of Unica Campaign flowcharts that take more than 10 minutes to complete.

Default value

600000

Name of group to receive job notifications**Description**

Notifications for all schedules for each object type are sent to all members of the group you specify here.

Unica Platform | Scheduler | Schedule registrations | [Product] | [Object type] | [Throttling group]

Default throttling groups exist for each of the object types that can be scheduled with the Unica scheduler. Note that these default groups do not appear on the User groups page. You can use the throttling group template to create additional groups.

Throttling threshold**Description**

The greatest number of schedules associated with this group that can run concurrently. The groups you specify here appear in the **Scheduler group** drop-down list in the scheduler user interface for creating and editing schedules. The default throttling group is set to 999, which is effectively no limit. Because all schedules must belong to a throttling group, you should leave this value unchanged so that schedules that you do not want to throttle can be assigned to this group.

Default value**Valid Values**

Any positive integer.

Unica Platform | Security

The property in this category specifies the login mode for Unica products.

Login method

Description

Specifies the authentication mode for all Unica products installed and configured to work together, as follows:

- If you set the value to `Unica Platform`, Unica products use the Unica Platform for authentication and authorization.
- If you set the value to `LDAP`, Unica products use an LDAP server for authentication.
- If you set the value to `Web access control`, Unica products use web access control software for authentication.
- If you set the value to `SAML 2.0`, Unica products use your IdP server for authentication.

If you change this setting, stop and restart the Unica Platform web application so that your change takes effect.

Default value

`Unica Platform`

Valid Values

`Unica Platform` | `LDAP` | `Web access control`

Unica Platform | Security | Login method details | LDAP

Properties in this category are used to configure LDAP integration.

LDAP server host name

Description

Specifies the name or IP address of the LDAP server. Set the value to the machine name or IP address of the LDAP server. For example:

```
machineName.companyDomain.com
```

If you are integrating with Windows™ Active Directory, use the server name instead of the DNS name.

Default value

Undefined

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

LDAP server port**Description**

Specifies the port on which the LDAP server listens. Set the value to the appropriate port number. Typically, the port number is 389 (636 if SSL is used).

Default value

389

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

User search filter**Description**

Specifies the filter to use to search for users. Valid values are any valid LDAP search filter (see [RFC 2254](#)). Note that you must XML-escape any XML characters in this value.

Typically, the value for the user login attribute is `uid` for LDAP servers and `sAMAccountName` for Windows™ Active Directory servers. You should verify this on your LDAP or Active Directory server. If your LDAP server is Windows™

Active Directory, you should change the default value of this property to use `sAMAccountName` rather than `uid`. For example:

```
(&( |(objectClass=user)(objectClass=person))(sAMAccountName={0}))
```

Default value

```
(&( |(objectClass=user)(objectClass=person))(uid={0}))
```

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

Use credentials stored in Unica Platform

Description

Specifies whether the Unica Platform uses credentials from the Unica Platform database when searching the LDAP or Windows™ Active Directory server during user authentication (at login time).

If this value is `true`, the Unica Platform uses credentials from the Unica Platform database, and you must set the appropriate values for the `Unica Platform user for LDAP credentials` and `Data source for LDAP credentials` properties in this category.

If your LDAP or Windows™ Active Directory server does not allow anonymous access, set this value to `true`.

If this value is `false`, the Unica Platform connects with the LDAP or Windows™ Active Directory server anonymously. You may set this value to `false` if your LDAP or Windows™ Active Directory server allows anonymous access.

Default value

```
false
```

Valid Values

```
true | false
```

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

Unica Platform user for LDAP credentials

Description

Specifies the name of the Unica user that has been given LDAP administrator login credentials. Set this value if you set the `Use credentials stored in Unica Platform` property in this category to `true`.

Set the value of this property to the user name you created for the Unica user when you configured LDAP integration. This property works in conjunction with the `Data source for LDAP credentials` property in this category.

Default value

`asm_admin`

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

Data source for LDAP credentials

Description

Specifies the Unica Platform data source for LDAP administrator credentials. Set this value if you set the `Use credentials stored in Unica Platform` property in this category to `true`.

Set the value of this property to the data source name you created for the Unica user when you configured LDAP integration. This property works in conjunction with the `Unica Platform user for LDAP credentials` property in this category.

Default value

Undefined

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

Base DN

Description

Specifies the base distinguishing name (DN) pointing to the root of the LDAP directory structure.

Default value

[CHANGE ME]

Valid Values

Any valid DN (see [RFC 1779](#), [RFC 2253](#))

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

Require SSL for LDAP connection

Path

Unica Platform | Security | LDAP

Description

Specifies whether the Unica Platform uses SSL when it connects to the LDAP server to authenticate users. If you set the value to `true`, the connection is secured using SSL.

Default value

`false`

Valid Values

`true` | `false`

Platform | Security | Login method details | Web access control

Properties in this category are used to configure integration with web access control software.

Username pattern

Description

Java™ regular expression used to extract the user login from the HTTP header variable in web access control software. Note that you must XML-escape any XML characters in the regular expression. The recommended value for SiteMinder and IBM Security Access Manager is `\w*`

You should also use this value when you use a custom proxy to integrate Unica Campaign hosted on premises and Digital Analytics in the cloud.

Default value

Undefined

Valid Values

Any Java™ regular expression.

Availability

This property is used only when the Unica Platform is configured to integrate with web access control software.

Web access control header variable

Description

Specifies the HTTP header variable configured in the web access control software, which is submitted to the web application server. By default, SiteMinder uses `sm_user` and IBM Security Access Manager (SAM) uses `iv-user`. For SAM, set this value to the user name component of the Raw string, not the HTTP string.

Default value

Undefined

Valid Values

Any string

Availability

This property is used only when the Unica Platform is configured to integrate with web access control software.

Platform | Security | Login method details | SAML 2.0

Properties in this category configure single sign-on through a SAML 2.0 IdP server.

IdP server URL for single sign-in

Description

The URL of the page that appears when users open the single sign-on URL to Unica.

Default value

[CHANGE ME]

IdP server URL for single sign-out

Description

Optional. When users log out, they can be redirected to the page you set here so that their logout also logs them out of the IdP server. Your IdP server is likely to provide a URL for this purpose.

Default value

[CHANGE ME]

Error page URL for SSO error

Description

If an error occurs during single sign-on due to a configuration or integration issue, users can be redirected to the page specified here. This setting overrides the default error page provided by Unica Platform.

Default value

[CHANGE ME]

Destination URL**Description**

The URL of the service provider (application) to which the user is redirected after successful authentication through the IdP server. This URL appears in every SAML request under the <AuthnRequest Destination> tag.

Default value

[CHANGE ME]

Consumer service URL**Description**

The assertion consumer service URL that the service provider (application) consumes and parses for SAML assertions. This URL appears in every SAML request under the <AuthnRequest AssertionConsumerServiceURL> tag. This value can be the same as the value of the **Destination URL** property.

Default value

[CHANGE ME]

Application ID**Description**

The application ID assigned to Unica Platform in the IdP server. This ID is included in every SAML request to the IdP server. This ID appears in every SAML request under the <Issuer> tag.

Default value

[CHANGE ME]

Service provider name qualifier**Description**

The service provider's name qualifier. This name qualifier appears in every SAML request under the <NameIDPolicy SPNameQualifier> tag.

Default value

[CHANGE ME]

Metadata path

Description

The location of the metadata file on the Unica Platform server.

Default value

[CHANGE ME]

Entity ID

Description

The entity ID of the IdP server. Set this property to the value of *entityID* in the XML declaration at the top of the metadata file produced by the IdP server.

Unica Platform uses this ID during assertion validation to load the IdP configurations and digital certificate.

Default value

[CHANGE ME]

Attributes NVP for response parsing

Description

User account attributes are sent to Unica Platform by the IdP server. You can use this configuration property to capture attributes for users created in Unica Platform automatically, when the **Add authenticated users to Platform** property is enabled.

The IdP server might use a different name for an attribute compared to the name that Unica Platform uses. You can use this property to map the IdP

attribute to the corresponding attribute in Unica Platform. This eliminates the need for code changes.

For example, the IdP server might use **emailAddress** as the name for an attribute that is named **Email** in Unica Platform. You would enter **Email=emailAddress** as a value in this property to map the attribute.

Use the following values for the user attributes in Unica Platform.

- FirstName
- LastName
- Department
- Organization
- Country
- Email
- Address1
- Address2
- Phone1

Use for work phone.

- Phone2

Use for mobile phone.

- Phone3

Use for home phone.

- AltLogin
- ExternalUsersGroup

If you enable the **Add authenticated users to Unica Platform** property, a user authenticated from the IdP server is created in Unica Platform if that user does not already have a Unica Platform account. These users are automatically added to a default user group, **ExternalUsersGroup**. However, you can also specify a custom group to which users are added. If you implement this option, set the value of the

ExternalUsersGroup attribute to the name of the custom user group. For example, if you want a user to be added to a group named MyGroup, you would set this value to `ExternalUserGroup=MyGroup`.

Separate multiple name-value pairs with a semi-colon.

Default value

```
omit-xml-declaration=yes;
```

Process encrypted IdP response

Description

If your IdP server is configured to send encrypted responses, enable this property to indicate that the SAML response from the IdP server must be decrypted using the configured shared key before Unica Platform processes it.

If you enable this property, you must also set the value of **Shared secret key** to the secret key that is used to decrypt the response.

Default value

```
Disabled
```

Shared secret key

Description

When the **Process encrypted IdP response** option is enabled, set this property value to the path of the keystore file.

Default value

```
[CHANGE ME]
```

Key store credential holder

Description

Set this value to the login name of the Unica user account that holds the SAML shared secret in a data source.

Default value

[CHANGE ME]

Key store credential data source**Description**

Set this value to the name of the data source created to hold the shared secret used for decryption. The password in the data source is the password for the key store file.

Default value

[CHANGE ME]

Certificate alias**Description**

When the **Process encrypted IdP response** option is enabled, set this property value to the certificate alias of the private key stored in the keystore file. This is used in decrypting the encrypted SAML response sent by the IDP server.

Default value

[CHANGE ME]

Add authenticated users to Platform**Description**

When this option is enabled, a user authenticated from the IdP server is created in Unica Platform if that user does not already have a Unica Platform account.

Newly created users are automatically added to a default group,

ExternalUsersGroup.

The **ExternalUsersGroup** has only the Unica Platform **UserRole**. An administrator must grant additional permissions for the newly created users to access and use Unica products. An administrator can grant additional

permissions by making users members of groups with different application access levels.

Alternatively, the SAML response can contain a custom user group name, and newly created users are added to this group.

When this option is disabled, a user authenticated from the IdP server can not access Unica Platform, if that user does not have an account in Unica Platform.

Default value

Disabled

Redirect to SSO**Description**

When this value is **True**:

- Users who log in to Unica are redirected to the IdP single sign on page
- After users log in, they go to the standard Unica Platform landing page.
- The standard Unica Platform login screen is never available

Platform | Security | LDAP synchronization

LDAP synchronization properties specify details that the system uses to log into the directory server and identify users to import. Some of these properties also control the frequency and other details of the automatic synchronization process.

LDAP sync enabled**Description**

Set to `true` to enable LDAP or Active Directory synchronization.

Default value

`false`

Valid Values

true | false

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

LDAP sync interval

Description

The Unica Platform synchronizes with the LDAP or Active Directory server at regular intervals, specified in seconds here. If the value is zero or less, the Unica Platform does not synchronize. If the value is a positive integer, the new value takes effect without a restart within ten minutes. Subsequent changes take effect within the configured interval time.

Default value

600, or ten minutes

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

LDAP sync delay

Description

This the time (in 24 hour format) after which the periodic synchronization with the LDAP server begins, after the Unica Platform is started. For example an `LDAP sync delay` of 23:00 and an `LDAP sync interval` of 600 mean that when the Unica Platform starts, the periodic synchronization starts to execute at 11:00 PM and executes every 10 minutes (600 seconds) thereafter.

Default value

23:00, or 11:00pm

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

LDAP sync timeout

Description

The LDAP sync timeout property specifies the maximum length of time, in minutes, after the start of a synchronization before the Unica Platform marks the process ended. The Platform allows only one synchronization process to run at a time. If a synchronization fails, it is marked as ended whether it completed successfully or not.

This is most useful in a clustered environment. For example, if the Unica Platform is deployed in a cluster, one server in the cluster might start an LDAP synchronization and then go down before the process is marked as ended. In that case, the Unica Platform will wait for the amount of time specified in this property, and then it will start the next scheduled synchronization.

Default value

600, (600 minutes, or ten hours)

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

LDAP sync scope

Description

Controls the scope of the initial query to retrieve the set of users. You should retain the default value of `SUBTREE` for synchronizing with most LDAP servers.

Default value

`SUBTREE`

Valid Values

The values are standard LDAP search scope terms.

- **OBJECT** - Search only the entry at the base DN, resulting in only that entry being returned
- **ONE_LEVEL** - Search all entries one level under the base DN, but not including the base DN.
- **SUBTREE** - Search all entries at all levels under and including the specified base DN.

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

LDAP provider URL

Description

For most implementations, set to the LDAP URL of the LDAP or Active Directory server, in one of the following forms:

- `ldap://IP_address:port_number`
- `ldap://machineName.domain.com:port_number`

On LDAP servers, the port number is typically 389 (636 if SSL is used).

If Unica is integrated with an Active Directory server, and your Active Directory implementation uses serverless bind, set the value of this property to the URL for your Active Directory server, using the following form:

```
ldap:///dc=example,dc=com
```

Default value

Undefined

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

Require SSL for LDAP connection

Path

Platform | Security | LDAP synchronization

Description

Specifies whether the Unica Platform uses SSL when it connects to the LDAP server to synchronize users. If you set the value to `true`, the connection is secured using SSL.

Default value

`false`

Valid Values

`true` | `false`

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

LDAP config Unica Platform group delimiter

Description

In the LDAP reference to Unica Platform group map category, if you want to map one LDAP or Active Directory group to multiple Unica Platform groups, use the delimiter specified here. It can be any single character that does not appear in the names it is separating.

Default value

`;` (semicolon)

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

LDAP reference config delimiter

Description

Specifies the delimiter that separates the `SEARCHBASE` and `FILTER` components that make up the LDAP or Active Directory reference (described in the `LDAP references for Unica Platform user creation category`).

`FILTER` is optional: if omitted, the Unica Platform server dynamically creates the filter based on the value of the `LDAP user reference attribute name` property.

Default value

`;` (semicolon)

Valid Values

Any single character that does not appear in the names it is separating.

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

Unica Platform user for LDAP credentials

Description

Specifies the name of Unica user that has been given LDAP administrator login credentials.

Set the value of this property to the user name you created for the Unica user when you configured LDAP integration. This property works in conjunction with the `Data source for LDAP credentials` property in this category.

Default value

`asm_admin`

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

Data source for LDAP credentials

Description

Specifies the Unica Platform data source for LDAP administrator credentials.

Set the value of this property to the data source name you created for the Unica user when you configured LDAP integration. This property works in conjunction with the `Unica Platform user for LDAP credentials` property in this category.

Default value

Undefined

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

LDAP user reference attribute name

Description

For group based import of users, set to the name that your LDAP or Active Directory server uses for the user attribute in the Group object. Typically, this value is `uniquemember` in LDAP servers and `member` in Windows™ Active Directory servers.

For attribute based import of users, set this property to `DN`, and when you configure the **LDAP reference map** property, set the `FILTER` portion of the value to the string your LDAP server uses for the attribute on which you want to search.

Default value

`member`

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

LDAP BaseDN periodic search disabled

Description

When this property is set to `True`, the Unica Platform performs the LDAP synchronization search using the distinguished name set in the `Base DN` property under the **Unica Platform | Security | LDAP** category. If this property is set to `False`, the Unica Platform performs the LDAP synchronization search using the groups mapped to LDAP groups under **LDAP reference to Unica Platform group map**.

The following table describes whether changes are picked up in periodic synchronization, depending on the value set for this property.

Table 77. Effect of this property on periodic synchronization behavior

Change	Is the change picked up when the value is set to <code>True</code> ?	Is the change picked up when the value is set to <code>False</code> ?
In Unica Platform, delete a user synchronized from the LDAP server	Yes	No
Remove a user from an LDAP group mapped to a Unica Platform group	No	No
In Unica Platform, remove a user from a Unica Platform group mapped to an LDAP group.	No	No
Add a new user to the LDAP server	Yes	Yes
Add a user to an LDAP group mapped to a Unica Platform group	Yes	No

Table 77. Effect of this property on periodic synchronization behavior (continued)

Change	Is the change picked up when the value is set to True?	Is the change picked up when the value is set to False?
Change user attributes on the LDAP server	Yes	Yes

Default value

False

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

User login

Description

Maps the Unica user's login to the equivalent user attribute in your LDAP or Active Directory server. `User login` is the only required mapping. Typically, the value for this attribute is `uid` for LDAP servers and `sAMAccountName` for Windows™ Active Directory servers. You should verify this on your LDAP or Active Directory server.

Default value

`uid`

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

First name

Description

Maps the First Name user attribute in the Unica Platform to the equivalent user attribute in your LDAP or Active Directory server.

Default value

`givenName`

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

Last name

Description

Maps the Last Name user attribute in the Unica Platform to the equivalent user attribute in your LDAP or Active Directory server.

Default value

`sn`

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

User title

Description

Maps the Title user attribute in the Unica Platform to the equivalent user attribute in your LDAP or Active Directory server.

Default value

`title`

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

Department

Description

Maps the Department user attribute in the Unica Platform to the equivalent user attribute in your LDAP or Active Directory server.

Default value

Undefined

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

Company

Description

Maps the Company user attribute in the Unica Platform to the equivalent user attribute in your LDAP or Active Directory server.

Default value

Undefined

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

Country

Description

Maps the Country user attribute in the Unica Platform to the equivalent user attribute in your LDAP or Active Directory server.

Default value

Undefined

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

User email**Description**

Maps the Email Address attribute in the Unica Platform to the equivalent user attribute in your LDAP or Active Directory server.

Default value

mail

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

Address 1**Description**

Maps the Address user attribute in the Unica Platform to the equivalent user attribute in your LDAP or Active Directory server.

Default value

Undefined

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

Work phone**Description**

Maps the Work Phone user attribute in the Unica Platform to the equivalent user attribute in your LDAP or Active Directory server.

Default value

telephoneNumber

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

Mobile phone

Description

Maps the Mobile Phone user attribute in the Unica Platform to the equivalent user attribute in your LDAP or Active Directory server.

Default value

Undefined

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

Home phone

Description

Maps the Home Phone user attribute in the Unica Platform to the equivalent user attribute in your LDAP or Active Directory server.

Default value

Undefined

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

Alternate login

Description

Maps the Alternate Login user attribute in the Unica Platform to the equivalent user attribute in your LDAP or Active Directory server.

Default value

Undefined

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

Platform | Security | LDAP synchronization | LDAP reference to Unica Platform group map

Properties in this category are used to configure LDAP integration.

LDAP reference map**Description**

Users who are members of the LDAP or Active Directory group specified here are imported to the Unica Platform group specified in the `Unica Platform group` property.

Set the value of this property using the following syntax: `SEARCHBASE`

`DELIMITER FILTER` where:

`SEARCHBASE` is the Distinguished Name (DN) of the object.

`DELIMITER` is the value of the `LDAP config AM group delimiter` property.

`FILTER` is the LDAP or Active Directory attribute filter. `FILTER` is optional when you use group based import: if omitted, the Unica Platform server dynamically creates the filter based on the value of the `LDAP user reference attribute name` property.

If you use attribute based import, set the value of `FILTER` to the string your LDAP server uses for the attribute on which you want to search. Also, you must set value of the **LDAP user reference attribute name** property to `DN`.

Default value

Undefined

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

Unica Platform group

Description

Users who are members of the LDAP or Active Directory group specified in the `LDAP reference group` property are imported to the Unica Platform group specified here.

Default value

Undefined

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

Platform | Security | Federated authentication

The properties in this category are used in implementing SAML (Security Assertion Markup Language) 2.0 based federated authentication, which enables single sign-on among diverse applications.

Allow federated login

Description

Select the check box in this property to enable federated authentication in an integrated environment.

Default value

Disabled

Identity provider URL

Description

The URL of the identity provider server.

Certificate issuer

Description

The URL of the Certificate Authority that issued the certificate on the identity provider server. If you generate your own certificates using the Java™ keytool utility, set this value to the IdP server URL.

Platform | Security | Federated authentication | partitions | partition[n]

The properties in this category are used in implementing SAML (Security Assertion Markup Language) 2.0 based federated authentication between Unica applications and other and third party applications.

Keystore path

Description

The location of the trusted keystore file in the web application server.

Keystore passkey

Description

The passkey for the keystore in the web application server.

Keystore alias

Description

The alias for the keystore in the web application server.

Unica Platform | Security | API management

Properties in this category configure authentication behavior that applies to all Unica APIs.

Enable session-based API authentication

Description

If you select the check box for this property to enable it, users who are authenticated by logging in to Unica are not asked to log in again when they access a secure API from an Unica application during the session for which they are authenticated.

For example, when this property is enabled, and an authenticated Unica Interact user calls a Unica Campaign API during their session, no further login is required.

Default value

Disabled

Delete security token after a single use**Description**

If you select the check box for this property to enable it, the token generated for an authenticated user is destroyed the first time this token is used for accessing any secure API. This enhances security by preventing any further use of the token.

Default value

Enabled

Platform | Security | API management | [Product] | (API configuration template)

Use the templates in this category to configure authentication for Unica APIs. You can block access, require HTTPS, or require authentication for APIs.

API URI**Description**

For each product, the first part of the URI is resolved by the security framework, as follows: `http[s]://host:port/context root/api/product`

Therefore, in this field you should enter only the resource name or names of the API you want to configure. You can obtain the string you need to enter from the product's API documentation.

The value used for this property must start with a / (forward slash); otherwise the configuration is ignored by the security framework.

This property supports an exact URL match as well a pattern match for the configured APIs.

- For an exact match, the URI may end with a forward slash (/) or the resource name.
- For a pattern match, the URI must end with an asterisk (*).

If you set the value of this property to `/*` the settings you use for the other properties in the category apply to all APIs for the product.



Note: For the Unica Platform `login` API, this configuration property is read-only.

Default value

Undefined

Block API access

Description

Select this option when you want to prevent an API from accessing a product. This option is not selected by default.

When an API is blocked, the security filter returns the HTTP status code 403 (forbidden).

Secure API access over HTTPS

Description

Select this option when you want to allow the API to access a product only over HTTPS. This option is selected by default.

When an API with this property enabled is accessed over HTTP rather than HTTPS, the security filter returns the HTTP status code 403 (forbidden).

Require authentication for API access

Description

Select this option when you want to require an API to authenticate before it can access a product. This option is selected by default.

When an API with this property enabled is accessed with invalid credentials, the security filter returns the HTTP status code 401 (unauthorized).



Note: For the Unica Platform `login` API, this configuration property is disabled, as this API is the first to be called for API authentication.

Unica Platform | Security | API management | [Product] | Unica Platform | Authentication

(Affinium|suite|security|apiSecurity|manager|managerAuthentication)Use the templates in this category to configure authentication for Unica APIs. You can block access, require HTTPS, or require authentication for APIs.

API URI

Description

For each product, the first part of the URI is resolved by the security framework, as follows: `http[s]://host:port/context root/api/product`

Therefore, in this field you should enter only the resource name or names of the API you want to configure. You can obtain the string you need to enter from the product's API documentation.

The value used for this property must start with a / (forward slash); otherwise the configuration is ignored by the security framework.

This property supports an exact URL match as well a pattern match for the configured APIs.

- For an exact match, the URI may end with a forward slash (/) or the resource name.
- For a pattern match, the URI must end with an asterisk (*).

If you set the value of this property to `/*` the settings you use for the other properties in the category apply to all APIs for the product.



Note: For the Unica Platform `login` API, this configuration property is read-only.

Default value

`/authentication/login`

Block API access

Description

Select this option when you want to prevent an API from accessing a product. This option is not selected by default.

When an API is blocked, the security filter returns the HTTP status code 403 (forbidden).

Default value

(Disabled)

Secure API access over HTTPS

Description

Select this option when you want to allow the API to access a product only over HTTPS. This option is selected by default.

When an API with this property enabled is accessed over HTTP rather than HTTPS, the security filter returns the HTTP status code 403 (forbidden).

Default value

(Enabled)

Require authentication for API access**Description**

Select this option when you want to require an API to authenticate before it can access a product. This option is selected by default.

When an API with this property enabled is accessed with invalid credentials, the security filter returns the HTTP status code 401 (unauthorized).



Note: For the Unica Platform `login` API, this configuration property is disabled, as this API is the first to be called for API authentication.

Default value

(Disabled)

Related information

[Security framework for Unica APIs \(on page 237\)](#)

Unica Platform | Security | API management | [Product] | Unica Platform | User

(Affinium|suite|security|apiSecurity|manager|managerUser)Use the templates in this category to configure authentication for Unica APIs. You can block access, require HTTPS, or require authentication for APIs.

API URI**Description**

For each product, the first part of the URI is resolved by the security framework, as follows: `http[s]://host:port/context root/api/product`

Therefore, in this field you should enter only the resource name or names of the API you want to configure. You can obtain the string you need to enter from the product's API documentation.

The value used for this property must start with a / (forward slash); otherwise the configuration is ignored by the security framework.

This property supports an exact URL match as well a pattern match for the configured APIs.

- For an exact match, the URI may end with a forward slash (/) or the resource name.
- For a pattern match, the URI must end with an asterisk (*).

If you set the value of this property to `/*` the settings you use for the other properties in the category apply to all APIs for the product.



Note: For the Unica Platform `login` API, this configuration property is read-only.

Default value

`/user/partitions/*`

Block API access

Description

Select this option when you want to prevent an API from accessing a product. This option is not selected by default.

When an API is blocked, the security filter returns the HTTP status code 403 (forbidden).

Default value

(Disabled)

Secure API access over HTTPS

Description

Select this option when you want to allow the API to access a product only over HTTPS. This option is selected by default.

When an API with this property enabled is accessed over HTTP rather than HTTPS, the security filter returns the HTTP status code 403 (forbidden).

Default value

(Disabled)

Require authentication for API access

Description

Select this option when you want to require an API to authenticate before it can access a product. This option is selected by default.

When an API with this property enabled is accessed with invalid credentials, the security filter returns the HTTP status code 401 (unauthorized).



Note: For the Unica Platform `login` API, this configuration property is disabled, as this API is the first to be called for API authentication.

Default value

(Enabled)

Related information

[Security framework for Unica APIs \(on page 237\)](#)

Unica Platform | Security | API management | [Product] | Unica Platform | Policy

(Affinium|suite|security|apiSecurity|manager|managerPolicy) Use the templates in this category to configure authentication for Unica APIs. You can block access, require HTTPS, or require authentication for APIs.

API URI

Description

For each product, the first part of the URI is resolved by the security framework, as follows: `http[s]://host:port/context root/api/product`

Therefore, in this field you should enter only the resource name or names of the API you want to configure. You can obtain the string you need to enter from the product's API documentation.

The value used for this property must start with a / (forward slash); otherwise the configuration is ignored by the security framework.

This property supports an exact URL match as well a pattern match for the configured APIs.

- For an exact match, the URI may end with a forward slash (/) or the resource name.
- For a pattern match, the URI must end with an asterisk (*).

If you set the value of this property to `/*` the settings you use for the other properties in the category apply to all APIs for the product.



Note: For the Unica Platform `login` API, this configuration property is read-only.

Default value

`/policy/partitions/*`

Block API access

Description

Select this option when you want to prevent an API from accessing a product. This option is not selected by default.

When an API is blocked, the security filter returns the HTTP status code 403 (forbidden).

Default value

(Disabled)

Secure API access over HTTPS

Description

Select this option when you want to allow the API to access a product only over HTTPS. This option is selected by default.

When an API with this property enabled is accessed over HTTP rather than HTTPS, the security filter returns the HTTP status code 403 (forbidden).

Default value

(Disabled)

Require authentication for API access

Description

Select this option when you want to require an API to authenticate before it can access a product. This option is selected by default.

When an API with this property enabled is accessed with invalid credentials, the security filter returns the HTTP status code 401 (unauthorized).



Note: For the Unica Platform `login` API, this configuration property is disabled, as this API is the first to be called for API authentication.

Default value

(Enabled)

Related information

[Security framework for Unica APIs \(on page 237\)](#)

Unica Platform | Security | API management | [Product] | Unica Platform | Configuration

(Affinium|suite|security|apiSecurity|manager|managerConfiguration) Use the templates in this category to configure authentication for Unica APIs. You can block access, require HTTPS, or require authentication for APIs.

API URI

Description

For each product, the first part of the URI is resolved by the security framework, as follows: `http[s]://host:port/context root/api/product`

Therefore, in this field you should enter only the resource name or names of the API you want to configure. You can obtain the string you need to enter from the product's API documentation.

The value used for this property must start with a / (forward slash); otherwise the configuration is ignored by the security framework.

This property supports an exact URL match as well a pattern match for the configured APIs.

- For an exact match, the URI may end with a forward slash (/) or the resource name.
- For a pattern match, the URI must end with an asterisk (*).

If you set the value of this property to `/ *` the settings you use for the other properties in the category apply to all APIs for the product.



Note: For the Unica Platform `login` API, this configuration property is read-only.

Default value

`/datasource/config`

Block API access

Description

Select this option when you want to prevent an API from accessing a product. This option is not selected by default.

When an API is blocked, the security filter returns the HTTP status code 403 (forbidden).

Default value

(Disabled)

Secure API access over HTTPS

Description

Select this option when you want to allow the API to access a product only over HTTPS. This option is selected by default.

When an API with this property enabled is accessed over HTTP rather than HTTPS, the security filter returns the HTTP status code 403 (forbidden).

Default value

(Disabled)

Require authentication for API access

Description

Select this option when you want to require an API to authenticate before it can access a product. This option is selected by default.

When an API with this property enabled is accessed with invalid credentials, the security filter returns the HTTP status code 401 (unauthorized).



Note: For the Unica Platform `login` API, this configuration property is disabled, as this API is the first to be called for API authentication.

Default value

(Enabled)

Related information

[Security framework for Unica APIs \(on page 237\)](#)

Unica Platform | Security | API management | [Product] | Unica Platform | Datasource

(Affinium|suite|security|apiSecurity|manager|managerDatasource)Use the templates in this category to configure authentication for Unica APIs. You can block access, require HTTPS, or require authentication for APIs.

API URI

Description

For each product, the first part of the URI is resolved by the security framework, as follows: `http[s]://host:port/context root/api/product`

Therefore, in this field you should enter only the resource name or names of the API you want to configure. You can obtain the string you need to enter from the product's API documentation.

The value used for this property must start with a / (forward slash); otherwise the configuration is ignored by the security framework.

This property supports an exact URL match as well a pattern match for the configured APIs.

- For an exact match, the URI may end with a forward slash (/) or the resource name.
- For a pattern match, the URI must end with an asterisk (*).

If you set the value of this property to `/*` the settings you use for the other properties in the category apply to all APIs for the product.



Note: For the Unica Platform `login` API, this configuration property is read-only.

Default value

`/datasource`

Block API access

Description

Select this option when you want to prevent an API from accessing a product. This option is not selected by default.

When an API is blocked, the security filter returns the HTTP status code 403 (forbidden).

Default value

(Disabled)

Secure API access over HTTPS

Description

Select this option when you want to allow the API to access a product only over HTTPS. This option is selected by default.

When an API with this property enabled is accessed over HTTP rather than HTTPS, the security filter returns the HTTP status code 403 (forbidden).

Default value

(Disabled)

Require authentication for API access

Description

Select this option when you want to require an API to authenticate before it can access a product. This option is selected by default.

When an API with this property enabled is accessed with invalid credentials, the security filter returns the HTTP status code 401 (unauthorized).



Note: For the Unica Platform `login` API, this configuration property is disabled, as this API is the first to be called for API authentication.

Default value

(Enabled)

Related information

[Security framework for Unica APIs \(on page 237\)](#)

Unica Platform | Security | API management | [Product] | Unica Platform | Login

(Affinium|suite|security|apiSecurity|manager|managerLogin)Use the templates in this category to configure authentication for Unica APIs. You can block access, require HTTPS, or require authentication for APIs.

API URI

Description

For each product, the first part of the URI is resolved by the security framework, as follows: `http[s]://host:port/context root/api/product`

Therefore, in this field you should enter only the resource name or names of the API you want to configure. You can obtain the string you need to enter from the product's API documentation.

The value used for this property must start with a / (forward slash); otherwise the configuration is ignored by the security framework.

This property supports an exact URL match as well a pattern match for the configured APIs.

- For an exact match, the URI may end with a forward slash (/) or the resource name.
- For a pattern match, the URI must end with an asterisk (*).

If you set the value of this property to /* the settings you use for the other properties in the category apply to all APIs for the product.



Note: For the Unica Platform `login` API, this configuration property is read-only.

Default value

/authentication/v1/login

Block API access

Description

Select this option when you want to prevent an API from accessing a product. This option is not selected by default.

When an API is blocked, the security filter returns the HTTP status code 403 (forbidden).

Default value

(Disabled)

Secure API access over HTTPS

Description

Select this option when you want to allow the API to access a product only over HTTPS. This option is selected by default.

When an API with this property enabled is accessed over HTTP rather than HTTPS, the security filter returns the HTTP status code 403 (forbidden).

Default value

(Disabled)

Require authentication for API access**Description**

Select this option when you want to require an API to authenticate before it can access a product. This option is selected by default.

When an API with this property enabled is accessed with invalid credentials, the security filter returns the HTTP status code 401 (unauthorized).



Note: For the Unica Platform `login` API, this configuration property is disabled, as this API is the first to be called for API authentication.

Default value

(Disabled)

Related information

[Security framework for Unica APIs \(on page 237\)](#)

Unica Platform | Security | API management | [Product] | Unica Marketing Campaign | Interact Collection

(Affinium|suite|security|apiSecurity|campaign|Interact Collection)Use the templates in this category to configure authentication for Unica APIs. You can block access, require HTTPS, or require authentication for APIs.

API URI**Description**

For each product, the first part of the URI is resolved by the security framework, as follows: `http[s]://host:port/context root/api/product`

Therefore, in this field you should enter only the resource name or names of the API you want to configure. You can obtain the string you need to enter from the product's API documentation.

The value used for this property must start with a / (forward slash); otherwise the configuration is ignored by the security framework.

This property supports an exact URL match as well a pattern match for the configured APIs.

- For an exact match, the URI may end with a forward slash (/) or the resource name.
- For a pattern match, the URI must end with an asterisk (*).

If you set the value of this property to `/*` the settings you use for the other properties in the category apply to all APIs for the product.



Note: For the Unica Platform `login` API, this configuration property is read-only.

Default value

`/rest/v1/interactCollection/*`

Block API access

Description

Select this option when you want to prevent an API from accessing a product. This option is not selected by default.

When an API is blocked, the security filter returns the HTTP status code 403 (forbidden).

Default value

(Disabled)

Secure API access over HTTPS

Description

Select this option when you want to allow the API to access a product only over HTTPS. This option is selected by default.

When an API with this property enabled is accessed over HTTP rather than HTTPS, the security filter returns the HTTP status code 403 (forbidden).

Default value

(Disabled)

Require authentication for API access

Description

Select this option when you want to require an API to authenticate before it can access a product. This option is selected by default.

When an API with this property enabled is accessed with invalid credentials, the security filter returns the HTTP status code 401 (unauthorized).



Note: For the Unica Platform `login` API, this configuration property is disabled, as this API is the first to be called for API authentication.

Default value

(Disabled)

Related information

[Security framework for Unica APIs \(on page 237\)](#)

Unica Platform | Security | API management | [Product] | Unica Marketing Campaign | Triggered Messages

(Affinium|suite|security|apiSecurity|campaign|Interact Collection)Use the templates in this category to configure authentication for Unica APIs. You can block access, require HTTPS, or require authentication for APIs.

API URI

Description

For each product, the first part of the URI is resolved by the security framework, as follows: `http[s]://host:port/context root/api/product`

Therefore, in this field you should enter only the resource name or names of the API you want to configure. You can obtain the string you need to enter from the product's API documentation.

The value used for this property must start with a / (forward slash); otherwise the configuration is ignored by the security framework.

This property supports an exact URL match as well a pattern match for the configured APIs.

- For an exact match, the URI may end with a forward slash (/) or the resource name.
- For a pattern match, the URI must end with an asterisk (*).

If you set the value of this property to `/*` the settings you use for the other properties in the category apply to all APIs for the product.



Note: For the Unica Platform `login` API, this configuration property is read-only.

Default value

`/rest/v1/triggeredMessages/*`

Block API access

Description

Select this option when you want to prevent an API from accessing a product. This option is not selected by default.

When an API is blocked, the security filter returns the HTTP status code 403 (forbidden).

Default value

(Disabled)

Secure API access over HTTPS

Description

Select this option when you want to allow the API to access a product only over HTTPS. This option is selected by default.

When an API with this property enabled is accessed over HTTP rather than HTTPS, the security filter returns the HTTP status code 403 (forbidden).

Default value

(Disabled)

Require authentication for API access

Description

Select this option when you want to require an API to authenticate before it can access a product. This option is selected by default.

When an API with this property enabled is accessed with invalid credentials, the security filter returns the HTTP status code 401 (unauthorized).



Note: For the Unica Platform `login` API, this configuration property is disabled, as this API is the first to be called for API authentication.

Default value

(Disabled)

Related information

[Security framework for Unica APIs \(on page 237\)](#)

Unica Platform | Security | API management | [Product] | Unica Marketing Campaign | Campaign REST API Filter

(Affinium|suite|security|apiSecurity|campaign|Campaign REST API Filter)Use the templates in this category to configure authentication for Unica APIs. You can block access, require HTTPS, or require authentication for APIs.

API URI

Description

For each product, the first part of the URI is resolved by the security framework, as follows: `http[s]://host:port/context root/api/product`

Therefore, in this field you should enter only the resource name or names of the API you want to configure. You can obtain the string you need to enter from the product's API documentation.

The value used for this property must start with a / (forward slash); otherwise the configuration is ignored by the security framework.

This property supports an exact URL match as well a pattern match for the configured APIs.

- For an exact match, the URI may end with a forward slash (/) or the resource name.
- For a pattern match, the URI must end with an asterisk (*).

If you set the value of this property to `/ *` the settings you use for the other properties in the category apply to all APIs for the product.



Note: For the Unica Platform `login` API, this configuration property is read-only.

Default value

`/rest/v1/*`

Block API access

Description

Select this option when you want to prevent an API from accessing a product. This option is not selected by default.

When an API is blocked, the security filter returns the HTTP status code 403 (forbidden).

Default value

(Disabled)

Secure API access over HTTPS

Description

Select this option when you want to allow the API to access a product only over HTTPS. This option is selected by default.

When an API with this property enabled is accessed over HTTP rather than HTTPS, the security filter returns the HTTP status code 403 (forbidden).

Default value

(Disabled)

Require authentication for API access

Description

Select this option when you want to require an API to authenticate before it can access a product. This option is selected by default.

When an API with this property enabled is accessed with invalid credentials, the security filter returns the HTTP status code 401 (unauthorized).



Note: For the Unica Platform `login` API, this configuration property is disabled, as this API is the first to be called for API authentication.

Default value

(Enabled)

Related information

[Security framework for Unica APIs \(on page 237\)](#)

Unica Platform | Security | API management | [Product] | Unica Marketing Campaign | Engage REST API Filter

(Affinium|suite|security|apiSecurity|campaign|Engage REST API Filter)Use the templates in this category to configure authentication for Unica APIs. You can block access, require HTTPS, or require authentication for APIs.

API URI

Description

For each product, the first part of the URI is resolved by the security framework, as follows: `http[s]://host:port/context root/api/product`

Therefore, in this field you should enter only the resource name or names of the API you want to configure. You can obtain the string you need to enter from the product's API documentation.

The value used for this property must start with a / (forward slash); otherwise the configuration is ignored by the security framework.

This property supports an exact URL match as well a pattern match for the configured APIs.

- For an exact match, the URI may end with a forward slash (/) or the resource name.
- For a pattern match, the URI must end with an asterisk (*).

If you set the value of this property to `/*` the settings you use for the other properties in the category apply to all APIs for the product.



Note: For the Unica Platform `login` API, this configuration property is read-only.

Default value

`/rest/engage/*`

Block API access

Description

Select this option when you want to prevent an API from accessing a product. This option is not selected by default.

When an API is blocked, the security filter returns the HTTP status code 403 (forbidden).

Default value

(Disabled)

Secure API access over HTTPS

Description

Select this option when you want to allow the API to access a product only over HTTPS. This option is selected by default.

When an API with this property enabled is accessed over HTTP rather than HTTPS, the security filter returns the HTTP status code 403 (forbidden).

Default value

(Disabled)

Require authentication for API access

Description

Select this option when you want to require an API to authenticate before it can access a product. This option is selected by default.

When an API with this property enabled is accessed with invalid credentials, the security filter returns the HTTP status code 401 (unauthorized).



Note: For the Unica Platform `login` API, this configuration property is disabled, as this API is the first to be called for API authentication.

Default value

(Disabled)

Related information

[Security framework for Unica APIs \(on page 237\)](#)

Unica Platform | Security | API management | [Product] | Unica Marketing Campaign | Campaign REST API V2 Filter

(Affinium|suite|security|apiSecurity|campaign|Campaign REST API V2 Filter)Use the templates in this category to configure authentication for Unica APIs. You can block access, require HTTPS, or require authentication for APIs.

API URI

Description

For each product, the first part of the URI is resolved by the security framework, as follows: `http[s]://host:port/context root/api/product`

Therefore, in this field you should enter only the resource name or names of the API you want to configure. You can obtain the string you need to enter from the product's API documentation.

The value used for this property must start with a / (forward slash); otherwise the configuration is ignored by the security framework.

This property supports an exact URL match as well a pattern match for the configured APIs.

- For an exact match, the URI may end with a forward slash (/) or the resource name.
- For a pattern match, the URI must end with an asterisk (*).

If you set the value of this property to /* the settings you use for the other properties in the category apply to all APIs for the product.



Note: For the Unica Platform `login` API, this configuration property is read-only.

Default value

`/rest/v2/*`

Block API access

Description

Select this option when you want to prevent an API from accessing a product. This option is not selected by default.

When an API is blocked, the security filter returns the HTTP status code 403 (forbidden).

Default value

(Disabled)

Secure API access over HTTPS

Description

Select this option when you want to allow the API to access a product only over HTTPS. This option is selected by default.

When an API with this property enabled is accessed over HTTP rather than HTTPS, the security filter returns the HTTP status code 403 (forbidden).

Default value

(Disabled)

Require authentication for API access

Description

Select this option when you want to require an API to authenticate before it can access a product. This option is selected by default.

When an API with this property enabled is accessed with invalid credentials, the security filter returns the HTTP status code 401 (unauthorized).



Note: For the Unica Platform `login` API, this configuration property is disabled, as this API is the first to be called for API authentication.

Default value

(Enabled)

Related information

[Security framework for Unica APIs \(on page 237\)](#)

Platform | Security | JWT authentication

JWT authentication is used for Journey Designer+Unica Campaign. JWT authentication allows single sign-on between applications.

Enable JWT authentication

Description

When the check box for this property is selected, JWT authentication is enabled.

This property applies only in environments where Journey Designer is integrated with Unica Campaign.

Default value

disabled

JWT service URL

Description

The URL of the JWT service. This value differs, depending on whether you have applied Unica Platform FixPack 10.0.0.1. Refer to the following examples.

- If you have **not** applied FixPack 10.0.0.1:

```
http://IP_ADDRESS/jwt/api/v1/tokens
```

- If you have applied FixPack 10.0.0.1:

```
http://IP_ADDRESS/api/v1/keys
```

This property applies only in environments where Journey Designer is integrated with Unica Campaign.

JWT shared secret

Description

The shared secret key that is sent from Unica Platform to the JWT service for authentication. This key is shared between Unica Platform and Journey Designer. The JWT issuer is mapped to the JWT shared secret within the JWT service.

This property applies only in environments where Journey Designer is integrated with Unica Campaign, and where Unica Platform is version 10.0.0.0 (that is where Unica Platform FixPack 10.0.0.1 is **not** applied).

JWT issuer

Description

The issuer name and version that is sent from Unica Platform to the JWT service for authentication.

This property applies only in environments where Journey Designer is integrated with Unica Campaign.

Platform | Notifications

Properties in this category control system behavior for notifications that Unica products can send to users.

How many days to retain alerts

Description

Specifies the amount of time, in days, that a system alert is retained in the system for historical purpose after the expiry date, which is provided by the application that sent the alert. Alerts older than the specified number of days are deleted from the system.

Default value

90

How frequently to send emails (in minutes)

Description

Specifies how many minutes the system waits before sending any new notification emails.

Default value

30

Maximum re-tries for sending email

Description

Specifies how many times the system attempts to send notification emails when an initial attempt to send fails.

Default value

1

Platform | Audit Events

The property on this page determines whether audit events are tracked.

Is event auditing enabled?

Description

Specifies whether the audit events are tracked.

Default value

False

Valid values

True | False

Platform | Audit Events | Audit events configuration

The events you select on this page are available in the security audit reports.

Record login and logout events for all accounts

Description

Specifies whether to track the user name and the date and time for log in and log out events for all user accounts.

Record when user sessions time out for all accounts

Description

Specifies whether to track the account user name and the date and time of sessions that are automatically timed out.

Record login and logout events for members of the HighSeverityAccounts group

Description

Specifies whether to track the user name and the date and time for log in and log out events for accounts that are members of the **highSeverityAccounts** group in Unica Platform. To enable this feature, you must set a severity level for this configuration property and add users to the highSeverityAccounts group.

Record LDAP group membership changes

Description

Specifies whether to record the addition or deletion of accounts, along with the user names and dates and times of these actions, for user accounts synchronized from an LDAP server. This property applies only when Unica Platform is integrated with a supported LDAP server, such IBM Security Directory server or Windows™ Active Directory.

Record when accounts are enabled and disabled

Description

Specifies whether to record the account user name and the date and time when user accounts are enabled or disabled.

Record when account passwords change

Description

Specifies whether to record the account user name and the date and time when user passwords change.

Record when account passwords are locked

Description

Specifies whether to record the account user name and the date and time when a password is locked out due to too many incorrect login attempts.

Record when groups are created or deleted in Platform

Description

Specifies whether to record when groups are added or deleted.

Record Platform group membership changes

Description

Specifies whether to record when user accounts are added to or removed from a group.

Record Platform group permission changes

Description

Specifies whether to record changes to group permissions.

Record role creation or deletion

Description

Specifies whether to record when roles are added or deleted. Only roles that are shown on the **Settings > User roles and permissions** page are tracked.

Record role membership changes

Description

Specifies whether to record changes in role membership. Only roles that are shown on the **Settings > User roles and permissions** page are tracked.

Record role permission changes

Description

Specifies whether to record changes in role permissions. Only roles that are shown on the **Settings > User roles and permissions** page are tracked.

Record changes to properties on the configuration page

Description

Specifies whether to record changes in configuration properties on the **Settings > Configuration** page. Changes made by users on the Configuration

page, or by users running the `configTool` are tracked. Configuration changes made by the installers during installation or upgrade are not tracked.

Enable audit backup

Description

Specifies whether to save audit data to the `USM_AUDIT_BACKUP` table.



Important: Because this is a bootstrap property that is read when the Unica Platform web application starts, you must stop and restart the Unica Platform web application when you change this property value.

Default value

False

Valid values

True | False

Archive data after the number of days specified here

Description

Specifies the interval, in days, between audit backups. The archived data is stored in the `USM_AUDIT_BACKUP` table and can be included in the Audit Events report when you set a custom date range that includes data from the archive.



Important: Because this is a bootstrap property that is read when the Unica Platform web application starts, you must stop and restart the Unica Platform web application when you change this property value.

Keep Audit records in primary for number days specified here

Description

Specifies how many days of data to keep in the `USM_AUDIT` table for the Audit Events report. When the default settings for the Audit Events report are in effect, only the data in the `USM_AUDIT` table is shown in the report.

 **Important:** Because this is a bootstrap property that is read when the Unica Platform web application starts, you must stop and restart the Unica Platform web application when you change this property value.

Archive start time

Description

Specifies the time of day when the system moves audit data into an archive. Use the 24 hour format for this value.

 **Important:** Because this is a bootstrap property that is read when the Unica Platform web application starts, you must stop and restart the Unica Platform web application when you change this property value.

Name of group to receive audit backup notifications

Description

Specifies the Unica group whose members should receive notification of archive backups. You can specify only one group for this property. Users in this group can manage their subscription to this notification by going to their **Settings > Users** page and clicking **Notification subscriptions**.

Platform | Audit Events | Audit events severity configuration

The severity level you specify for each event on this page appears in the Audit Events report. You can use the severity level to sort and filter the report data. The events are identical to those in the **Platform | Audit Events | Audit events configuration** category.

Digital Analytics configuration properties

This section describes the Digital Analytics configuration properties on the Configuration page.

These configuration properties are used in configuring single sign-on between Digital Analytics and Unica. See the Unica Platform Administrator's Guide for details about this integration.

Digital Analytics®

The property in this category is part of the configuration for enabling single sign-on between Digital Analytics and Unica.

Enable Coremetrics® Analytics

Description

This is part of the configuration for enabling single sign-on between Digital Analytics and Unica.

Set to `true` as one of the steps for enabling single sign-on.

See the Unica Platform Administrator's Guide for details about this integration.

Default value

`false`

Digital Analytics® | Integration | partitions | partition[n]

Properties in this category are part of the configuration for enabling single sign-on between Digital Analytics and Unica.

Platform user for Coremetrics® account

Description

Specifies the login name of the Unica user account that holds the Digital Analytics shared secret in a data source.

This is part of the configuration for enabling single sign-on between Digital Analytics and Unica. See the Unica Platform Administrator's Guide for details about this integration.

Default value

`asm_admin`

Datasource for Coremetrics® account**Description**

Specifies the name of the data source created to hold the Digital Analytics shared secret.

This is part of the configuration for enabling single sign-on between Digital Analytics and Unica. See the Unica Platform Administrator's Guide for details about this integration.

Default value

`CoremetricsDS`

Report configuration properties

The report configuration properties for Unica are at **Settings > Configuration > Reports**.

To generate reports, the Unica suite integrates with Cognos®, a business intelligence application. You use the **Integrations > Cognos** properties to identify your Cognos® system. Then, for Unica Campaign, IBM eMessage, and Unica Interact, you must configure additional properties to set up and customize the reporting schemas.

Reports | Integrations | Cognos [version]

The Unica suite integrates with Cognos to generate reports.

This page displays properties that specify URLs and other parameters that are used by the system.

Integration Name

Description

Read-only. Specifies that IBM Cognos is the third-party reporting or analytical tool that is used by the Unica to display the reports.

Default value

Cognos

Vendor

Description

Read-only. Specifies that IBM Cognos is the name of the company that provides the application that is specified by the Integration Name property.

Default value

Cognos

Version

Description

Read-only. Specifies the product version of the application that is specified by the Integration Name property.

Default value

<version>

Enabled

Description

Specifies whether IBM Cognos is enabled for the suite.

Default value

False

Valid Values

True | False

Integration Class Name

Description

Read-only. Specifies the fully qualified name of the Java class that creates the integration interface that is used to connect to the application specified by the `Integration Name` property.

Default value

```
com.unica.report.integration.cognos.CognosIntegration
```

Domain

Description

Specifies the fully qualified company domain name in which your Cognos server is running. For example, `myCompanyDomain.com`.

If your company uses subdomains, the value in this field must include the appropriate subdomain as well.

Default value

```
[CHANGE ME]
```

Valid Values

A string no longer than 1024 characters.

Portal URL

Description

Specifies the URL of the IBM Cognos Connection portal. Use a fully qualified host name, including the domain name (and subdomain, if appropriate) that is specified in the **Domain** property. For example: `http://MyReportServer.MyCompanyDomain.com/cognos<version>/cgi-bin/cognos.cgi`

You can find the URL in IBM Cognos Configuration at: **Local Configuration > Environment** .

Default value

```
http://[CHANGE ME]/cognos<version>/cgi-bin/cognos.cgi
```

Valid Values

A well-formed URL.

Dispatch URL

Description

Specifies the URL of the IBM Cognos Content Manager. Use a fully qualified host name, including the domain name (and subdomain, if appropriate) specified in the `Domain` property. For example: `http://MyReportServer.MyCompanyDomain.com:9300/p2pd/servlet/dispatch`

You can find the URL in Cognos® Configuration at: **Local Configuration > Environment** .

Default value

```
http://[CHANGE ME]:9300/p2pd/servlet/dispatch
```

9300 is the default port number for the Cognos Content Manager. Be sure that the port number specified matches that used in the Cognos installation.

Valid Values

A well-formed URL.

Authentication mode

Description

Specifies whether the IBM Cognos application is using the `Authentication Provider`, which means it relies on the Unica Platform for authentication.

Default value

```
anonymous
```

Valid Values

- `anonymous`: means that authentication is disabled.
- `authenticated`: means that the communications between the system and the Cognos system are secured at the machine level. You configure a single system user and configure it with the appropriate access rights. By convention, this user is named "cognos_admin."
- `authenticatedPerUser`: means that the system evaluates individual user credentials.

Authentication namespace

Description

Read only. The namespace of the Authentication Provider.

Default value

UNICA

Authentication user name

Description

Specifies the login name for the reporting system user. The applications log in to Cognos as this user when Cognos is configured to use the Unica Authentication provider. This user also has access to Unica.

This setting applies only when the **Authentication mode** property is set to **authenticated**.

Default value

cognos_admin

Authentication datasource name

Description

Specifies the name of the data source for the reporting system user that holds the Cognos login credentials.

Default value

Cognos

Enable form authentication

Description

Specifies whether form-based authentication is enabled. You set this property to `True` when either of the following condition is true:

- When the Unica is not installed in the same domain as the IBM® Cognos applications.
- When IBM Cognos is accessed by using an IP address (within the same network domain) instead of the Fully Qualified Hostname (which is being used to access the Unica applications), even if both the Unica applications and the IBM Cognos installation are on the same machine.

However, when the value is `True`, the login process to Cognos Connection passes the login name and password in clear text and therefore is not secure unless IBM Cognos and the Unica are configured to use SSL communication.

Even with SSL configured, the user name and password appear as clear text in the HTML source code when you "view source" in a displayed report. For this reason, you must install IBM Cognos and Unica in the same domain.

Default value

`False`

Valid Values

`True` | `False`

Reports | Schemas | [product] | [schema name] | SQL Configuration

The SQL script creates views or tables for the reporting schemas. The **Reports | Schemas | [product] | [schema name] | SQL Configuration** property provides information about the name of the views or tables.

Table/View Name

Description

Specifies the name of the view or table that the SQL script you generate for this reporting schema creates. As a best practice, you should not change the name for any of the standard or default Table/View names. If you do, you must also change the name of the view in the Cognos® model in IBM® Cognos® Framework Manager.

When you create a new reporting schema for a new audience level, you must specify the names of all the new reporting tables/views.

Default value

Varies by schema

Valid Values

A string with the following restrictions.

- It can be no longer than 18 characters
- It must use all uppercase letters

You must use the following naming convention:

- Start the name with the letter "UAR"
- Add a one-letter code to represent the Unica application. See the list of codes, below.
- Add an underscore character
- Add the table name, including a one or two letter code to indicate the audience level
- Finish with an underscore character.

The SQL generator appends a time dimension code, if appropriate. See the following list of codes:

For example: `UARC_COPERF_DY` is the name of the reporting view or table for Campaign Offer Performance by Day.

Following is the list of Unica application codes.

- Unica Campaign: C
- IBM eMessage: E
- Unica Interact: I
- Unica Collaborate: X
- Unica Plan: P
- Leads: L

Following is the list of the Time Dimension Codes added by the generator.

- Hour: HR
- Day: DY
- Week: WK
- Month: MO
- Quarter: QU
- Year: YR

Reports | Schemas | Campaign

The **Reports | Schemas | Campaign** property provides information about the data source that identifies the Unica Campaign database.

Input Datasource (JNDI)

Description

Specifies the name of the JNDI data source that identifies the Unica Campaign database, specifically, the system tables. This data source must exist if you want to use the SQL generation tool to generate scripts that create reporting tables. The SQL generation tool can generate scripts that create reporting views without this data source, but it cannot validate them.

The database type of this data source must match the database type that you select when you generate the SQL scripts for the Unica Campaign views or reporting tables.

Default value

`campaignPartition1DS`

Reports | Schemas | Campaign | Offer Performance

The Offer Performance Schema yields contact and response history metrics for all offers and for offers by campaign. By default, the schema is configured to generate a "summary" view (or table) across all time.

Audience Key**Description**

Specifies the name of the column that is the Audience Key for the audience level that is supported by this reporting schema.

Default value

`CustomerID`

Valid Values

A string value no longer than 255 characters

If the key includes more than one column, use commas between the column names. For example, `ColumnX,ColumnY`.

Contact History Table**Description**

Specifies the name of the Contact History table for the audience level that is supported by this reporting schema.

Default value

`UA_ContactHistory`

Detailed Contact History Table**Description**

Specifies the name of the Detailed Contact History table for the audience level that is supported by this reporting schema.

Default value

`UA_DtlContactHist`

Response History Table

Description

Specifies the name of the Response History table for the audience level that is supported by this reporting schema.

Default value

`UA_ResponseHistory`

Over Time Variations

Description

Specifies the calendar time periods that are used by the "over time" reports supported by this schema.

Default value

`Day, Month`

Valid Values

`Day, Week, Month, Quarter, Year`

Reports | Schemas | Campaign | [schema name] | Columns | [Contact Metric] and [Response metric]

Use these properties to add contact and response metrics to the Campaign Performance or Offer Performance reporting schemas.

Column Name

Configuration category

Reports | Schemas | Campaign | [schema name] | Columns |
[Contact Metric]

Description

Specifies the name to use in the reporting view or table for the column that is specified in the **Input Column Name** field.

Default value

[CHANGE ME]

Valid Values

The name can be no longer than 18 characters, it must be in all uppercase letters, and it cannot have spaces.

Function

Configuration category

Reports | Schemas | Campaign | [schema name] | Columns |
[Contact Metric]

Description

Specifies how the contact metric is determined or calculated.

Default value

count

Valid Values

count, count distinct, sum, min, max, average

Input Column Name

Configuration category

Reports | Schemas | Campaign | [schema name] | Columns |
[Contact Metric]

Description

The name of the column that provides the contact metric you are adding to this reporting schema.

Default value

[CHANGE ME]

Valid Values

The name of the column in the Contact History and Detailed Contact History tables.

Control Treatment Flag**Configuration category**

Reports | Schemas | Campaign | [schema name] | Columns | [Contact Metric]

Description

If you use the sample IBM® Cognos® reports or create your own custom reports that include control groups, then each contact metric must have two columns in the reporting schema. One column represents the metric for the control group and the other column represents the metric for the target group. The value in **Control Treatment Flag** specifies whether the column in the view represents the control group or the target group.

If your reports do not include control groups, you do not need the second column for the control group.

Default value

0

Valid Values

- 0: the column represents the target group
- 1: the column represents the control group

Column Name

Configuration category

Reports | Schemas | Campaign | [schema name] | Columns |
[Response Metric]

Description

Specifies the name to use in the reporting view or table for the column that is specified in the **Input Column Name** field.

Default value

[CHANGE ME]

Valid Values

The name can be no longer than 18 characters, it must be in all uppercase letters, and it cannot have spaces.

Function

Configuration category

Reports | Schemas | Campaign | [schema name] | Columns |
[Response Metric]

Description

Specifies how the response metric is determined or calculated.

Default value

count

Valid Values

count, count distinct, sum, min, max, average

Input Column Name

Configuration category

Reports | Schemas | Campaign | [schema name] | Columns |
[Response Metric]

Description

The name of the column that provides the response metric you are adding to this reporting schema.

Default value

[CHANGE ME]

Valid Values

The name of the column in the Response History table.

Control Treatment Flag

Configuration category

Reports | Schemas | Campaign | [schema name] | Columns |
[Response Metric]

Description

If you use the standard IBM® Cognos® reports or create your own custom reports that include control groups, then each response metric must have two columns in the reporting schema. One column represents the response from the control group and the other column represents the response from the target group. The value in **Control Treatment Flag** specifies whether the column in the view represents the control group or the target group.

If your reports do not include control groups, you do not need the second column for the control group.

Default value

0

Valid Values

- 0: the column represents the target group
- 1: the column represents the control group

Reports | Schemas | Campaign | Campaign Performance

The Campaign Performance schema yields contact and response history metrics at the campaign, campaign-offer, and campaign-cell level.

Audience Key

Description

Specifies the name of the column that is the Audience Key for the audience level that is supported by this reporting schema.

Default value

`CustomerID`

Valid Values

A string value no longer than 255 characters.

If the key includes more than one column, use commas between the column names. For example, `ColumnX,ColumnY`.

Contact History Table

Description

Specifies the name of the Contact History table for the audience level that is supported by this reporting schema.

Default value

`UA_ContactHistory`

Detailed Contact History Table

Description

Specifies the name of the Detailed Contact History table for the audience level that is supported by this reporting schema.

Default value

`UA_DtlContactHist`

Response History Table

Description

Specifies the name of the Response History table for the audience level that is supported by this reporting schema.

Default value

`UA_ResponseHistory`

Over Time Variations

Description

Specifies the calendar time periods that are used by the "over time" reports supported by this schema.

Default value

`Day, Month`

Valid Values

`Day, Week, Month, Quarter, Year`

Reports | Schemas | Campaign | Campaign Offer Response Breakout

The Campaign Offer Response Breakout schema supports reporting on campaign-detailed responses, which are broken out by response type and by offer data. This schema template gives different response counts for each custom Response Type for campaigns and offers grouped by campaign.

This schema

Response History Table

Description

Specifies the name of the Response History table for the audience level that is supported by this reporting schema.

Default value

UA_ResponseHistory

Reports | Schemas | Campaign | Campaign Offer Response Breakout | Columns | [Response Type]

Use the **Reports | Schemas | Campaign | Campaign Offer Response Breakout | Columns | [Response Type]** property to add any custom response types that you want to include in your reports to the reporting schema.

Column Name

Description

Specifies the name to use in the reporting view or table for the column that is specified in the **Response Type Code** field.

Default value

[CHANGE ME]

Valid Values

The name can be no longer than 18 characters, it must be in all uppercase letters, and it cannot have spaces.

Response Type Code

Description

The response type code for the specified response type. This value is held in the `ResponseTypeCode` column in the `UA_UsrResponseType` table.

Default value

[CHANGE ME]

Valid Values

The example response type codes are as follows:

- EXP (explore)
- CON (consider)
- CMT (commit)
- FFL (fulfill)
- USE (use)
- USB (unsubscribe)
- UKN (unknown)

Your Unica Campaign installation may have additional custom response type codes.

Control Treatment Flag

Description

If you use the standard IBM® Cognos® reports provided in the Unica Reports Pack or custom reports that include control groups, then each response type must have two columns in the reporting schema. One column represents the response type from the control group and the other column represents the response type from the target group. The value in **Control Treatment Flag** specifies whether the column in the view represents the control group or the target group.

If your reports do not include control groups, you do not need the second column for the control group.

Default value

0

Valid Values

- 0: the column represents the target group
- 1: the column represents the control group

Reports | Schemas | Campaign | [schema name] | Columns | [Response Metric]

Use the **Reports | Schemas | Campaign | [schema name] | Columns | [Response Metric]** property to add the response metrics that you want to include in your reports to the Campaign Performance or Offer Performance reporting schemas.

Column Name

Description

Specifies the name to use in the reporting view or table for the column that is specified in the **Input Column Name** field.

Default value

[CHANGE ME]

Valid Values

The name can be no longer than 18 characters, it must be in all uppercase letters, and it cannot have spaces.

Function

Description

Specifies how the response metric is determined or calculated.

Default value

count

Valid Values

count, count distinct, sum, min, max, average

Input Column Name

Description

The name of the column that provides the response metric you are adding to this reporting schema.

Default value

[CHANGE ME]

Valid Values

The name of the column in the Response History table.

Control Treatment Flag

Description

If you use the standard IBM® Cognos® reports or create your own custom reports that include control groups, then each response metric must have two columns in the reporting schema. One column represents the response from the control group and the other column represents the response from the target group. The value in **Control Treatment Flag** specifies whether the column in the view represents the control group or the target group.

If your reports do not include control groups, you do not need the second column for the control group.

Default value

0

Valid Values

- 0: the column represents the target group
- 1: the column represents the control group

Reports | Schemas | Campaign | Campaign Offer Contact Status Breakout

The Campaign Offer Contact Status Breakout schema supports reporting on campaign-detailed contacts, which are broken out by contact status type and by offer data. This schema template gives different contact counts for each custom Contact Status Type for campaigns and offers grouped by campaign.

By default, none of the example Unica Campaign reports use this schema.

Audience Key

Description

Specifies the name of the column that is the Audience Key for the audience level that is supported by this reporting schema.

Default value

`CustomerID`

Valid Values

A string value no longer than 255 characters.

If the key includes more than one column, use commas between the column names. For example, `ColumnX,ColumnY`.

Contact History Table

Description

Specifies the name of the Contact History table for the audience level that is supported by this reporting schema.

Default value

`UA_ContactHistory`

Detailed Contact History Table

Description

Specifies the name of the Detailed Contact History table for the audience level that is supported by this reporting schema.

Default value

`UA_DtlContactHist`

Reports | Schemas | Campaign | Campaign Offer Contact Status Breakout | Columns | [Contact Status]

Use the **Reports | Schemas | Campaign | Campaign Offer Contact Status Breakout | Columns | [Contact Status]** to add the contact status that you want to include in your reports to the reporting schemas.

Column Name

Description

Specifies the name to use in the reporting view or table for the column that is specified in the **Contact Status** field.

Default value

[CHANGE ME]

Valid Values

The name can be no longer than 18 characters, it must be in all uppercase letters, and it cannot have spaces.

Contact Status Code

Description

The name of the contact status code. This value is held in the `ContactStatusCode` column in the `UA_ContactStatus` table.

Default value

[CHANGE ME]

Valid Values

The example contact status types are as follows.

- CSD (campaign send)
- DLV (delivered)
- UNDLV (undelivered)
- CTR (control)

Your Unica Campaign installation may have additional custom contact status types.

Reports | Schemas | Campaign | Campaign Custom Attributes | Columns

Use these properties to add any custom offer attributes that you want to include in your reports to the reporting schema.

Column Name

Configuration category

Reports | Schemas | Campaign | Campaign Custom Attributes
| Columns | [Campaign Custom Column]

Description

Specifies the name to use in the reporting view or table for the attribute that is identified in the **Attribute ID** field.

Default value

[CHANGE ME]

Valid Values

The name can be no longer than 18 characters, it must be in all uppercase letters, and it cannot have spaces.

Attribute ID

Configuration category

Reports | Schemas | Campaign | Campaign Custom Attributes
| Columns | [Campaign Custom Column]

Description

The value from the attribute's `AttributeID` column in the **UA_CampAttribute** table.

Default value

0

Value Type

Configuration category

Reports | Schemas | Campaign | Campaign Custom Attributes
| Columns | [Campaign Custom Column]

Description

The data type of the campaign attribute.

Default value

StringValue

Valid Values

StringValue, NumberValue, DatetimeValue

If this campaign attribute holds a currency value, select `NumberValue`.

If this campaign attribute's **Form Element Type** was set to `Select Box - String` in Unica Campaign, select `StringValue`.

Column Name

Configuration category

Reports | Schemas | Campaign | Campaign Custom Attributes
| Columns | [Cell Custom Column]

Description

Specifies the name to use in the reporting view or table for the attribute that is identified in the **Attribute ID** field.

Default value

[CHANGE ME]

Valid Values

The name can be no longer than 18 characters, it must be in all uppercase letters, and it cannot have spaces.

Attribute ID

Configuration category

Reports | Schemas | Campaign | Campaign Custom Attributes
| Columns | [Cell Custom Column]

Description

The value from the attribute's `AttributeID` column in the **UA_CellAttribute** table.

Default value

0

Value Type

Configuration category

Reports | Schemas | Campaign | Campaign Custom Attributes
| Columns | [Cell Custom Column]

Description

The data type of the cell attribute.

Default value

StringValue

Valid Values

StringValue, NumberValue, DatetimeValue

Column Name

Configuration category

Reports | Schemas | Campaign | Campaign Custom Attributes
| Columns | [Offer Custom Column]

Description

Specifies the name to use in the reporting view or table for the attribute that is identified in the **Attribute ID** field.

Default value

[CHANGE ME]

Valid Values

The name can be no longer than 18 characters, it must be in all uppercase letters, and it cannot have spaces.

Attribute ID

Configuration category

Reports | Schemas | Campaign | Campaign Custom Attributes
| Columns | [Offer Custom Column]

Description

The value from the attribute's `AttributeID` column in the **UA_OfferAttribute** table.

Default value

0

Value Type

Configuration category

Reports | Schemas | Campaign | Campaign Custom Attributes
| Columns | [Offer Custom Column]

Description

The data type of the offer attribute.

Default value

StringValue

Valid Values

StringValue, NumberValue, DatetimeValue

If this offer attribute holds a currency value, select `NumberValue`.

If this offer attribute's **Form Element Type** was set to `Select Box - String` in Campaign, select `StringValue`.

Reports | Schemas | Campaign | Campaign Custom Attributes | Columns | [Campaign Custom Column]

Use the **Reports | Schemas | Campaign | Campaign Custom Attributes | Columns | [Campaign Custom Column]** property to add any custom campaign attributes that you want to include in your reports to the reporting schema.

Column Name

Description

Specifies the name to use in the reporting view or table for the attribute that is identified in the **Attribute ID** field.

Default value

[CHANGE ME]

Valid Values

The name can be no longer than 18 characters, it must be in all uppercase letters, and it cannot have spaces.

Attribute ID

Description

The value from the attribute's `AttributeID` column in the **UA_CampAttribute** table.

Default value

0

Value Type

Description

The data type of the campaign attribute.

Default value

StringValue

Valid Values

StringValue, NumberValue, DatetimeValue

If this campaign attribute holds a currency value, select `NumberValue`.

If this campaign attribute's **Form Element Type** was set to `Select Box - String` in Unica Campaign, select `StringValue`.

Reports | Schemas | Campaign | [schema name] | Columns | [Contact Metric]

Use the **Reports | Schemas | Campaign | [schema name] | Columns | [Contact Metric]** property to add contact metrics to the Campaign Performance or Offer Performance reporting schemas.

Column Name

Description

Specifies the name to use in the reporting view or table for the column that is specified in the **Input Column Name** field.

Default value

[CHANGE ME]

Valid Values

The name can be no longer than 18 characters, it must be in all uppercase letters, and it cannot have spaces.

Function

Description

Specifies how the contact metric is determined or calculated.

Default value

count

Valid Values

count, count distinct, sum, min, max, average

Input Column Name

Description

The name of the column that provides the contact metric you are adding to this reporting schema.

Default value

[CHANGE ME]

Valid Values

The name of the column in the Contact History and Detailed Contact History tables.

Control Treatment Flag

Description

If you use the sample IBM® Cognos® reports or create your own custom reports that include control groups, then each contact metric must have two columns in the reporting schema. One column represents the metric for the control group and the other column represents the metric for the target group. The value in **Control Treatment Flag** specifies whether the column in the view represents the control group or the target group.

If your reports do not include control groups, you do not need the second column for the control group.

Default value

0

Valid Values

- 0: the column represents the target group
- 1: the column represents the control group

Reports | Schemas | Campaign | Campaign Custom Attributes | Columns | [Offer Custom Column]

Use the **Reports | Schemas | Campaign | Campaign Custom Attributes | Columns | [Offer Custom Column]** property to add any custom offer attributes that you want to include in your reports to the reporting schema.

Use this form to add

Column Name

Description

Specifies the name to use in the reporting view or table for the attribute that is identified in the **Attribute ID** field.

Default value

[CHANGE ME]

Valid Values

The name can be no longer than 18 characters, it must be in all uppercase letters, and it cannot have spaces.

Attribute ID

Description

The value from the attribute's `AttributeID` column in the **UA_OfferAttribute** table.

Default value

0

Value Type

Description

The data type of the offer attribute.

Default value

StringValue

Valid Values

StringValue, NumberValue, DatetimeValue

If this offer attribute holds a currency value, select `NumberValue`.

If this offer attribute's **Form Element Type** was set to `Select Box - String` in Campaign, select `StringValue`.

Reports | Schemas | Campaign | Campaign Custom Attributes | Columns | [Cell Custom Column]

Use the **Reports | Schemas | Campaign | Campaign Custom Attributes | Columns | [Cell Custom Column]** property to add any custom cell attributes that you want to include in your reports to the reporting schema.

Column Name

Description

Specifies the name to use in the reporting view or table for the attribute that is identified in the **Attribute ID** field.

Default value

[CHANGE ME]

Valid Values

The name can be no longer than 18 characters, it must be in all uppercase letters, and it cannot have spaces.

Attribute ID

Description

The value from the attribute's `AttributeID` column in the **UA_CellAttribute** table.

Default value

0

Value Type

Description

The data type of the cell attribute.

Default value

`StringValue`

Valid Values

`StringValue, NumberValue, DatetimeValue`

Reports | Schemas | Interact

The Unica Interact reporting schemas reference three separate databases: the design time, runtime, and learning databases. Use the **Reports | Schemas | Interact** property to specify the JNDI names of the data sources for those databases.

The data sources that are specified on this page must exist if you want to use the Reporting SQL generation tool to generate scripts that create reporting tables. The SQL generation tool can generate scripts that create reporting views without these data sources, but it cannot validate the scripts.

The database type of the data sources must match the database type that you select when you generate the SQL scripts for the views or reporting tables.

Interact Design Datasource (JNDI)

Description

Specifies the name of the JNDI data source that identifies the Unica Interact design time database, which is also the Unica Campaign system tables.

Default value

`campaignPartition1DS`

Interact Runtime Datasource (JNDI)

Description

Specifies the name of the JNDI data source that identifies the Unica Interact runtime database.

Default value

`InteractRTDS`

Interact Learning Datasource (JNDI)

Description

Specifies the name of the JNDI data source that identifies the Unica Interact learning database.

Default value

`InteractLearningDS`

Reports | Schemas | Interact | Interact Performance

The Interact Performance schema yields contact and response history metrics at the channel, channel-offer, channel-segment, channel-interaction point, interactive cell, interactive cell-offer, interactive cell-interaction point, interactive offer, interactive offer-cell, and interactive offer-interaction point levels.

Audience Key

Description

Specifies the name of the column that is the Audience Key for the audience level that is supported by this reporting schema.

Default value

`CustomerID`

Valid Values

A string value no longer than 255 characters.

If the key includes more than one column, use commas between the column names. For example, `ColumnX,ColumnY`.

Detailed Contact History Table

Description

Specifies the name of the Detailed Contact History table for the audience level that is supported by this reporting schema.

Default value

`UA_DtlContactHist`

Response History Table

Description

Specifies the name of the Response History table for the audience level that is supported by this reporting schema.

Default value

`UA_ResponseHistory`

Over Time Variations

Description

Specifies the calendar time periods that are used by the "over time" reports supported by this schema.

Default value

`Hour, Day`

Valid Values

`Hour, Day, Week, Month, Quarter, Year`

Reports | Schemas | IBM eMessage

The **Reports | Schemas | IBM eMessage** property specifies the name of the data source that identifies the eMessage tracking tables, which are in the Unica Campaign system tables.

Unica Deliver Tracking Datasource (JNDI)

Description

Specifies the name of the JNDI data source that identifies the eMessage tracking tables, which are in the Unica Campaign system tables. This data source must exist if you want to use the Reports SQL generation tool to validate scripts that create reporting tables. The SQL generation tool can generate scripts that create reporting views without this data source, but it cannot validate them.

The database type of this data source must match the database type that you select when you generate the SQL scripts for the views or reporting tables.

Default value

`campaignPartition1DS`

Unica Plan configuration properties

This section describes the Unica Plan configuration properties on the **Settings > Configuration** page.

Unica Plan

Properties in this category specify the default and supported locales for your installation of Unica Plan.

supportedLocales

Description

Specifies the locales available in your installation of Unica Plan. List only the locales that you are using. Each locale you list uses memory on the server. The amount of memory that is used depends on the size and number of templates.

If you add locales after the initial installation or upgrade, you must run the upgrade servlets again. See upgrade documentation for details.

If you change this value, you must stop and restart your Unica Plan deployment before the change takes effect.

Default value

en_US

defaultLocale

Description

Specifies the supported locale in which you want Unica Plan to display for all users, unless explicitly overridden for specific users by Unica Plan administrators.

If you change this value, you must stop and restart your Unica Plan deployment before the change takes effect.

Default value

en_US

Unica Plan | navigation

The properties in this category specify options for navigation, such as Uniform Resource Identifiers, URLs, and ports.

welcomePageURI

Description

The Uniform Resource Identifier of the Unica Plan index page. This value is used internally by Unica applications. Changes to this value are not recommended.

Default value

affiniumPlan.jsp?cat=projectlist

projectDetailpageURI

Description

The Uniform Resource Identifier of the Unica Plan detail page. This value is used internally by Unica applications. Changes to this value are not recommended.

Default value

blank

seedName**Description**

Used internally by Unica applications. Changes to this value are not recommended.

Default value

Plan

type**Description**

Used internally by Unica applications. Changes to this value are not recommended.

Default value

Plan

httpPort**Description**

The port number that is used by the application server for connections to the Unica Plan application.

Default value

7001

httpsPort**Description**

The port number that is used by the application server for secure connections to the Unica Plan application.

Default value

7001

serverURL**Description**

The URL of the Unica Plan installation. Accepts locators with either the HTTP or HTTPS protocol.

If users access Unica Plan with the Chrome browser, use the fully qualified domain name (FQDN) in the URL. If the FQDN is not used, the Chrome browser cannot access the product URLs.

Default value

`http://<server>:<port>/plan`



Note: <server> must be lowercase.

logoutURL**Description**

Used internally. Changes to this value are not recommended.

Unica Platform uses this value to call the logout handler of each registered application if the user clicks the logout link in suite.

Default value

`/uapsysservlet?cat=sysmodules&func=logout`

displayName**Description**

Used internally.

Default value

Unica Plan

Unica Plan | about

The configuration properties in this section list information about your Unica Plan installation. You cannot edit these properties.

displayName**Description**

The display name of the product.

Value

Unica Plan

releaseNumber**Description**

The currently installed release.

Value

<version>.<release>.<modification>

copyright**Description**

The copyright year.

Value

<year>

OS**Description**

The operating system on which Unica Plan is installed.

Value

<operating system and version>

java

Description

The current version of Java™.

Value

<version>

support

Description

Read documentation and place service requests.

Value

<https://hclpnpsupport.hcltech.com/csm>

appServer

Description

The address of the application server on which Unica Plan is installed.

Value

<IP address>

otherString

Description

Value

blank

Unica Plan | umoConfiguration

These properties specify information about the basic configuration of Unica Plan.

serverType

Description

Application Server Type. Used for Calendar export.

Valid values

WEBLOGIC, WEBSHERE, JBOSS, TOMCAT

Default value

Websphere

DBType

Description

Database Type. Indicates on which type of database the system tables are stored.

Valid values

DB2, ORACLE, SQLSERVER, MARIADB, and INFORMIX



Note: Do not select **DBType** as `INFORMIX`, during installation of versions 12.0.0.1 and 12.0.0.0, as it is not functional.

Default value

DB2

userManagerSyncTime

Description

Time in milliseconds to between scheduled synchronizations with Unica Platform.

Default value

10800000 (milliseconds: 3 hours)

encodeCSV

Description

When the value of this setting is true, when the TCS grid in a Campaign integrated project is exported, the values of strings in cells are enclosed in quotes. When such data is imported and if there is a formula in a string, it is prevented from running when user visits the TCS grid page

Valid values

True | False

Default value

False

firstMonthInFiscalYear

Description

Set to the month that you would like your account fiscal year to begin. The Summary tab for the account contains a view-only table, which lists budget information by month for the fiscal years of the account. The first month in this table is determined by this parameter.

January is represented by 0. To have your fiscal year to begin in April, set **firstMonthInFiscalYear** to 3.

Valid values

Integers 0 to 11

Default value

0

maximumItemsToBeRetainedInRecentVisits

Description

The maximum number of links to recently viewed pages to display on the **Recent** menu.

Default value

10 (links)

maxLimitForTitleString**Description**

The maximum number of characters that can display in a page title. If titles are longer than the specified number, Unica Plan clips them.

Default value

40 (characters)

maximumLimitForBulkUploadItems**Description**

The maximum number of attachments you can upload at the same time.

Default value

5 (attachments)

workingDaysCalculation**Description**

Controls how Unica Plan calculates durations.

Valid values

- `bus`: Business days only, includes working days only. Does not include weekends and days off.
- `wkd`: Business days + Weekends, includes working days and weekends. Does not include days off.
- `off`: Business days + Days off, includes all working days and days off. Does not include weekends.
- `all`: includes all days in the calendar.

Default value

all

validateAllWizardSteps

Description

When users create a program, project, or request with the wizard, Unica Plan automatically validates that the required fields on the current page have values. This parameter controls whether Unica Plan validates the required fields on all pages (tabs) when a user clicks **Finish**.

Valid values

- **True**: Unica Plan checks the required fields on pages that the user did not view (except workflow, tracking, and attachments). If a required field is blank, the wizard opens that page and displays an error message.
- **False**: Unica Plan does not validate required fields on pages the user did not view.

Default value

True

enableRevisionHistoryPrompt

Description

Ensures that users are prompted to add change comments when they save a project, request, or approval.

Valid values

True | False

Default value

False

useForecastDatesInTaskCalendar

Description

Specifies the type of dates that are used when tasks display in calendar view.

Valid values

- `True`: uses forecast and actual dates to display tasks.
- `False`: uses target dates to display tasks.

Default value

`False`

copyRequestProjectCode**Description**

Controls whether you want to carry the Project Code (PID) over from a request to a project. If you set this parameter to `False`, the project and the request use different codes.

Valid values

`True` | `False`

Default value

`True`

projectTemplateMonthlyView**Description**

Controls whether the monthly view is allowed in the workflow for a project template.

Valid values

`True` | `False`

Default value

`False`

disableAssignmentForUnassignedReviewers

Description

Specifies how work is assigned by role for approvals. The **disableAssignmentForUnassignedReviewers** parameter controls the behavior of **Assign work by Role** on the People tab for assignment of approvers in workflow approvals.

Valid values

- **True:** unassigned reviewers in the People tab are not added to the approval as new steps.
 - Append option: The existing, owner-assigned approvers without an assigned role do not change. New approver steps are not added even if the People tab has reviewers with the role "unassigned."
 - Replace option: The existing owner assigned approvers without a role are replaced with a blank. New approver steps would not be added even if the people tab has reviewers with the role "unassigned."
- **False:** unassigned reviewers are added to the approval.
 - Append option: All reviewers without a role are appended to the approval as reviewers if the approval has owner assigned steps without defined roles.
 - Replace Option: The existing approvers of approvals are replaced with the unassigned approvers in the People tab.

Default value

False

enableApplicationLevelCaching

Description

Indicates whether application-level caching is enabled or not. For best results in a clustered environment on which multicasting of caching messages is not enabled, consider turning off application level caching for Unica Plan.

Valid values

True | False

Default value

True

customAccessLevelEnabled**Description**

Determines whether you use custom access levels (project roles) in Unica Plan.

Valid values

- **True:** user access to projects and requests is evaluated according to Object Access Levels and Custom Access Levels (project roles). Tab security is enabled for custom tabs.
- **False:** user access to projects and requests is evaluated according only to Object Access Levels (object implicit roles), and tab security is turned off for custom tabs.

Default value

True

enableUniqueIdsAcrossTemplatizableObjects**Description**

Determines whether you use unique internal IDs for all of the objects that are created from templates, including programs, projects, plans, and invoices.

Valid values

- `True` enables unique internal IDs across all objects that are created from templates. This configuration simplifies cross-object reporting by allowing the system to use the same table for different object types.
- `False` disables unique internal IDs across all objects that are created from templates.

Default value

`True`

FMEnabled

Description

Enables and disables the Financial Management Module, which determines whether the Accounts, Invoices, and Budget tabs appear in the product.

Valid values

`True` | `False`

Default value

`False`

FMProjVendorEnabled

Description

Parameter that is used to show/hide vendor column for project line items.

Valid values

`True` | `False`

Default value

`False`

FMPrgmVendorEnabled

Description

Parameter that is used to show/hide vendor column for program line items.

Valid values

True | False

Default value

False

Unica Plan | umoConfiguration | Approvals

These properties specify options for approvals.

specifyDenyReasons

Description

Enables a customizable list of reasons for denying an approval. When enabled, administrators populate the Approval Deny Reasons list with options, then associate deny reasons with each workflow template and each project template that defines a workflow. Users who deny an approval, or an item within an approval, are required to select one of these predefined reasons.

Valid values

True | False

Default value

False

approveWithChanges

Description

Enables the **Approve with changes** option for an approval. When enabled, The **Allow approvers to approve with changes** option is selected by default when a user sets up approvals in a project template, project, or a standalone approval. The **Allow approvers to approve with changes** option can be edited if the **overrideApproveWithChanges** property is set to `True`.

An approver can approve a task by selecting the **Approve with changes** option if the **Allow approvers to approve with changes** option is selected when the approval is set up.

Valid values

True | False

Default value

True

overrideApproveWithChanges

Description

Set to `True` to allow a user to edit the default setting for the **Allow approvers to approve with changes** option when a user sets up approvals in a project template, project, or a standalone approval. The default setting is determined by the **approveWithChanges** property.

Valid values

True | False

Default value

True

Unica Plan | umoConfiguration | templates

These properties specify information about templates in Unica Plan. For best results, do not change the default values of these parameters.

templatesDir

Description

Identifies the directory that contains all of your project template definitions, which are stored in XML files.

Use a fully qualified path.

Default value

```
<HCL_Unica_Home>/<Plan_Home>/templates
```

assetTemplatesFile**Description**

The XML file that defines the templates for assets. This file must be in the directory that is specified by **templatesDir**.

Default value

```
asset_templates.xml
```

planTemplatesFile**Description**

The XML file that defines the templates for plans. This file must be in the directory that is specified by **templatesDir**.

Default value

```
plan_templates.xml
```

programTemplatesFile**Description**

The XML file that defines the templates for programs. This file must be in the directory that is specified by **templatesDir**.

Default value

```
program_templates.xml
```

projectTemplatesFile**Description**

The XML file that defines the templates for projects. This file must be in the directory that is specified by **templatesDir**.

Default value

```
project_templates.xml
```

invoiceTemplatesFile

Description

The XML file that defines the templates for invoices. This file must be in the directory that is specified by **templatesDir**.

Default value

```
invoice_templates.xml
```

componentTemplatesFile

Description

The XML file that defines the templates for custom marketing object types. This file must be in the directory that is specified by **templatesDir**.

Default value

```
component_templates.xml
```

metricsTemplateFile

Description

The XML file that defines the templates for metrics. This file must be in the directory that is specified by **templatesDir**.

Default value

```
metric_definition.xml
```

teamTemplatesFile

Description

The XML file that defines the templates for teams. This file must be in the directory that is specified by **templatesDir**.

Default value

```
team_templates.xml
```

offerTemplatesFile

Description

The XML file that defines the templates for offers. This file must be in the directory that is specified by **templatesDir**.

Default value

```
uap_sys_default_offer_comp_type_templates.xml
```

Unica Plan | umoConfiguration | attachmentFolders

These properties specify directories to upload and store attachments.

uploadDir

Description

The upload directory where attachments for projects are stored.

Default value

```
<Plan_Home>/projectattachments
```

planUploadDir

Description

The upload directory where attachments for plans are stored.

Default value

```
<Plan_Home>/planattachments
```

programUploadDir

Description

The upload directory where attachments for programs are stored.

Default value

```
<Plan_Home>/programattachments
```

componentUploadDir

Description

The upload directory where attachments for marketing objects are stored.

Default value

<Plan_Home>/componentattachments

taskUploadDir

Description

The upload directory where attachments for tasks are stored.

Default value

<Plan_Home>/taskattachments

approvalUploadDir

Description

The upload directory where approval items are stored.

Default value

<Plan_Home>/approvalitems

assetUploadDir

Description

The upload directory where assets are stored.

Default value

<Plan_Home>/assets

accountUploadDir

Description

The upload directory where attachments for accounts are stored.

Default value

<Plan_Home>/accountattachments

invoiceUploadDir

Description

The upload directory where attachments for invoices are stored.

Default value

<Plan_Home>/invoiceattachments

graphicalRefUploadDir

Description

The upload directory where attribute images are stored.

Default value

<Plan_Home>/graphicalrefimages

templateImageDir

Description

The upload directory where template images are stored.

Default value

<Plan_Home>/images

recentDataDir

Description

The temporary directory that stores the recent data (serialized) for each user.

Default value

<Plan_Home>/recentdata

workingAreaDir

Description

The temporary directory that stores CSV files that are uploaded during grid imports.

Default value

`<Plan_Home>/umotemp`

managedListDir

Description

The upload directory where managed list definitions are stored.

Default value

`<Plan_Home>/managedList`

Unica Plan | umoConfiguration | fileUpload

The properties in this category specify options for file uploads.

validateFileUpload

Description

You can choose `True` to validate a file that is uploaded or `False` if you do not want to validate a file that is uploaded.

allowedFileTypes

Description

The type of file allowed to be uploaded. File types can include `.doc`, `.ppt`, `.xls`, `.pdf`, `.gif`, `.jpeg`, `.png`, and `.mpp`.

fileMaxSize

Description

The maximum size allowed for the file that you upload.

Unica Plan | umoConfiguration | Email

These properties specify information for sending email notifications in Unica Plan.

notifyEMailMonitorJavaMailHost

Description

Optional string that specifies either the DNS host name of the email notifications mail server or its dot-formatted IP address. Set to the machine name or IP address of your SMTP server.

This parameter is necessary if you did not provide Unica Plan with an existing JavaMail™ session that uses the session parameter and the delegate is marked "Complete."

Default value

[CHANGE-ME]

notifyDefaultSenderEmailAddress

Description

Set to a valid email address. The system sends email messages to this address when there is no valid email address available to send the notification email messages.

Default value

[CHANGE-ME]

notifySenderAddressOverride

Description

Use this parameter to specify a standard value for the REPLY-TO and FROM email addresses for notifications. By default, these addresses are populated with the email address of the event owner.

Default value

blank

Unica Plan | umoConfiguration | markup

These properties specify markup options. Unica Plan provides markup tools for making comments on attachments. You can use either Adobe™ Acrobat markup or native Unica Plan markup. Use the properties in this category to configure which option to use.

markupServerType

Description

Determines which markup option to use.

Valid values

- `SOAP` enables users to edit and view markups in PDF documents. Adobe™ Acrobat Professional is required for markups. If specified, users cannot view markups that were made previously in a web browser with the native Unica Plan method.

If you specify `SOAP`, you must also configure the **markupServerURL** parameter.

If you specify `SOAP`, you must delete the customized `UMO_Markup_Collaboration.js` that was copied in the JavaScripts subdirectory of the directory where Adobe Acrobat is installed.

For example: `C:\Program files (x86)\Adobe\Acrobat 10.0\Acrobat\Javascripts\UMO_Markup_Collaboration.js`.

This file is no longer required.

- `MCM` enables the native Unica Plan markup method that allows users to edit and view markups in a web browser. If specified, users cannot edit or view markups that were made previously in a PDF with Adobe™ Acrobat.
- If blank, the markup function is disabled and the **View/Add Markup** link does not appear.

Default value

MCM

markupServerURL

Description

Dependent on **markupServerType** = SOAP.

Set to the URL for the computer that hosts the markup server, including the number of the port the web application server uses for listening. The URL must contain the fully qualified host name.

Accepts locators with either the HTTP or HTTPS protocol.

Default value

```
http://<server>:<port>/plan/services/collabService?wsdl
```

instantMarkupFileConversion

Description

If `True`, Unica Plan converts PDF attachments to images as soon as they are uploaded, rather than doing this conversion the first time a user opens the item for markup.

Valid values

True | False

Default value

False

Unica Plan | umoConfiguration | grid

These properties specify options for grids.

gridmaxrow

Description

An optional integer to define the maximum number of rows to be retrieved in grids. The default, `-1`, retrieves all rows.

Default value

-1

reloadRuleFile

Description

An optional boolean parameter that indicates whether the grid validation plug-in needs to be reloaded or not.

Valid values

True | False

Default value

True

gridDataValidationClass

Description

An optional parameter to specify custom grid data validation class. If not specified, the default, the built in plug-in is used for grid data validation.

Default value

blank

tvcDataImportFieldDelimiterCSV

Description

Delimiter to use to parse data imported into a grid. Default is comma (,).

Default value

, (comma)

maximumFileSizeToImportCSVFile

Description

Represents the maximum file size in MB that can be uploaded while importing comma-separated data for TVC.

Default value

0 (unlimited)

maximumRowsToBeDisplayedPerPageInGridView

Description

Specifies the number of rows to display per page in grid view.

Valid values

positive integers

Default value

100

griddatasxsd

Description

Name of grid data XSD file.

Default value

`griddataschema.xsd`

gridpluginxsd

Description

Name of grid plug-ins XSD file.

Default value

`gridplugin.xsd`

gridrulesxsd

Description

Name of grid rules XSD file.

Default value

`gridrules.xsd`

Unica Plan | umoConfiguration | workflow

These properties specify options for the workflow in Unica Plan.

hideDetailedDateTime

Description

Optional show/hide parameter for detailed date time in the tasks page.

Valid values

True | False

Default value

False

daysInPastRecentTask

Description

This parameter determines how long tasks are considered "recent." If the task is "active" and started less than this number of days ago, or the Target End Date of the task is between today and this number of days in the past, the task displays as a recent task.

Valid values

positive integers

Default value

14 (days)

daysInFutureUpcomingTasks

Description

This parameter determines how many days in the future to look for upcoming tasks. If the task starts in the next **daysInFutureUpcomingTasks** or does not end before the current date, it is an upcoming task.

Valid values

positive integers

Default value

14 (days)

beginningOfDay**Description**

Begin hour of the working day. This parameter is used to calculate the datetimes in workflow using fractional durations.

Valid values

integers from 0 to 12

Default value

9 (9 AM)

numberOfHoursPerDay**Description**

Number of hours per day. This parameter is used to calculate the datetimes in workflow using fractional durations.

Valid values

integers from 1 to 24

Default value

8 (hours)

mileStoneRowBGColor**Description**

Defines the background color for workflow tasks. To specify the value, insert the # character before the six-character Hex code for the color. For example, #0099CC.

Default value

#DDDDDD

Unica Plan | umoConfiguration | integrationServices

These properties specify information about Unica Plan Integration Services module. The Integration Services module extends the function of Unica Plan with web services and triggers.

enableIntegrationServices

Description

Enables and disables the Integration Services module.

Valid values

True | False

Default value

False

integrationProcedureDefinitionPath

Description

Optional full file path to the custom procedure definition XML file.

Default value

[plan-home]/devkits/integration/examples/src/procedure/procedure-plugins.xml

integrationProcedureClasspathURL

Description

URL to the class path for custom procedures.

Default value

file:/// [plan-home]/devkits/integration/examples/classes/

Unica Plan | umoConfiguration | campaignIntegration

The properties in this category specify options for the Unica Campaign integration.

defaultCampaignPartition

Description

When Unica Plan is integrated with Unica Campaign, this parameter specifies the default Unica Campaign partition if the campaign-partition-id is not defined in the project template.

Default value

`partition1`

webServiceTimeoutInMilliseconds

Description

Added for Web Service integration API calls. This parameter is used as a timeout for web services API calls.

Default value

`1800000 milliseconds (30 minutes)`

Unica Plan | umoConfiguration | reports

These properties specify information about reports that are used by Unica Plan.

reportsAnalysisSectionHome

Description

Indicates the home directory for the Analysis Section reports. The value for Cognos reports must be `/content/folder[@name='Affinium Plan']`. The value for BIRT reports must be Affinium Plan.

Default value

`/content/folder[@name='Affinium Plan']`

reportsAnalysisTabHome

Description

Indicates the home directory for the Analysis Tab reports. The value for Cognos reports must be `/content/folder[@name='Affinium Plan - Object Specific Reports']`. The value for BIRT reports must be `Affinium Plan - Object Specific Reports`

Default value

`/content/folder[@name='Affinium Plan - Object Specific Reports']`

cacheListOfReports

Description

This parameter enables caching of a list of reports on object instance's analysis page.

Valid values

`True` | `False`

Default value

`False`

Unica Plan | umoConfiguration | invoiceRollup

The properties in this category specify options for invoice rollups.

invoiceRollupMode

Description

Specifies how rollups occur. Acceptable values follow.

Valid values

- `immediate`: rollups occur every time that an invoice is marked PAID.
- `schedule`: rollups occur on a scheduled basis.

If this parameter is set to `schedule`, the system uses the following parameters to determine when rollups occur.

- `invoiceRollupScheduledStartTime`
- `invoiceRollupScheduledPollPeriod`

Default value

`immediate`

`invoiceRollupScheduledStartTime`

Description

If **`invoiceRollupMode`** is `schedule`, this parameter is used as follows.

- If this parameter contains a value (for example, 11:00 pm), that value is the start time for the schedule to start.
- If this parameter is undefined, the rollup schedule starts when the server starts.

If **`invoiceRollupMode`** is `immediate`, this parameter is not used.

Default value

`11:00 pm`

`invoiceRollupScheduledPollPeriod`

Description

If **`invoiceRollupMode`** is `schedule`, this parameter specifies the poll period in seconds for rollup to occur.

If **`invoiceRollupMode`** is `immediate`, this parameter is not used.

Default value

`3600 (1 hour)`

Unica Plan | umoConfiguration | database

These properties specify information about the database that is used for Unica Plan.

fileName

Description

Path to file for loading data sources using JNDI lookup.

Default value

`plan_datasources.xml`

sqlServerSchemaName

Description

Specifies the database schema to use. This parameter applies only if you are using SQL Server for your Unica Plan database.

Default value

`dbo`

db2ServerSchemaName



Important: Changes to the default value supplied for this parameter are not recommended.

Description

Used internally by Unica applications.

Default value

`blank`

thresholdForUseOfSubSelects

Description

Specifies the number of records beyond which a subquery must be used in the IN clause of SQL (for listing pages) instead of the actual entity IDs in the IN clause. Setting this parameter improves performance for Unica Plan installations that have a large application data set. As a best practice, do not change this value unless you encounter performance issues. If this parameter is missing or commented out, the database behaves as if the threshold is set to a large value.

Default value

3000 (records)

commonDataAccessLayerFetchSize**Description**

This parameter specifies resultset fetch size for certain performance sensitive, critical queries.

Default value

0

commonDataAccessLayerMaxResultSetSize**Description**

This parameter specifies maximum resultset size for certain performance sensitive, critical queries.

Default value

-1

useDBSortForAllList**Description**

This parameter is used to configure ALL Unica Plan List Handlers. Use another **useDBSortFor<module>List** parameter to override the paging behavior of a particular list.

Valid values

- `True`: get one page of list data from the database at a time.
- `False`: cache all list data.

Default value

`True`

useDBSortForPlanList

Description

This parameter is used to configure the Plan List Handler.

Valid values

- `True`: get one page of list data from the database at a time.
- `False`: cache all list data.

Default value

`True`

useDBSortForProjectList

Description

This parameter is used to configure the Project List Handler.

Valid values

- `True`: get one page of list data from the database at a time.
- `False`: cache all list data.

Default value

`True`

useDBSortForTaskList

Description

This parameter is used to configure the Task List Handler.

Valid values

- `True`: get one page of list data from the database at a time.
- `False`: cache all list data.

Default value

`True`

useDBSortForProgramList**Description**

This parameter is used to configure the Program List Handler.

Valid values

- `True`: get one page of list data from the database at a time.
- `False`: cache all list data.

Default value

`True`

useDBSortForApprovalList**Description**

This parameter is used to configure the Approval List Handler.

Valid values

- `True`: get one page of list data from the database at a time.
- `False`: cache all list data.

Default value

`True`

useDBSortForInvoiceList**Description**

This parameter is used to configure the Invoice List Handler.

Valid values

- `True`: get one page of list data from the database at a time.
- `False`: cache all list data.

Default value

`True`

useDBSortForAlerts

Description

This parameter is used to configure the Alerts List Handler.

Valid values

- `True`: get one page of list data from the database at a time.
- `False`: cache all list data.

Default value

`True`

Unica Plan | umoConfiguration | listingPages

These properties specify information about listing items, such as marketing objects or projects, on pages in Unica Plan.

listItemsPerPage

Description

Specifies how many items (rows) are displayed in one list page. This value must be greater than 0.

Default value

10

listPageGroupSize

Description

Specifies the size of visible page numbers in the list navigator in the list page. For example, pages 1-5 is a page group. This value must be greater than 0.

Default value

5

maximumItemsToBeDisplayedInCalendar

Description

The maximum number of objects (plans, programs, projects, or tasks) the system displays on calendars. Use this parameter to limit the number of objects that display when users select the calendar view. The number 0 indicates that there is no restriction.

Default value

0

listDisplayShowAll

Description

Display "Show All" link on listing pages.

Default value

False

Valid Values

True | False

Unica Plan | umoConfiguration | objectCodeLocking

These properties specify information about object locks for plans, programs, projects, assets, and marketing objects in Unica Plan.

enablePersistentObjectLock

Description

This parameter must be set to `True` if Unica Plan is deployed in a clustered environment. The object lock information is persistent in the database.

Valid values

`True` | `False`

Default value

`False`

lockProjectCode

Description

Determines whether users can edit the Project Code or PID on the Summary tab of a project.

Valid values

- `True`: enables locking.
- `False`: disables locking.

Default value

`True`

lockProgramCode

Description

Determines whether users can edit the Program Code or PID on the Summary tab of a program.

Valid values

- `True`: enables locking.
- `False`: disables locking.

Default value

True

lockPlanCode

Description

Determines whether users can edit the Plan Code or PID on the Plan Summary tab for a plan.

Valid values

- True: enables locking.
- False: disables locking.

Default value

True

lockMarketingObjectCode

Description

Determines whether users can edit the Marketing Object Code or PID on the Summary tab of a marketing object.

Valid values

- True: enables locking.
- False: disables locking.

Default value

True

lockAssetCode

Description

Determines whether users can edit the Asset Code or PID on the Summary tab of an asset.

Valid values

- `True`: enables locking.
- `False`: disables locking.

Default value

`True`

Unica Plan | umoConfiguration | thumbnailGeneration

These properties specify information about how and when Unica Plan generates thumbnails.

trueTypeFontDir

Description

Specifies the directory where the True Type fonts are located. This parameter is required for thumbnail generation on operating systems other than Windows™ that use Aspose. For Windows™ installations, this parameter is optional.

Default value

blank

coreThreadPoolSize

Description

Specifies the number of persistent threads that are kept in the thread pool for thumbnail generator threads.

Default value

5

maxThreadPoolSize

Description

Specifies the maximum number of threads that are allowed in the thread pool for thumbnail generator threads.

Default value

10

threadKeepAliveTime**Description**

Parameter to configure the keep-alive time for thumbnail generator threads.

Default value

60

threadQueueSize**Description**

Parameter to configure the thread queue size for thumbnail generator threads.

Default value

20

disableThumbnailGeneration**Description**

Determines whether thumbnail images are generated for uploaded documents. A value of `True` enables thumbnail generation.

Default value

`False`

Valid values

`True` | `False`

markupImgQuality**Description**

Magnification or zoom factor to apply to the rendered page.

Default value

1

Unica Plan | umoConfiguration | Scheduler | intraDay

This property specifies how frequently the scheduler runs during the day.

schedulerPollPeriod

Description

Defines how frequently, in seconds, a batch job to calculate project health status runs each day.



Note: Only the daily batch job updates the project health status history, which is used by reports.

Default value

60 (seconds)

Unica Plan | umoConfiguration | Scheduler | daily

This property specifies what time the scheduler starts each day.

schedulerStartTime

Description

Defines the start time for a batch job that calculates project health status.

This job also:

- Updates the project health status history that is used by reports.
- Initiates distribution of email notifications to users who subscribe to them.



Note: The system initiates this batch job only if the calculation is not already running. Define this parameter so that the job starts at a different time than the **intraDay** parameter, and at a time when users are not likely to request this calculation manually.

Default value

11:00 pm

Unica Plan | umoConfiguration | Notifications

These properties specify information about notifications in Unica Plan, including information about the event monitor.

notifyPlanBaseURL

Description

The URL for your Unica Plan deployment, including the host name and port number. Unica Plan includes this URL in notifications that contain links to other information in Unica Plan.



Note: Do not use "localhost" as a server name unless your mail client and Unica Plan server are running on same server.

Default value

`http://<server>:<port>/plan/affiniumplan.jsp`

notifyDelegateClassName

Description

The fully qualified Java™ class name of the delegate implementation to be instantiated by the service. This class must implement the `com.unicacorp.afc.service.IServiceImpl` interface. Defaults to a local implementation if not specified.

Default value

blank

notifyIsDelegateComplete

Description

Optional Boolean string that indicates whether the delegate implementation is complete. Defaults to `True` if not specified.

Default value

`True`

Valid Values

`True` | `False`

notifyEventMonitorStartTime

Description

Specifies when the event notification monitor process begins for the first time after Unica Plan starts. Format the value according to the short version of the `java.text.DateFormat` class for the current locale. For example, in US English locale, a valid string might be `11:45 pm`.

Default value

Blank (Immediately after Unica Plan is started.)

notifyEventMonitorPollPeriod

Description

Defines the approximate time, in seconds, for the event monitor to sleep between polls. Events accumulate in the event queue between polling periods; shorter polling periods process notifications sooner, but impose more system overhead. If you erase the default and leave the value blank, the poll period defaults to a short period, usually under a minute.

Default value

5 (seconds)

notifyEventMonitorRemoveSize

Description

Specifies the number of events to remove from the queue in one shot. The event monitor removes events from the event queue in the increments that are specified by this value until none are left.



Note: You can set this value to a number other than 1 to increase event processing performance. However, if the service host goes down before removed events are processed, there is a risk of event loss.

Default value

10

alertCountRefreshPeriodInSeconds

Description

Specifies, in seconds, the system-wide alert count refresh period for the alerts count. This count displays near the top of the navigation bar after a user logs in.



Note: Changing the refresh period to poll faster can have performance implications in a multi-user environment.

Default value

180 (3 minutes)

Unica Plan | umoConfiguration | Notifications | Email

These properties specify information about email notifications in Unica Plan.

notifyEMailMonitorStartTime

Description

Specifies when the email monitor process runs for the first time after Unica Plan starts. Format the value according to the short version of the `java.text.DateFormat` class for the current locale. For example, in US English locale, a valid string might be `11:59 pm`.

Default value

Blank (Immediately after Unica Plan starts.)

notifyEMailMonitorPollPeriod

Description

Defines the approximate time, in seconds, for the email monitor to sleep between polls.



Note: As with events, email messages accumulate in the queue between polling periods; shorter polling times send email messages sooner, but can increase system overhead.

Default value

60 (seconds)

notifyEMailMonitorJavaMailSession

Description

JNDI name of an existing, initialized JavaMail™ Session to use for email notifications. If not specified and the delegate is marked `Complete`, then the JavaMail™ host parameter must be supplied so Unica Plan can create a session.

Default value

blank

notifyEMailMonitorJavaMailProtocol

Description

Specifies the mail server transport protocol to use for email notifications.

Default value

smtp

notifyEMailMonitorRemoveSize

Description

Specifies the number of email messages to remove from queue at one time. The email monitor continues to remove messages from the email queue incrementally until none remain.



Note: You can set this value to a number other than 1 to increase email processing performance. However, if the service host goes down before removed email messages are processed, there is a risk of message loss.

Default value

10 (messages)

notifyEMailMonitorMaximumResends

Description

Specifies the maximum number of times the system attempts to send an email message that failed in the first attempt to send it. When a send fails, the email is put back into the queue until it reaches the maximum number of attempts that are allowed by this parameter.

For example, **notifyEMailMonitorPollPeriod** is set to poll every 60 seconds. Setting the **notifyEMailMonitorMaximumResends** property to 60 attempts causes the email monitor to resend a failed message one time in each poll

(every minute), for up to 1 hour. A value of 1440 (24x60) causes the email monitor to try every minute for up to 24 hours.

Default value

1 (attempt)

showUserNameInEmailNotificationTitle

Description

Specifies whether the Unica Plan notification and alert systems includes the user name in the **From** field of email notifications.



Note: This setting is applicable only to email messages sent by the notification and alert systems in Unica Plan.

Valid values

- `True`: Unica Plan appends the user name to the title of the message and displays both in the **From** field of the email
- `False`: Unica Plan displays only the message title in the **From** field

Default value

`False`

notifyEMailMonitorJavaMailDebug

Description

Specifies whether JavaMail™ debug mode is set.

Valid values

- `True`: enables JavaMail™ debug.
- `False`: disables debug tracing.

Default value

False

Unica Plan | umoConfiguration | Notifications | project

These properties specify information about project alarms in Unica Plan.

notifyProjectAlarmMonitorStartTime

Description

Specifies when the project alarm monitors run for the first time after Unica Plan starts. Format the value according to the short version of the `java.text.DateFormat` class for the current locale. For example, in US English locale, a valid string might be `11:59 pm`. If you erase the default and leave the value blank, this monitor starts immediately after you create it.

Default value

`10:00 pm`

notifyProjectAlarmMonitorPollPeriod

Description

Defines the approximate time, in seconds, for the project and program alarm monitors to sleep between polls.

Default value

Blank (60 seconds)

notifyProjectAlarmMonitorScheduledStartCondition

Description

Defines the number of days before the start date of a project for Unica Plan to send notifications to users.



Note: If this value is `-1`, then Unica Plan does not send these notifications.

Default value

1 (day)

notifyProjectAlarmMonitorScheduledEndCondition

Description

Defines the number of days before the end date of a project for Unica Plan to send end notifications to users.



Note: If this value is -1 , then Unica Plan does not send these notifications.

Default value

3 (days)

notifyProjectAlarmMonitorTaskScheduledStartCondition

Description

Defines the number of days before the start date of a task for Unica Plan to send start notifications to users.



Note: If this value is -1 , then Unica Plan does not send these notifications.

Default value

1 (day)

notifyProjectAlarmMonitorTaskScheduledEndCondition

Description

Defines the number of days before the end date of a task for Unica Plan to send end notifications to users.



Note: If this value is -1 , then Unica Plan does not send these notifications.

Default value

3 (days)

notifyProjectAlarmMonitorTaskLateCondition**Description**

Defines the number of days after the start date of a task for Unica Plan to send users notification that a task did not start.



Note: If this value is -1 , then Unica Plan does not send these notifications.

Default value

3 (days)

notifyProjectAlarmMonitorTaskOverdueCondition**Description**

Defines the number of days after the end date of a task for Unica Plan to send users notification that a task did not finish.



Note: If this value is -1 , then Unica Plan does not send these notifications.

Default value

3 (days)

notifyProjectAlarmMonitorTaskScheduledMilestoneCondition**Description**

Defines the number of days before the start date of a milestone task for Unica Plan to send notifications.



Note: If this value is -1 , then Unica Plan does not send these notifications.

Default value

1 (day)

Unica Plan | umoConfiguration | Notifications | projectRequest

These properties specify information about project request alarms in Unica Plan.

notifyRequestAlarmMonitorLateCondition

Description

Defines the number of days for Unica Plan to send a notification that the request is late.



Note: If this value is -1 , then Unica Plan does not send these notifications.

Default value

3 (days)

notifyRequestAlarmMonitorScheduledEndCondition

Description

Defines the number of days before the end date of a request for Unica Plan to send end notifications to users.



Note: If this value is -1 , then Unica Plan does not send these notifications.

Default value

1 (day)

Unica Plan | umoConfiguration | Notifications | program

The properties in this category specify options for program notification schedules.

notifyProgramAlarmMonitorScheduledStartCondition**Description**

Defines the number of days before the start date of a program that Unica Plan sends start notifications to users.



Note: If this value is -1, then Unica Plan does not send these notifications.

Default value

1 (day)

notifyProgramAlarmMonitorScheduledEndCondition**Description**

Defines the number of days before the end date of a program that Unica Plan sends end notifications to users.



Note: If this value is -1, then Unica Plan does not send these notifications.

Default value

3 (days)

Unica Plan | umoConfiguration | Notifications | marketingObject

These properties specify information about marketing object alarms in Unica Plan.

notifyComponentAlarmMonitorScheduledStartCondition

Description

Specifies the number of days before the start date of a marketing object for Unica Plan to send start notifications to users.



Note: If this value is -1 , then Unica Plan does not send these notifications.

Default value

1 (day)

notifyComponentAlarmMonitorScheduledEndCondition

Description

Specifies the number of days before the end date of a marketing object for Unica Plan to send end notifications to users.



Note: If this value is -1 , then Unica Plan does not send these notifications.

Default value

3 (days)

Unica Plan | umoConfiguration | Notifications | approval

These properties specify information about approval alarms in Unica Plan.

notifyApprovalAlarmMonitorStartTime

Description

Specifies when the approval alarm monitor begins processing for the first time after Unica Plan starts. Format the value according to the short version of the `java.text.DateFormat` class for the current locale. For example, in US English

locale, a valid string might be 11:59 pm. If you delete the default and leave this value blank, the monitor starts immediately after it is created.



Note: For best results, configure the alarm monitors to start during off-peak hours and stagger their start times to spread out the data processing load.

Default value

9:00 pm

notifyApprovalAlarmMonitorPollPeriod

Description

Specifies the approximate time, in seconds, for the approval alarm monitor to sleep between polls.

Default value

Blank (60 seconds)

notifyApprovalAlarmMonitorLateCondition

Description

Specifies the number of days after the start date of an approval for the system to begin notifying users that the approval is late.



Note: If this value is -1, then Unica Plan does not send these notifications.

Default value

3 (days)

notifyApprovalAlarmMonitorScheduledEndCondition

Description

Specifies the number of days before the end date of an approval for the system to begin sending end notifications to users.



Note: If this value is `-1`, then Unica Plan does not send these notifications.

Default value

`1 (day)`

Unica Plan | umoConfiguration | Notifications | asset

These properties specify information about asset alarms in Unica Plan.

notifyAssetAlarmMonitorStartTime

Description

Specifies when the asset alarm monitor process runs for the first time after Unica Plan starts. Format the value according to the short version of the `java.text.DateFormat` class for the current locale. For example, in US English locale, a valid string might be `11:59 pm`. If you delete the default and leave this value blank, the monitor starts immediately after it is created.



Note: For best results, configure the alarm monitors to start during off-peak hours and stagger their start times to spread out the data processing load.

Default value

`11:00 pm`

notifyAssetAlarmMonitorPollPeriod

Description

Specifies the time, in seconds, for the asset alarm monitor to sleep between polls.

Default value

Blank (60 seconds)

notifyAssetAlarmMonitorExpirationCondition**Description**

Specifies the number of days before an asset is going to expire for Unica Plan to notify users that the asset is about to expire.



Note: If this value is -1, Unica Plan does not check for expiration.

Default value

5 (days)

Unica Plan | umoConfiguration | Notifications | invoice

These properties specify information about invoice alarms in Unica Plan.

notifyInvoiceAlarmMonitorStartTime**Description**

Specifies when the invoice alarm monitor process runs for the first time after Unica Plan starts. Format the value according to the short version of the `java.text.DateFormat` class for the current locale. For example, in US English locale, a valid string might be `11:59 pm`. If you delete the default and leave the value blank, the monitor starts immediately after you create it.



Note: For best results, configure the alarm monitors to start during off-peak hours and to stagger their start times to spread out the data processing load.

Default value

9:00 pm

notifyInvoiceAlarmMonitorDueCondition

Description

Specifies the number of days before the due date for Unica Plan to notify users that an invoice is due.



Note: If this value is -1 , then Unica Plan does not send these notifications.

Default value

5 (days)

Unica Campaign configuration properties

The configuration properties for Unica Campaign are located at **Settings > Configuration**.

Campaign

To specify the locales and component applications that your installation supports, choose **Settings > Configuration**, then click the Unica Campaign category.

currencyLocale

Description

The `currencyLocale` property is a global setting that controls how currency is displayed in the Unica Campaign web application, regardless of the display locale.



Important: No currency conversion is performed by Unica Campaign when the display locale changes (for example, if the multi-locale feature is implemented and the display locale changes based on user-specific locales). You must be aware that when a locale is switched, for example, from English US, in which a currency amount is, for example, US\$10.00, to a French locale, the currency amount



is unchanged (10,00) even if the currency symbol changes with the locale.

Default value

en_US

supportedLocales**Description**

The `supportedLocales` property specifies the locales or language-locale pairs that Unica Campaign supports. The value of this property is set by the installer when you install Unica Campaign. For example: de,en,fr,ja,es,ko,pt,it,zh,ru.

Default value

All languages/locales into which Unica Campaign has been localized.

defaultLocale**Description**

The `defaultLocale` property specifies which of the locales specified in the `supportedLocales` property is considered the default display locale for Unica Campaign. The value of this property is set by the installer when you install Unica Campaign.

Default value

en

acoInstalled**Path****Description**

The `acoInstalled` property specifies whether Unica Optimize is installed.

When Unica Optimize is installed and configured, set the value to `yes`, which causes the Unica Optimize process to be displayed in flowcharts. If the value

is `true` and Unica Optimize is not installed or configured, the process is displayed but disabled (grayed out).

Default value

`false`

Valid Values

`false` and `true`

collaborateInstalled

Description

The `collaborateInstalled` property specifies whether Unica Collaborate is installed. When Unica Collaborate is installed and configured, set the value to `true`, which causes the Unica Collaborate features to be available in the Unica Campaign user interface.

Default value

`false`

Valid Values

`true` | `false`

Campaign | FlowchartEvents

The properties in this category pertain to Unica Director.

enableEvents

Configuration category

`Affinium|Campaign|FlowchartEvents`

Description

This property is used for publishing flowchart execution details to Unica Director. User will need to set this to Yes for publishing flowchart events.

Default value

No

Campaign | FlowchartEvents | ActiveMQ

The properties in this category pertain to Unica Director.

url

Configuration category

Affinium|Campaign|FlowchartEvents|ActiveMQ

Description

Specify the activeMQ listener url.

Default value

None

Platform User with Data Sources for ActiveMQ Credentials

Configuration category

Affinium|Campaign|FlowchartEvents|ActiveMQ

Description

Specify the Unica Platform user name that contains the datasource with the name specified under the configuration property ActiveMQ.

Default value

None

Data Source For ActiveMQ message broker credentials

Configuration category

Affinium|Campaign|FlowchartEvents|ActiveMQ

Description

Specify the name of the dataSource that holds the credentials.

Default value

ACTIVEMQ_CRED_DS

queueName

Configuration category

Affinium|Campaign|FlowchartEvents|ActiveMQ

Description

This mentions the queue name used to publish the flowchart information from Campaign. Please do not modify this.

Default value

flowchartInfo-campaign

Campaign | collaborate

The properties in this category pertain to Unica Collaborate configuration.

CollaborateIntegrationServicesURL

Description

The `CollaborateIntegrationServicesURL` property specifies the server and port number of Unica Collaborate. This URL is used by Unica Campaign when a user publishes a flowchart to Unica Collaborate.

Default value

```
http://localhost:7001/collaborate/services/  
CollaborateIntegrationServices1.0
```

Campaign | navigation

Some of the properties in this category are used internally and should not be changed.

welcomePageURI

Configuration category

Campaign|navigation

Description

The `welcomePageURI` property is used internally by other applications. It specifies the Uniform Resource Identifier of the Unica Campaign index page. You should not change this value.

Default value

No default value defined.

seedName**Configuration category**

`Campaign|navigation`

Description

The `seedName` property is used internally by other applications. You should not change this value.

Default value

No default value defined.

type**Configuration category**

`Campaign|navigation`

Description

The `type` property is used internally by other applications. You should not change this value.

Default value

No default value defined.

httpPort**Configuration category**

`Campaign|navigation`

Description

This property specifies the port used by the Unica Campaign web application server. If your installation of Unica Campaign uses a port that is different from the default, you must edit the value of this property.

Default value

7001

httpsPort

Configuration category

`Campaign|navigation`

Description

If SSL is configured, this property specifies the port used by the Unica Campaign web application server for secure connections. If your installation of Unica Campaign uses a secure port that is different from the default, you must edit the value of this property.

Default value

7001

serverURL

Configuration category

`Campaign|navigation`

Description

The `serverURL` property specifies the URL used by Unica Campaign. If your installation of Unica Campaign has a URL that is different from the default, you should edit the value as follows:

```
http://machine_name_or_IP_address:port_number/context-root
```

If users access Unica Campaign with the Chrome browser, use the fully qualified domain name (FQDN). If the FQDN is not used, the Chrome browser cannot access the product URLs.

Default value

```
http://localhost:7001/Campaign
```

logoutURL**Configuration category**

```
Campaign|navigation
```

Description

The `logoutURL` property is used internally to call the logout handler of the registered application if the user clicks the logout link. Do not change this value.

serverURLInternal**Configuration category**

```
Campaign|navigation
```

Description

The `serverURLInternal` property specifies the URL for the Unica Campaign web application when SiteMinder is used; this property is also used for internal communication with other Unica applications, such as IBM eMessage and Unica Interact. If the property is empty, the value in the `serverURL` property is used. Modify this property if you need internal application communication to be http and external communication to be https. If you use SiteMinder, you must set this value to the URL for the Unica Campaign web application server, formatted as follows:

```
http://machine_name_or_IP_address:port_number/context-root
```

Default value

No default value defined.

campaignDetailPageURI

Configuration category

Campaign|navigation

Description

The `campaignDetailPageURI` property is used internally by other applications. It specifies the Uniform Resource Identifier of the Unica Campaign detail page. You should not change this value.

Default value

campaignDetails.do?id=

flowchartDetailPageURI

Configuration category

Campaign|navigation

Description

The `flowchartDetailPageURI` property is used to construct a URL to navigate to the details of a flowchart in a specific campaign. You should not change this value.

Default value

flowchartDetails.do?campaignID=&id=

schedulerEditPageURI

Configuration category

Campaign|navigation

Description

This property is used to construct a URL to navigate to the Scheduler page. Do not change this value.

Default value

jsp/flowchart/scheduleOverride.jsp?taskId=

offerDetailPageURI

Configuration category

Campaign|navigation

Description

The `offerDetailPageURI` property is used to construct a URL to navigate to the details of a specific offer. You should not change this value.

Default value

offerDetails.do?id=

offerlistDetailPageURI

Configuration category

Campaign|navigation

Description

The `offerlistDetailPageURI` property is used to construct a URL to navigate to the details of a specific offer list. You should not change this value.

Default value

displayOfferList.do?offerListId=

mailingDetailPageURI

Configuration category

Campaign|navigation

Description

This property is used to construct a URL to navigate to the mailing details page for IBM eMessage. Do not change this value.

Default value

view/MailingDetails.do?mailingId=

optimizeDetailPageURI

Configuration category

Campaign|navigation

Description

This property is used to construct a URL to navigate to Unica Optimize details page. Do not change this value.

Default value

optimize/sessionLinkClicked.do?optimizeSessionID=

optimizeSchedulerEditPageURI

Configuration category

Campaign|navigation

Description

This property is used to construct a URL to navigate to the Unica Optimize Scheduler edit page. Do not change this value.

Default value

optimize/editOptimizeSchedule.do?taskID=

displayName

Configuration category

Campaign|navigation

Description

The `displayName` property specifies the link text used for the Unica Campaign link in the drop-down menu that exists in the GUI of each product.

Default value

Campaign

Campaign | caching

Certain objects, such as offers, are cached in the web application server to improve response times in the Unica Campaign user interface. The `Campaign|caching` configuration properties specify the length of time that cached data is retained. Smaller values result in more frequent cache updates, which can adversely affect performance by consuming processing resources on both the web server and the database.

offerTemplateDataTTLSeconds

Configuration category

`Campaign|caching`

Description

The `offerTemplateDataTTLSeconds` property specifies the length of time, in seconds, that the system retains the Offer Template cache data (Time to Live). An empty value means the cache data is never purged.

Default value

600 (10 minutes)

campaignDataTTLSeconds

Configuration category

`Campaign|caching`

Description

The `campaignDataTTLSeconds` property specifies the length of time, in seconds, that the system retains the Unica Campaign cache data (Time to Live). An empty value means the cache data is never purged.

Default value

600 (10 minutes)

sessionDataTTLSeconds

Configuration category

Campaign | caching

Description

The `sessionDataTTLSeconds` property specifies the length of time, in seconds, that the system retains the Session cache data (Time to Live). An empty value means the cache data is never purged.

Default value

600 (10 minutes)

folderTreeDataTTLSeconds

Configuration category

Campaign | caching

Description

The `folderTreeDataTTLSeconds` property specifies the length of time, in seconds, that the system retains the Folder Tree cache data (Time to Live). An empty value means the cache data is never purged.

Default value

600 (10 minutes)

attributeDataTTLSeconds

Configuration category

Campaign | caching

Description

The `attributeDataTTLSeconds` property specifies the length of time, in seconds, that the system retains the Offer Attribute cache data (Time to Live). An empty value means the cache data is never purged.

Default value

600 (10 minutes)

initiativeDataTTLSeconds

Configuration category

Campaign|caching

Description

The `initiativeDataTTLSeconds` property specifies the length of time, in seconds, that the system retains the Initiative cache data (Time to Live). An empty value means the cache data is never purged.

Default value

600 (10 minutes)

offerDataTTLSeconds

Configuration category

Campaign|caching

Description

The `offerDataTTLSeconds` property specifies the length of time, in seconds, that the system retains the Offer cache data (Time to Live). An empty value means the cache data is never purged.

Default value

600 (10 minutes)

segmentDataTTLSeconds

Configuration category

Campaign|caching

Description

The `segmentDataTTLSeconds` property specifies the length of time, in seconds, that the system retains the Segment cache data (Time to Live). An empty value means the cache data is never purged.

Default value

600 (10 minutes)

Campaign | partitions

This category contains properties to configure Unica Campaign partitions, including the default partition, which is named partition1.

One category should be created for each Unica Campaign partition. This section describes the properties in the partition[n] category, which apply to all partitions that you configure in Unica Campaign.

Campaign | partitions | partition[n] | Deliver

Define properties in this category to define characteristics of recipient lists and specify the location of resources that upload the lists to IBM Hosted Services.

DeliverPluginJarFile

Description

Complete path to the location of the file that operates as the Recipient List Uploader (RLU). This plug-in to Unica Campaign uploads OLT data and associated metadata to the remote services hosted by HCL. The location that you specify must be the full local directory path in the file system for the computer that hosts the Unica Campaign web application server.

The HCL installer populates this setting automatically for the default partition when you run the installer. For other partitions, you must configure this property manually. Because there is only one RLU for each IBM eMessage installation, all partitions must specify the same location for the RLU.

Do not change this setting unless HCL instructs you to do so.

Default value

No default value defined.

Valid Values

Full local directory path to where you installed the Unica Campaign web server.

defaultSeedInterval

Description

The number of messages between seed messages if `defaultSeedType` is `Distribute list`.

Default value

1000

defaultSeedType

Description

The default method that IBM eMessage uses to insert seed addresses into a recipient list.

Default value

`Distribute IDS`

Valid Values

- `Distribute IDS` - Distribute IDs evenly, based on the size of the recipient list and the number of seed addresses available, inserts seed addresses at equal intervals throughout the entire recipient list.
- `Distribute list` - Insert seed address for every `defaultSeedInterval` IDs in main list. Inserts the entire list of available seed addresses at specified intervals throughout the recipient list. You must specify the interval between insertion points.

oltTableNamePrefix

Description

Used in the generated schema for the output list table. You must define this parameter.

Default value

OLT

Valid Values

The prefix can contain no more than 8 alphanumeric or underscore characters, and must start with a letter.

oltDimTableSupport

Description

This configuration parameter controls the ability to add dimension tables to output list tables (OLT) created in the IBM eMessage schema. Dimension tables are required to use advanced scripting for email to create data tables in email messages.

The default setting is `False`. You must set this property to `True` so that marketers can create dimension tables when they use the IBM eMessage process to define a recipient list. For more information about creating data tables and working with advanced scripts for email, see the IBM eMessage User's Guide.

Default value

False

Valid Values

True | False

Campaign | partitions | partition[n] | IBM eMessage | contactAndResponseHistTracking

Use the properties in this category to configure IBM eMessage offer integration with Unica Campaign for the current partition.

etlEnabled

Description

Unica Campaign uses its own ETL process to extract, transform, and load offer response data from the IBM eMessage tracking tables into the Unica Campaign contact and response history tables.

The ETL process coordinates information across the necessary tables, including `UA_UsrResponseType` (Unica Campaign response types) and `UA_RespTypeMapping` (mapping of response types between Unica Campaign and IBM eMessage).

Setting the value to `Yes` ensures that information about IBM eMessage offer contact and response history is coordinated between Unica Campaign and IBM eMessage. For example, email response data will be included in Unica Campaign reports.



Note: You must also set `Unica Campaign | partitions | partition[n] | server | internal | eMessageInstalled` to `Yes` for this partition or the ETL process will not run.



Tip: If you want to monitor the progress of the ETL, enable `Unica Campaign | monitoring | monitorEnabledForEmessage`.

Default value

No

Valid values

Yes | No

runOnceADay

Description

Indicate whether the ETL process should run only once a day.

If the value is `Yes`: You must specify a **startTime**; the ETL job then runs until all of the records are processed; and the **sleepIntervallInMinutes** is ignored.

If the value is `No`: The ETL job starts as soon as the Campaign web server starts. The ETL job stops after all of the records are processed, then waits for the time specified by **`sleepIntervallnMinutes`**.

Default value

No

Valid values

Yes | No

batchSize**Description**

The ETL process uses this parameter to fetch records that have been downloaded by the RCT into the local IBM eMessage system tables. Because large values can impact performance, the list of available values is restricted to the valid values shown below. If you anticipate large volumes of records, adjust the **`batchSize`** together with the **`sleepIntervallnMinutes`** to process records at regular intervals.

Default value

100

Valid values

100 | 200 | 500 | 1000

sleepIntervallnMinutes**Description**

Specify the interval in minutes between ETL jobs. This option determines the wait time after a job finishes. The ETL process waits for this duration before starting the next job. Multiple jobs can run synchronously and there may be multiple ETL jobs per partition.

If **`runOnceADay`** is `Yes`, you cannot set a sleep interval.

Default value

60

Valid values

Positive integers

startTime**Description**

Specify a time to start the ETL job. You must use the English locale format to specify the start time.

Default value

12:00:00 AM

Valid valuesAny valid time in the format `hh:mm:ss AM/PM`**notificationScript****Description**

An optional executable or script file that is run after each ETL job is done. For example, you might want to be notified of the success or failure of each ETL job, for monitoring purposes. The notification script runs every time the ETL job for a given partition finishes running.

The parameters passed in to this script are fixed and cannot be changed. The following parameters can be used by the script:

- `etlStart`: The start time of ETL in number of milliseconds.
- `etlEnd`: The end time of ETL in number of milliseconds.
- `totalCHRecords`: Total number of contact records processed.
- `totalRHRecords`: Total number of response history records processed.
- `executionStatus`: Execution status of the ETL with value 1 (failed) or 0 (succeeded).

Default value

No default value defined.

Valid values

Any valid path that the Unica Campaign server can access with Read and Execute permissions. For example: `D:\myscripts\scriptname.exe`

Campaign | partitions | partition[n] | Engage

These properties control authentication and data exchange between Unica Campaign and Engage if the products are integrated.

To access these properties, choose **Settings > Configuration**. If your Unica Campaign installation has multiple partitions, set these properties for each partition that uses the integration.

Service URL

Configuration category

Campaign | partitions | partition[n] | Engage

Description

The `Service URL` indicates the URL where Unica Campaign can access the IBM® Engage application. The Engage Org Admin must provide this value.

Default value

<none>

Example

`https://engageapi.abc01.com/`

OAuth URL Suffix

Configuration category

Campaign | partitions | partition[n] | Engage

Description

The `OAuth URL Suffix` specifies the authentication token for the Engage APIs.

Default value

oauth/token

API URL Suffix**Configuration category**

Campaign | partitions | partition[n] | Engage

Description

The `API URL Suffix` is set to `XMLAPI` to ensure that Unica Campaign uses the Engage XML APIs. Best practice is to leave this set to the default value.

Default value

XMLAPI

Platform User with Data Sources for Engage Credentials**Configuration category**

Campaign | partitions | partition[n] | Engage

Description

The `Platform User with Data Sources for Engage Credentials` indicates the name of the Unica Platform user account that is allowed to connect to the IBM® Engage server. This user account contains the data sources that provide Engage credentials. Typically, `asm_admin` is used.

Default value

No default value defined.

Valid values

The Unica Platform user account that contains the data sources for Engage integration credentials.

Data Source for Client ID

Configuration category

Campaign | partitions | partition[n] | Engage

Description

The `Data Source for Client ID` value must exactly match the name of the Engage Client ID data source that was created for the user account that connects to the IBM® Engage server (**Platform User with Data Sources for Engage Credentials**). In other words, the value must match what is set up as the datasource for the Unica Platform user. Best practice is to leave this set to the default value.

Default value

ENGAGE_CLIENT_ID_DS

Data Source for Client Secret

Configuration category

Campaign | partitions | partition[n] | Engage

Description

The `Data Source for Client Secret` value must exactly match the name of the Engage Client Secret data source that was created for the user account that connects to the IBM® Engage server (**Platform User with Data Sources for Engage Credentials**). Best practice is to leave this set to the default value.

Default value

ENGAGE_CLIENT_SECRET_DS

Data Source for Client Refresh Token

Configuration category

Campaign | partitions | partition[n] | Engage

Description

The `Data Source for Client Refresh Token` value must exactly match the name of the Engage Client Refresh Token data source that was created for the user account that connects to the IBM® Engage server (**Platform User with Data Sources for Engage Credentials**). Best practice is to leave this set to the default value.

Default value

ENGAGE_CLIENT_REF_TOK_DS

Data Source for File Transfer Credentials**Configuration category**

Campaign | partitions | partition[n] | Engage

Description

The `Data Source for File Transfer Credentials` indicates the name of the data source that provides the credentials for FTP communication between Campaign and Engage. This value must exactly match the name of the Engage FTP data source that was created for the user account that connects to the IBM® Engage server (**Platform User with Data Sources for Engage Credentials**). Best practice is to leave this set to the default value.

Default value

ENGAGE_FTP_DS

Host Name for File Transfer**Configuration category**

Campaign | partitions | partition[n] | Engage

Description

The `Host Name for File Transfer` indicates the host name of the Engage FTP server where Campaign uploads the contact list in TSV format. This file gets deleted automatically after it is uploaded into a contact list.

Default value

<none>

Valid values

Any valid address in the list of IBM® Marketing Cloud FTP addresses.. For example: `transfer2.silverpop.com`

Port Number for File Transfer

Configuration category

Campaign | partitions | partition[n] | Engage

Description

The `Port Number for File Transfer` indicates the port number for the FTP server that is specified in **Host Name for File Transfer**.

Default value

22

Valid values

Any valid FTP port number

Use proxy for ServiceURL

Description

Determine if you use proxy for ServiceURL. If you select `Yes`, your connection uses the proxy server. Proxy server details can be configured under Campaign | proxy. If you select `No`, a proxy server is not used to connect to Engage.

Default value

No

Valid values

Yes, No

Use proxy for FTP

Description

Determine if you use proxy for FTP. If you select `Yes`, your connection to the Engage FTP server uses the proxy server. Proxy server details can be configured under Campaign | proxy. If you select `No`, a proxy server is not used to connect to the Engage FTP server.

Default value

No

Valid values

Yes, No

allowableFailurePercentage**Description**

When a campaign contact list is processed in Engage, an error is returned to Campaign if a contact fails for any reason. Use the `allowableFailurePercentage` property to specify the percentage of failed records that are allowed before the campaign process fails. If the percentage of failed records is greater than the configured `allowableFailurePercentage`, the process fails.

If the percentage of failed records is less than or equal to the configured `allowableFailurePercentage`, the process does not fail. Duplicate records are considered as valid records and so they do not affect the `allowableFailurePercentage` for a process box. All valid records are imported into Engage.

The percentage of failed records is calculated as $([TOTAL_ROWS - TOTAL_VALID] / TOTAL_ROWS) * 100$.

Any warnings and errors for the process are logged in the `ImportErrors` log file. You can delete this file at regular intervals. The `ImportErrors` log file is located in the `<Campaign_home>/logs` folder.

Default value

0

Valid values

Integers between 0-100.

Campaign | partitions | partition[n] | Engage |
contactAndResponseHistTracking

These properties specify the ETL of events that are downloaded from UBX in the Unica Campaign history tables.

To access these properties, choose **Settings > Configuration**. If your Unica Campaign installation has multiple partitions, set these properties for each partition that uses the integration.

etlEnabled

Description

Determine whether you want to enable the ETL transfer of data from the events table in the Unica Campaign history table.

Default value

No

Valid values

Yes, No

runOnceADay

Description

Determine whether the ETL runs once a day. It can run repeatedly if you specify the `sleepIntervallnMinutes` property. If `runOnceADay` is set to `yes`, ETL runs once a day at the specified time.

Valid values

Yes, No

batchSize

Description

The number of records that are processed in one ETL cycle.

Default value

100

Valid values

100, 200, 500, 1000, 10000, 100000

sleepIntervallInMinutes

Description

Specify the number of minutes the ETL waits it runs again. This value is used when `runOnceADay` is set to `No`.

Default value

60

Valid values

Positive integers.

startTime

Description

When `runOnceADay` is set to `Yes`, this property determines the ETL run start.

Default value

12:00:00 AM

Valid values

Any valid time in the format `hh:mm:ss AM/PM`.

notificationScript

Description

Enter any script that can run after the ETL execution is complete.

Default value

No default value defined.

Valid values

Any valid path that the Campaign server can access with Read and Execute permissions. Example: `D:\myscripts\scriptname.exe`

Campaign | partitions | partition[n] | UBX

These properties control authentication and data exchange between Unica Campaign, Engage, and UBX if the products are integrated.

To access these properties, choose **Settings > Configuration**. If your Unica Campaign installation has multiple partitions, set these properties for each partition that uses the integration.

API URL

Description

Specify the UBX Server API URL.

Data Source for UBX Endpoint Authorization key

Description

Specify the datasource name that contains the authorization key for the Unica Campaign registered endpoint. For example, `UBX_DS`.

Platform User with Data Sources for UBX Credentials

Description

Specify the Platform user name that contains the datasource with the name specified under the configuration property **Data Source for UBX Endpoint Authorization key**.

Use proxy for API URL

Description

Determine if you want to use a proxy server for the UBX connection. If you select `Yes`, the proxy server details are configured under Campaign | proxy.

Campaign | partitions | partition[n] | UBX | Event Download Schedule

These properties specify the schedule for when events are downloaded from UBX into Unica Campaign.

To access these properties, choose **Settings > Configuration**. If your Unica Campaign installation has multiple partitions, set these properties for each partition that uses the integration.

Event Download Enabled

Description

Determine if you want to enable events from UBX to download to the events table in the Unica Campaign system schema.

Default value

No

Valid values

Yes, No

runOnceADay

Description

Determine if the download should occur on a daily basis. It can run repeatedly if you specify the `sleepIntervallnMinutes` property.

sleepIntervallnMinutes

Description

Specify the number of minutes the download waits before executing again.
This value is used when `runOnceADay` is set to `No`.

startTime

Description

When `runOnceADay` is set to `Yes`, this property determines when the event download starts.

Campaign | partitions | partition[n] | Coremetrics

The properties in this category specify integration settings for Digital Analytics and Unica Campaign for the selected partition.

If your Unica Campaign installation has multiple partitions, set these properties for each partition that you want to affect. For these properties to take effect, `UC_CM_integration` must be set to `Yes` for the partition (under `partitions | partition[n] | server | internal`).

ServiceURL

Description

The `ServiceURL` specifies the location of the Digital Analytics integration service that provides the integration point between Digital Analytics and Unica Campaign. Note that the default port for `https` is `443`.

Default value

```
https://export.coremetrics.com/eb/segmentapi/1.0/api.do
```

Valid values

The only supported value for this release is the default value shown above.

CoremetricsKey

Description

Unica Campaign uses the `CoreMetricsKey` to map IDs exported from Digital Analytics to the corresponding Audience ID in Unica Campaign. The value defined for this property must exactly match the value used in the translation table.

Default value

`registrationid`

Valid values

The only supported value for this release is `registrationid`.

ClientID**Description**

Set this value to the unique Digital Analytics Client ID assigned to your company.

Default value

No default value defined.

TranslationTableName**Description**

Specify the name of the translation table being used to translate Digital Analytics keys to Unica Campaign Audience IDs. For example, `Cam_CM_Trans_Table`. If you do not specify a table name, an error will occur if users run a flowchart that uses Digital Analytics segments as input, because without the table name, Unica Campaign does not know how to map IDs from one product to the other.



Note: When you map or re-map a translation table, the **Table Name** assigned in the Table Definition dialog must exactly match (including case) the `TranslationTableName` defined here.

Default value

No default value defined.

ASMUserForCredentials

Description

The `ASMUserForCredentials` property specifies which Unica account is allowed to access the Digital Analytics integration service. See below for additional information.

If no value is specified, Unica Campaign checks the currently logged-in user's account to see if the `ASMDatasourceForCredentials` value is specified as a data source. If it is, then access is allowed. If not, access is denied.

Default value

`asm_admin`

ASMDatasourceForCredentials

Description

The `ASMDatasourceForCredentials` property identifies the data source assigned to the Unica Platform account specified in the **ASMUserForCredentials** setting. The default is `UC_CM_ACCESS`. This "data source for credentials" is the mechanism that Unica Platform uses to store the credentials that provide access to the integration service.

Although a default value of `UC_CM_ACCESS` is supplied, a data source of that name is not provided, nor do you have to use that name.



Important: You must choose **Settings > Users**, select the user specified in `ASMUserForCredentials`, click the **Edit Data Sources** link, and add a new data source whose name exactly matches the value defined here (for example, `UC_CM_ACCESS`). For Data Source Login and Data Source Password, use the credentials associated with your Digital Analytics Client ID. For information about data sources, user accounts, and security, see the *Unica Platform Administrator's Guide*

Default value

UC_CM_ACCESS

Campaign | partitions | partition[n] | reports

The **Campaign | partitions | partition[n] | reports** property defines the different types of folders for reports.

offerAnalysisTabCachedFolder

Description

The `offerAnalysisTabCachedFolder` property specifies the location of the folder that contains the specification for bursted (expanded) offer reports listed on the Analysis tab when you reach it by clicking the Analysis link on the navigation pane. The path is specified by using the XPath notation.

Default value

```
/content/folder[@name='Affinium Campaign - Object Specific Reports']/folder[@name='offer']/folder[@name='cached']
```

segmentAnalysisTabOnDemandFolder

Description

The `segmentAnalysisTabOnDemandFolder` property specifies the location of the folder that contains the segment reports listed on the Analysis tab of a segment. The path is specified by using the XPath notation.

Default value

```
/content/folder[@name='Affinium Campaign - Object Specific Reports']/folder[@name='segment']/folder[@name='cached']
```

offerAnalysisTabOnDemandFolder

Description

The `offerAnalysisTabOnDemandFolder` property specifies the location of the folder that contains the offer reports listed on the Analysis tab of an offer. The path is specified by using the XPath notation.

Default value

```
/content/folder[@name='Affinium Campaign - Object Specific Reports']/folder[@name='offer']
```

segmentAnalysisTabCachedFolder**Description**

The `segmentAnalysisTabCachedFolder` property specifies the location of the folder that contains the specification for bursted (expanded) segment reports listed on the Analysis tab when you reach it by clicking the Analysis link on the navigation pane. The path is specified by using the XPath notation.

Default value

```
/content/folder[@name='Affinium Campaign - Object Specific Reports']/folder[@name='segment']
```

analysisSectionFolder**Description**

The `analysisSectionFolder` property specifies the location of the root folder where report specifications are stored. The path is specified by using the XPath notation.

Default value

```
/content/folder[@name='Affinium Campaign']
```

campaignAnalysisTabOnDemandFolder**Description**

The `campaignAnalysisTabOnDemandFolder` property specifies the location of the folder that contains the campaign reports listed on the Analysis tab of a campaign. The path is specified by using the XPath notation.

Default value

```
/content/folder[@name='Affinium Campaign - Object Specific
Reports']/folder[@name='campaign']
```

campaignAnalysisTabCachedFolder**Description**

The `campaignAnalysisTabCachedFolder` property specifies the location of the folder that contains the specification for bursted (expanded) campaign reports listed on the Analysis tab when you reach it by clicking the Analysis link on the navigation pane. The path is specified by using the XPath notation.

Default value

```
/content/folder[@name='Affinium Campaign - Object Specific
Reports']/folder[@name='campaign']/folder[@name='cached']
```

campaignAnalysisTabEmessageOnDemandFolder**Description**

The `campaignAnalysisTabEmessageOnDemandFolder` property specifies the location of the folder that contains the IBM eMessage reports listed on the Analysis tab of a campaign. The path is specified by using the XPath notation.

Default value

```
/content/folder[@name='Affinium Campaign']/folder[@name='eMessage
Reports']
```

campaignAnalysisTabInteractOnDemandFolder**Description**

Report server folder string for Unica Interact reports.

Default value

```
/content/folder[@name='Affinium Campaign']/folder[@name='Interact
Reports']
```

Availability

This property is applicable only if you install Unica Interact.

interactiveChannelAnalysisTabOnDemandFolder**Description**

Report server folder string for Interactive Channel analysis tab reports.

Default value

```
/content/folder[@name='Affinium Campaign - Object Specific Reports']/
folder[@name='interactive channel']
```

Availability

This property is applicable only if you install Unica Interact.

Campaign | partitions | partition[n] | validation

The Validation Plugin Development Kit (PDK), delivered with Unica Campaign, allows third parties to develop custom validation logic for use in Unica Campaign. Properties in the `partition[n] > validation` category specify the classpath and class name of the custom validation program, and an optional configuration string.

validationClass**Description**

The `validationClass` property specifies the name of the class used for validation in Unica Campaign. The path to the class is specified in the `validationClasspath` property. The class must be fully qualified with its package name.

For example:

```
com.unica.campaign.core.validation.samples.SimpleCampaignValidator
```

indicates the `SimpleCampaignValidator` class from the sample code.

This property is undefined by default, which causes Unica Campaign to perform no custom validation.

Default value

No default value defined.

validationConfigString**Description**

The `validationConfigString` property specifies a configuration string that is passed into the validation plugin when Unica Campaign loads it. The use of the configuration string may vary, depending on the plugin used.

This property is undefined by default.

Default value

No default value defined.

validationClasspath**Description**

The `validationClasspath` property specifies the path to the class used for custom validation in Unica Campaign.

- Use either a full path or a relative path. If the path is relative, the behavior depends on the application server that is running Unica Campaign. WebLogic uses the path to the domain work directory, which by default is `c:\bea\user_projects\domains\mydomain`.
- If the path ends in a slash (forward slash / for UNIX™ or backslash \ for Windows™), Unica Campaign assumes that it points to the location of the Java™ plug-in class that should be used.
- If the path does not end in a slash, Unica Campaign assumes that it is the name of a .jar file that contains the Java™ class. For example, the value `/<CAMPAIGN_HOME>/devkits/validation/lib/validator.jar` is the path on a UNIX™ platform that points to the JAR file that is provided with the plug-in developer's kit.

This property is undefined by default, which causes the property to be ignored.

Default value

No default value defined.

Campaign | partitions | partition[n] | audienceLevels | audienceLevel

Do not edit properties in this category. These properties are created and populated when a user creates audience levels on the Administration page in Unica Campaign.

numFields

Description

This property indicates the number of fields in the audience level. Do not edit this property.

Default value

No default value defined.

audienceName

Description

This property indicates the audience name. Do not edit this property.

Default value

No default value defined.

Campaign | partitions | partition[n] | audienceLevels | audienceLevel
| field[n]

Properties in the this category define an audience level field. These properties are populated when a user creates audience levels on the Administration page in Unica Campaign You should not edit properties in this category.

type

Description

The `partition[n] > audienceLevels > audienceLevel > field[n] > type` property is populated when a user creates audience levels on the Administration page in Unica Campaign. You should not edit this property.

Default value

No default value defined.

name

Description

The `partition[n] > audienceLevels > audienceLevel > field[n] > name` property is populated when a user creates audience levels on the Administration page in Unica Campaign. You should not edit this property.

Default value

No default value defined.

Campaign | partitions | partition[n] | dataSources

The properties in `Campaign|partitions|partition[n]|dataSources` determine how Unica Campaign interacts with databases, including its own system tables, for the specified partition.

These properties specify the databases that Unica Campaign can access and they control many aspects of how queries are formed.

Each data source that you add in Unica Campaign is represented by a category under `Campaign|partitions|partition[n]|dataSources|<data-source-name>`.



Note: The Unica Campaign system tables data source for each partition must be named `UA_SYSTEM_TABLES` in Unica Platform, and every Unica Campaign partition must have a `dataSources | UA_SYSTEM_TABLES` category on the Configuration page.

New category name

Configuration category

*Campaign|partitions|partition[n] |
dataSources|dataSourceName*

Description

Use the `New category name` field when you create a data source by clicking on one of the provided templates. The provided templates are indicated by italics and parentheses, for example (DB2® Template). Enter a category name to identify the data source, such as DB2_Customers. After you save a new category, it appears in the navigation tree. You can change its properties as needed. The properties that are available depend on which template you selected. All of the possible properties for all templates are listed below in alphabetical order.

AccessLibrary

Description

Unica Campaign chooses its data source access library according to the data source type. For example, `libora4d.so` is used for Oracle connectivity, while `libdb24d.so` is used for DB2® connectivity. In most cases, the default selections are appropriate. However, the `AccessLibrary` property can be changed if the default value proves to be incorrect in your Unica Campaign environment. For example, 64-bit Unica Campaign provides two ODBC access libraries: one appropriate for ODBC data sources compatible with the unixODBC implementation (`libodb4d.so`) and the other compatible with the DataDirect implementation (`libodb4dDD.so`, used by Unica Campaign to access, for example, Teradata).

AliasPrefix

Description

The `AliasPrefix` property specifies the way Unica Campaign forms the alias name that Unica Campaign creates automatically when using a dimension table and writing to a new table.

Note that each database has a maximum identifier length; check the documentation for the database you are using to be sure that the value you set does not exceed the maximum identifier length for your database.

Default value

A

Additional libraries for AIX**Description**

Unica Campaign includes two additional libraries for AIX ODBC driver managers that support the ODBC ANSI API rather than the ODBC Unicode API:

- `libodb4dAO.so` (32- and 64-bit): ANSI-only library for unixODBC-compatible implementations
- `libodb4dDDAO.so` (64-bit only): ANSI-only library for DataDirect-compatible implementations

If you determine that the default access library must be overridden, set this parameter (for example, to `libodb4dDD.so`, overriding the default selection of `libodb4d.so`).

Default value

No default value defined.

AllowBaseJoinsInSelect**Description**

This property determines whether Unica Campaign attempts to do a SQL join of base tables (from the same data source) used in a Select process; otherwise, the equivalent join is done on the Unica Campaign server.

Default value

TRUE

Valid Values

TRUE | FALSE

AllowSegmentUsingSQLCase

Configuration category

*Campaign|partitions|partition[n] |
dataSources|dataSourcename*

Description

This property specifies whether the Segment process consolidates multiple SQL statements into a single SQL statement, when specific configuration conditions are met.

Setting this property to `TRUE` results in significant performance improvements when all of the following conditions are met:

- Segments are mutually exclusive.
- All segments come from a single table.
- Criteria for each segment are based on the macro language.

In this case, Unica Campaign generates a single SQL `CASE` statement to perform segmentation, followed by segment-by-field processing on the Unica Campaign application server.

Default value

TRUE

Valid Values

TRUE | FALSE

AllowTempTables

Configuration category

`Campaign|partitions|partition[n]|
dataSources|dataSourcename`

Description

This property specifies whether Unica Campaign creates temporary tables in the database. Creating temporary tables can significantly improve the performance of campaigns.

When the value is `TRUE`, temporary tables are enabled. Each time a query is issued against the database (for example, by the Segment process), the resulting IDs are written to a temporary table in the database. When an additional query is issued, Unica Campaign can use that temporary table to retrieve rows from the database.

A number of Unica Campaign operations, such as `useInDbOptimization`, rely on the ability to create temp tables. If temporary tables are not enabled, Unica Campaign retains the selected IDs in the Unica Campaign server memory. The additional query retrieves IDs from the database and matches them to the IDs in server memory. This can negatively impact performance.

You must have appropriate privileges to write in the database to use temporary tables. Privileges are determined by the database login that you provide when you connect to the database.

Default value

`TRUE`



Note: Typically, you set **AllowTempTables** to `TRUE`. To override the value for a specific flowchart, open the flowchart in Edit mode, select **Admin**  **>** **Advanced settings**, click the **Server optimization** tab, and select **Disallow use of temp tables for this flowchart**.

ASMSaveDBAuthentication

Configuration category

```
Campaign|partitions|partition[n] |
dataSources|dataSourcename
```

Description

The `ASMSaveDBAuthentication` property specifies whether, when you log in to Unica Campaign and map a table in a data source you did not previously log in to, Unica Campaign saves your user name and password in Unica.

If you set this property to `TRUE`, Unica Campaign does not prompt you for a user name and password when you log in to the data source. If you set this property to `FALSE`, Unica Campaign prompts you for a user name and password each time you log in to the data source.

Default value

`TRUE`

Valid Values

`TRUE | FALSE`

ASMUserForDBCredentials

Configuration category

```
Campaign|partitions|partition[n] |
dataSources|dataSourcename
```

Description

The `ASMUserForDBCredentials` property specifies the Unica user name that is assigned to the Unica Campaign system user (required to access the Unica Campaign system tables).

This property must be the same user that was created as the Unica Campaign system user during installation. This property is undefined by default.

Default value

No default value defined.

BulkInsertBlockSize

Configuration category

```
Campaign|partitions|partition[n] |  
dataSources|dataSourcename
```

Description

This property defines the maximum size of a data block, in number of records, that Unica Campaign passes to the database at a time.

Default value

100

BulkInsertRequiresColumnType

Configuration category

```
Campaign|partitions|partition[n] |  
dataSources|dataSourcename
```

Description

The `BulkInsertRequiresColumnType` property is required to support DataDirect ODBC data sources only. Set this property to TRUE for DataDirect ODBC data sources when you use bulk (array) inserts. Set the property to FALSE to be compatible with most other ODBC drivers.

Default value

FALSE

BulkReaderBlockSize

Configuration category

```
Campaign|partitions|partition[n] |  
dataSources|dataSourcename
```

Description

The `BulkReaderBlockSize` property defines the size of a data block, in number of records, that Unica Campaign reads from the database at a time.

Default value

2500

ConditionalSQLCloseBracket

Configuration category

```
Campaign|partitions|partition[n] |
dataSources|dataSourcename
```

Description

The `ConditionalSQLCloseBracket` property specifies the type of bracket that is used to indicate the end of a conditional segment in raw SQL custom macros. Conditionalized segments that are enclosed in the specified open and close bracket type are used only if temp tables exist. They are ignored if there are no temp tables.

Default value

} (closing curly brace)

ConditionalSQLOpenBracket

Configuration category

```
Campaign|partitions|partition[n] |
dataSources|dataSourcename
```

Description

The `ConditionalSQLOpenBracket` property specifies the type of bracket used to indicate the start of a conditional segment in raw SQL custom macros. Conditionalized segments enclosed within the brackets specified by the `ConditionalSQLOpenBracket` and `ConditionalSQLCloseBracket` properties are used only if temp tables exist, and are ignored if there are no temp tables.

Default value

{ (opening curly brace)

ConnectionCacheSize

Configuration category

```
Campaign|partitions|partition[n] |
dataSources|dataSourcename
```

Description

The `ConnectionCacheSize` property specifies the number of connections that Unica Campaign maintains in a cache for each data source.

By default (`N=0`), Unica Campaign establishes a new connection to a data source for each operation; if Unica Campaign maintains a cache of connections and a connection is available for reuse, Unica Campaign uses the cached connection rather than establishing a new connection.

If the setting is not 0, when a process is done with a connection, Unica Campaign keeps up to the specified number of connections open for an amount of time that is specified by the `InactiveConnectionTimeout` property. After this time expires, the connections are removed from the cache and closed.

Default value

0 (zero)

DateFormat

Configuration category

```
Campaign|partitions|partition[n] |
dataSources|dataSourcename
```

Description

Unica Campaign uses the value of the `DateFormat` property to determine how to parse data in `date` formats when using the Unica Campaign macro language or when interpreting data from date columns.

Set the value of the `DateFormat` property to the format in which Unica Campaign expects to receive dates from this data source. The value must match the format that your database uses to display dates on select. For most databases, this setting is the same as the setting for the `DateOutputFormatString` property.



Note: If you use the multi-locale feature, do not use date formats that contain 3-letter months (MMM), %b (abbreviated month name), or %B (full month name). Instead, use a delimited or fixed format with a numeric value for the month.

To determine the date format that your database uses, select a date from the database. For additional information, see the following table.

Table 78. Date formats

Database	To determine the correct setting
DB2®	<p>Connect to the database from a machine that is running the Unica Campaign server. Use <code>db2test</code> in the <code>Campaign\bin</code> directory to connect and issue the following command:</p> <pre>values current date</pre> <p>If your operating system does not provide the <code>db2test</code> utility, use the <code>cxntest</code> utility to test connections to the target database.</p>
Hive-based Hadoop big data	<p>All Date strings (Date, DateFormat, DateTimeFormat, DateTimeOutputFormatString) must use the dash "-" character to format dates. Hive does not support any other characters for dates. Example: %Y-%m-%d %H:%M:%S</p>
Netezza®	<p>Connect to the database from a machine that is running the Unica Campaign server. Use <code>odbctest</code>, in the</p>

Table 78. Date formats (continued)

Database	To determine the correct setting
	<p>Campaign\bin directory, to connect and issue the following command:</p> <pre data-bbox="581 457 1300 688">CREATE TABLE date_test (f1 DATE); INSERT INTO date_test values (current_date); SELECT f1 FROM date_test;</pre> <p>Another way to select date format is to run following command:</p> <pre data-bbox="581 825 1300 951">SELECT current_date FROM ANY_TABLE limit 1;</pre> <p>where ANY_TABLE is the name of any existing table.</p>
Oracle	<p>Log in to the database from the machine that is running the Unica Campaign server. Use SQL *Plus to connect and issue the following command:</p> <pre data-bbox="581 1230 948 1255">SELECT sysdate FROM dual</pre> <p>The current date is returned in NLS_DATE_FORMAT for that client.</p>
SQL Server	<p>Connect to the database from a machine that is running the Unica Campaign listener. Use <code>odbcetest</code>, in the Campaign\bin directory, to connect and issue the following command:</p> <pre data-bbox="581 1644 818 1669">SELECT getdate()</pre> <p>If the Use regional settings when outputting currency, numbers, dates, and times option is not checked in the ODBC data source configuration, then you cannot reset the date format. In general, it is easier to leave</p>

Table 78. Date formats (continued)

Database	To determine the correct setting
	this setting cleared so that the date format configuration does not change for each language.
Teradata	<p>Teradata allows you to define the date format on a per-column basis. In addition to <code>dateFormat</code> and <code>dateOutputFormatString</code>, you must set <code>SuffixOnCreateDateField</code>. To be consistent with the system table settings, use:</p> <ul style="list-style-type: none"> • <code>SuffixOnCreateDateField = FORMAT 'YYYY-MM-DD'</code> • <code>DateFormat = DELIM_Y_M_D</code> • <code>DateOutputFormatString = %Y-%m-%d</code>

Default value

`DELIM_Y_M_D`

Valid Values

Any of the formats that are specified in the `DATE` macro

DateOutputFormatString**Configuration category**

`Campaign|partitions|partition[n]|
dataSources|dataSourcename`

Description

The `DateOutputFormatString` property specifies the format of the date datatype to be used when Unica Campaign writes any date, such as a campaign start or end date, to a database. Set the value of the `DateOutputFormatString` property to the format that the data source expects

for columns of the type `date`. For most databases, this setting is the same as the setting for the `[data_source_name] > DateFormat` property.

The `DateOutputFormatString` property can be set to any of the formats that are specified for `format_str` in the `DATE_FORMAT` macro. The `DATE_FORMAT` macro accepts two different kinds of formats. One is an identifier (for example, `DELIM_M_D_Y`, `DDMMYYYY`, the same as accepted by the `DATE` macro), while the other is a format string. The value of the `DateOutputFormatString` property must be a format string - it must not be one of the `DATE` macro identifiers. Typically, use one of the delimited formats.

You can verify whether you selected the correct format by creating a table and inserting a date in the format you selected, as described in the following procedure.

To verify `DateOutputFormatString`

1. Connect to the database using the appropriate tool, as described in the table for "Selecting a date by database".

Do not use the query tools that come with the database (such as SQL Server's Query Analyzer) to verify that dates are being sent to the database correctly. These query tools might convert the date format to something other than what Unica Campaign actually sent to the database.

2. Create a table and insert a date in the format you selected. For example, if you selected `%m/%d/%Y`:

```
CREATE TABLE date_test (F1 DATE)
INSERT INTO date_test VALUES ('03/31/2004')
```

If the database allows the `INSERT` command to complete successfully, then you selected the correct format.

Default value

`%Y/%m/%d`

DateTimeFormat

Configuration category

```
Campaign|partitions|partition[n]|
dataSources|dataSourcename
```

Description

The value of the `<data-source-name> DateTimeFormat` property specifies the format in which Unica Campaign expects to receive datetime/timestamp data from a database. It must match the format that your database uses to display datetime/timestamp data on select. For most databases, this setting is the same as the setting for `DateTimeOutputFormatString`.

Typically, you set the `DateTimeFormat` by prepending your `DateFormat` value with `DT_` after determining the `DateFormat` value as described previously.



Note: If you use the multi-locale feature, do not use date formats that contain 3-letter months (MMM), %b (abbreviated month name), or %B (full month name). Instead, use a delimited or fixed format with a numeric value for the month.

Default value

DT_DELIM_Y_M_D

Valid Values

Only delimited formats are supported, as follows:

- DT_DELIM_M_D
- DT_DELIM_M_D_Y
- DT_DELIM_Y_M
- DT_DELIM_Y_M_D
- DT_DELIM_M_Y
- DT_DELIM_D_M
- DT_DELIM_D_M_Y

DateTimeOutputFormatString

Configuration category

```
Campaign|partitions|partition[n]|
dataSources|dataSourcename
```

Description

The `DateTimeOutputFormatString` property specifies the format of the `datetime` datatype to be used when Unica Campaign writes any `datetime`, such as a campaign start or end date and time, to a database. Set the value of the `DateTimeOutputFormatString` property to the format that the data source expects for columns of the type `datetime`. For most databases, this setting is the same as the setting for the `[data_source_name] > DateTimeFormat` property.

See `DateOutputFormatString` for a method for verifying that the format you select is correct.

Default value

```
%Y/%m/%d %H:%M:%S
```

DB2NotLoggedInitially

Configuration category

```
Campaign|partitions|partition[n]|
dataSources|dataSourcename
```

Description

This property determines whether Unica Campaign uses the `not logged initially` SQL syntax when populating temporary tables in DB2®.

A value of `TRUE` disables logging for inserts into temp tables, which improves performance and decreases database resource consumption. When set to `TRUE`, if a temp table transaction fails for any reason, the table will become corrupted and must be dropped. All data previously contained in the table will be lost.

If your version of DB2® does not support the `not logged initially` syntax, set this property to `FALSE`.

If you are using a DB2® 11 user database on z/OS®, set this property to `FALSE`. If you are using DB2® 10.5 with the BLU feature ON for a user database, set both **DB2NotLoggedInitially** and **DB2NotLoggedInitiallyUserTables** to `FALSE`.

Default value

`TRUE`

Valid Values

`TRUE` | `FALSE`

DB2NotLoggedInitiallyUserTables

Configuration category

`Campaign|partitions|partition[n]|
dataSources|dataSourcename`

Description

The `DB2NotLoggedInitiallyUserTables` property determines whether Unica Campaign uses the `not logged initially` SQL syntax for inserts into DB2® user tables.

A value of `TRUE` disables logging for inserts into the user tables, which improves performance and decreases database resource consumption.

When set to `TRUE`, if a user table transaction fails for any reason, the table will become corrupted and must be dropped. All data previously contained in the table will be lost.

If you are using DB2® 10.5 with the BLU feature ON for a user database, set both **DB2NotLoggedInitially** and **DB2NotLoggedInitiallyUserTables** to `FALSE`.



Note: The **DB2NotLoggedInitiallyUserTables** property is not used for the Unica Campaign system tables.

Default value

FALSE

Valid Values

TRUE | FALSE

DefaultScale

Configuration category

*Campaign|partitions|partition[n] |
dataSources|dataSourcename*

Description

The `DefaultScale` property is used when Unica Campaign creates a database field to store numeric values from a flat file or a derived field, when using the Snapshot or Export process.

This property is not used for numeric values originating in a database table, unless the database field omits information about precision and scale.

(Precision indicates the total number of digits allowed for the field. Scale indicates the number of digits allowed to the right of the decimal point. For example, 6.789 has a precision of 4 and a scale of 3. Values obtained from a database table include information about precision and scale, which Unica Campaign uses when creating the field.)

Example: Flat files do not indicate precision and scale so you can use `DefaultScale` to specify how many places to the right of the decimal point to define for the field that is created, as shown below:

- `DefaultScale=0` creates a field with no places to the right of the decimal point (only whole numbers can be stored).
- `DefaultScale=5` creates a field with a maximum of 5 values to the right of the decimal point.

If the value set for `DefaultScale` exceeds the field's precision, `DefaultScale=0` is used for those fields. For example, if the precision is 5, and `DefaultScale=6`, a value of zero is used.

Default value

0 (zero)

DefaultTextType**Configuration category**

```
Campaign|partitions|partition[n] |  
dataSources|dataSourcename
```

Description

The `DefaultTextType` property is intended for ODBC data sources. This property tells Unica Campaign how to create text fields in the destination data source if the source text fields are from a different data source type. For example, the source text fields might be from a flat file or from a different type of DBMS. If the source text fields are from the same type of DBMS, this property is ignored and the text fields are created in the destination data source using the data types from the source text fields.

Default value

VARCHAR

Valid Values

VARCHAR | NVARCHAR

DeleteAsRecreate**Configuration category**

```
Campaign|partitions|partition[n] |  
dataSources|dataSourcename
```

Description

The `DeleteAsRecreate` property specifies whether, when an output process is configured to `REPLACE TABLE` and if `TRUNCATE` is not supported, Unica Campaign drops and recreates the table or only deletes from the table.

When the value is `TRUE`, Unica Campaign drops the table and recreates it.

When the value is `FALSE`, Unica Campaign executes a `DELETE FROM` from the table.

Default value

`FALSE`

Valid Values

`TRUE` | `FALSE`

DeleteAsTruncate

Configuration category

```
Campaign|partitions|partition[n] |
dataSources|dataSourcename
```

Description

The `DeleteAsTruncate` property specifies whether, when an output process is configured to `REPLACE TABLE`, Unica Campaign uses `TRUNCATE TABLE` or deletes from the table.

When the value is `TRUE`, Unica Campaign runs a `TRUNCATE TABLE` from the table.

When the value is `FALSE`, Unica Campaign runs a `DELETE FROM` from the table.

The default value depends on the database type.

Default value

- `TRUE` for Netezza®, Oracle, and SQLServer.
- `FALSE` for other database types.

Valid Values

TRUE | FALSE

DisallowTempTableDirectCreate

Configuration category

*Campaign|partitions|partition[n] |
dataSources|dataSourcename*

Description

This property is used by Oracle, Netezza®, and SQL Server data sources and is ignored for all other data sources.

This property specifies the way Unica Campaign adds data to a temp table.

When set to `FALSE`, Unica Campaign performs direct create-and-populate SQL syntax using one command. For example: `CREATE TABLE <table_name> AS ...` (for Oracle and Netezza) and `SELECT <field_names> INTO <table_name> ...` (for SQL Server).

When set to `TRUE`, Unica Campaign creates the temp table and then populates it directly from table to table using separate commands.

Default value

FALSE

Valid Values

TRUE | FALSE

DSN

Configuration category

*Campaign|partitions|partition[n] |
dataSources|dataSourcename*

Description

Set this property to the data source name (DSN) as assigned in your ODBC configuration for this Unica Campaign data source. For SQL server, set this property to the DSN (data source name) that was created during installation.

For Oracle and DB2®, set this property to the database name or the SID (service) name. This value is undefined by default.

Using the Unica Campaign data source configuration properties, you can specify multiple logical data sources that refer to the same physical data source. For example, you can create two sets of data source properties for the same data source, one with `AllowTempTables = TRUE` and the other with `AllowTempTables = FALSE`. Each of these data sources has a different name in Unica Campaign, but if they refer to the same physical data source they have the same DSN value.

Default value

No default value defined.

DSNUsingOSAuthentication

Configuration category

```
Campaign|partitions|partition[n] |
dataSources|dataSourcename
```

Description

The `DSNUsingOSAuthentication` property applies only when an Unica Campaign data source is SQL Server. Set the value to `TRUE` when the DSN is configured to use Windows Authentication mode.

Default value

FALSE

Valid Values

TRUE | FALSE

EnableBaseDimSelfJoin

Configuration category

```
Campaign|partitions|partition[n] |
dataSources|dataSourcename
```

Description

The `EnableBaseDimSelfJoin` property specifies whether the Unica Campaign database behavior will perform self-joins when the Base and Dimension tables are mapped to the same physical table and the Dimension is not related to the Base table on the Base table's ID field(s).

By default, this property is set to `FALSE`, and when the Base and Dimension tables are the same database table and the relationship fields are the same (for example, `AcctID` to `AcctID`), Unica Campaign assumes that you do not want to perform a join.

Default value

`FALSE`

EnableSelectDistinct

Configuration category

`Campaign|partitions|partition[n]|
dataSources|dataSourcename`

Description

The `EnableSelectDistinct` property specifies whether the internal lists of IDs for Unica Campaign are de-duplicated by the Unica Campaign server or by the database.

When the value is `TRUE`, the database performs de-duplication, and SQL queries generated against the database then have the form (when appropriate):

```
SELECT DISTINCT key FROM table
```

When the value is `FALSE`, the Unica Campaign server performs de-duplication, and SQL queries generated against the database have the form:

```
SELECT key FROM table
```

Leave the default value of `FALSE` if:

- Your database is constructed so that unique identifiers (primary keys of base tables) are already guaranteed to be de-duped.
- You want the Unica Campaign application server to perform de-duplication to reduce resource consumption/burden on the database.

Regardless of what value you specify for this property, Unica Campaign automatically ensures that keys are de-duplicated as required. This property merely controls where the de-duplication effort occurs (on the database or on the Unica Campaign server).

Default value

TRUE

Valid Values

TRUE | FALSE

EnableSelectOrderBy

Configuration category

`Campaign|partitions|partition[n] |
dataSources|dataSourcename`

Description

The `EnableSelectOrderBy` property specifies whether the internal lists of IDs for Unica Campaign are sorted by the Unica Campaign server or by the database.

When the value is `TRUE`, the database performs the sorting, and SQL queries generated against the database have the form:

```
SELECT <key> FROM <table> ORDER BY <key>
```

When the value is `FALSE`, the Unica Campaign server performs the sorting, and SQL queries generated against the database have the form:

```
SELECT <key> FROM <table>
```



Note: Only set this property to `FALSE` if the audience levels used are text strings on a non-English database. All other scenarios can use the default of `TRUE`.

Default value

`TRUE`

Valid Values

`True` | `False`

ExcludeFromTableDisplay

Configuration category

`Campaign|partitions|partition[n]|
dataSources|dataSourcename`

Description

The `ExcludeFromTableDisplay` parameter allows you to limit the database tables that are displayed during table mapping in Unica Campaign. It does not reduce the number of table names retrieved from the database. Table names that match the specified patterns are not displayed. Values for this parameter are case-sensitive.

Example: If you set the value to `sys.*`, tables with names that begin with all lower case `sys.` are not displayed.

Example: `UAC_*` (the default value for SQL Server data sources) excludes temp tables and Extract tables, when the `ExtractTablePrefix` property's value is the default value.

Example: To exclude the Unica Platform system tables, as they are not relevant when working with user data:

`DF_*,USM_*,OLS_*,QRTZ*,USCH_*,UAR_*`

Using Oracle as an example, the complete value would be:

UAC_*,PUBLIC.*,SYS.*,SYSTEM.*,DF_*,USM_*,OLS_*,QRTZ*, USCH_*,UAR_*

Default value

UAC_*,PUBLIC.*,SYS.*,SYSTEM.* (for an Oracle data source)

UAC_* (for a SQL Server data source)

UAC_*,SYSCAT.*,SYSIBM.*,SYSSTAT.* (for a DB2® data source)

ExtractTablePostExecutionSQL

Configuration category

*Campaign|partitions|partition[n] |
dataSources|dataSourcename*

Description

Use the `ExtractTablePostExecutionSQL` property to specify one or more complete SQL statements that run immediately after the creation and population of an Extract table.

Tokens available to `ExtractTablePostExecutionSQL` are described below.

Token	Description
<AMUSER>	This token is replaced with the Unica user name associated with the flowchart for which the Extract table was created.
<CAMPAIGNCODE>	This token is replaced with the code for the campaign associated with the flowchart for which the Extract table was created.
<CAMPAIGNNAME>	This token is replaced with the name of the campaign associated with the flowchart for which the Extract table was created.

Token	Description
<DBUSER>	This token is replaced with the database user name for the database where the Extract table was created.
<FLOWCHARTNAME>	This token is replaced with the name of the flowchart associated with the Extract table creation.
<KEYCOLUMNS>	This token is replaced with the Extract table column name(s).
<TABLENAME>	This token is replaced with the Extract table name.
<USER>	This token is replaced with the Unica Campaign user name of the user running the flowchart.

Default value

Not defined

Valid Values

A valid SQL statement

ExtractTablePrefix**Configuration category**

*Campaign|partitions|partition[n]|
dataSources|dataSourcename*

Description

The `ExtractTablePrefix` property specifies a string that is automatically prepended to all Extract table names in Unica Campaign. This property is

useful when two or more data sources point to the same database. For details, see the `TempTablePrefix` description.

Default value

UAC_EX

ForceNumeric

Configuration category

`Campaign|partitions|partition[n]|
dataSources|dataSourcename`

Description

The `ForceNumeric` property specifies whether Unica Campaign retrieves numeric values as the data type `double`. When the value is set to `TRUE`, Unica Campaign retrieves all numeric values as the data type `double`.

Default value

FALSE

Valid Values

TRUE | FALSE

HiveQueryMode

Configuration category

`Campaign|partitions|partition[n]|
dataSources|dataSourcename`

Description

This property is used only for Hive-based Hadoop data sources (BigDataODBCHiveTemplate). It provides a way to switch between the DataDirect and Cloudera drivers. For DataDirect, select `Native`. For Cloudera, select `SQL`.

Valid Values

Native | SQL

InactiveConnectionTimeout

Configuration category

`Campaign|partitions|partition[n]|
dataSources|dataSourcename`

Description

The `InactiveConnectionTimeout` property specifies the number of seconds an inactive Unica Campaign database connection is left open before it is closed. Setting the value to 0 disables the timeout, leaving the connection open.

Default value

120

InsertLogSize

Configuration category

`Campaign|partitions|partition[n]|
dataSources|dataSourcename`

Description

The `InsertLogSize` property specifies when a new entry is entered in the log file while the Unica Campaign Snapshot process is running. Every time the number of records written by the Snapshot process reaches a multiple of the number specified in the `InsertLogSize` property, a log entry is written. The log entries can help you determine how far a running Snapshot process has progressed. Setting this value too low may create large log files.

Default value

100000 (one hundred thousand records)

Valid Values

Positive integers

JndiName

Configuration category

*Campaign|partitions|partition[n] |
dataSources|dataSourcename*

Description

The `JndiName` property is used only when configuring the Unica Campaign system tables (not for user data sources). Set its value to the Java Naming and Directory Interface (JNDI) data source that you created in your application server (WebSphere® or WebLogic) to connect to this data source.

Default value

`campaignPartition1DS`

LoaderCommand

Configuration category

*Campaign|partitions|partition[n] |
dataSources|dataSourcename*

Description

This property specifies the command issued to invoke your database load utility in Unica Campaign. If you set this property, Unica Campaign enters the database loader utility mode for all output files from the Snapshot process that are used with the **Replace all records** settings. This property also invokes the database loader utility mode when Unica Campaign uploads ID lists into temp tables.

The valid value for this property is any full path name either to the database load utility executable or to a script that launches the database load utility. Using a script allows you to perform additional setup before invoking the load utility.



Note: If you use Unica Optimize and you are configuring loader settings for the UA_SYSTEM_TABLES datasource, there are important considerations to take into account. For example, you must use absolute paths for **LoaderCommand** and **LoaderCommandForAppend**. Read about setting up Unica Campaign to use database load utilities in the *Unica Campaign Administrator's Guide*.

Most database load utilities require several arguments to be launched successfully. These arguments can include specifying the data file and control file to load from and the database and table to load into. Unica Campaign supports the following tokens, which are replaced by the specified elements when the command is run. Consult your database load utility documentation for the correct syntax to use when invoking your database load utility.

This property is undefined by default.

Tokens available to **LoaderCommand** are described below.

Token	Description
<AMUSER>	This token is replaced with the Unica user name associated with the flowchart being run.
<CAMPAIGNCODE>	This token is replaced with the code for the campaign associated with the flowchart.
<CAMPAIGNNAME>	This token is replaced with the name of the campaign associated with the flowchart being run.
<CONTROLFILE>	This token is replaced with the full path and file name to the temporary control file that Unica Campaign generates according to the

Token	Description
	template that is specified in the LoaderControlFileTemplate property.
<DATABASE>	This token is replaced with the name of the data source that Unica Campaign is loading data into. This is the same data source name used in the category name for this data source.
<DATAFILE>	This token is replaced with the full path and file name to the temporary data file created by Unica Campaign during the loading process. This file is in the Unica Campaign Temp directory, UNICA_ACTMPDIR.
<DBUSER>	This token is replaced with the database user name for the database.
<DSN>	This token is replaced with the value of the DSN property. If the DSN property is not set, the <DSN> token is replaced by the data source name used in the category name for this data source (the same value used to replace the <DATABASE> token).
<FLOWCHARTNAME>	This token is replaced with the name of the flowchart being run.

Token	Description
<NUMFIELDS>	This token is replaced with the number of fields in the table.
<PASSWORD>	This token is replaced with the database password from the current flowchart connection to the data source.
<TABLE>	This token is obsolete. Use <TABLENAME> instead.
<TABLENAME>	This token is replaced with the database table name that Unica Campaign is loading data into. This is the target table from your Snapshot process or the name of the Temp Table being created by Unica Campaign.
<USER>	This token is replaced with the database user from the current flowchart connection to the data source.

Default value

No default value defined.

Valid Values

Any full path name either to the database load utility executable or to a script that launches the database load utility.

LoaderCommandForAppend**Configuration category**

```
Campaign|partitions|partition[n] |
dataSources|dataSourcename
```

Description

This property specifies the command issued to invoke your database load utility for appending records to a database table in Unica Campaign. If you set this property, Unica Campaign enters database loader utility mode for all output files from the Snapshot process that are used with the **Append Records** settings.

This property is specified as a full path name either to the database load utility executable or to a script that launches the database load utility. Using a script allows you to perform additional setup before invoking the load utility.

Most database load utilities require several arguments to be successfully launched. These can include specifying the data file and control file to load from and the database and table to load into. The tokens are replaced by the specified elements when the command is run.

Consult your database load utility documentation for the correct syntax to use when invoking your database load utility.

This property is undefined by default.

Tokens available to **LoaderCommandForAppend** are described below.

Token	Description
<AMUSER>	This token is replaced with the Unica user name associated with the flowchart being run.
<CAMPAIGNCODE>	This token is replaced with the code for the campaign associated with the flowchart being run.

Token	Description
<CAMPAIGNNAME>	This token is replaced with the name of the campaign associated with the flowchart being run.
<CONTROLFILE>	This token is replaced with the full path and file name to the temporary control file that Unica Campaign generates according to the template that is specified in the LoaderControlFileTemplate property.
<DATABASE>	This token is replaced with the name of the data source that Unica Campaign is loading data into. This is the same data source name used in the category name for this data source.
<DATAFILE>	This token is replaced with the full path and file name to the temporary data file created by Unica Campaign during the loading process. This file is in the Unica Campaign Temp directory, UNICA_ACTMPDIR.
<DBUSER>	This token is replaced with the database user name for the database where the temp tables were created.
<DSN>	This token is replaced with the value of the DSN property. If the DSN

Token	Description
	property is not set, the <DSN> token is replaced by the data source name used in the category name for this data source (the same value used to replace the <DATABASE> token).
<FLOWCHARTNAME>	This token is replaced with the name of the flowchart associated with the temp table creation.
<NUMFIELDS>	This token is replaced with the number of fields in the table.
<PASSWORD>	This token is replaced with the database password from the current flowchart connection to the data source.
<TABLE>	This token is obsolete. Use <TABLENAME> instead.
<TABLENAME>	This token is replaced with the database table name that Unica Campaign is loading data into. This is the target table from your Snapshot process or the name of the Temp Table being created by Unica Campaign.
<USER>	This token is replaced with the database user from the current flowchart connection to the data source.

Default value

No default value defined.

LoaderControlFileTemplate**Configuration category**

```
Campaign|partitions|partition[n]|
dataSources|dataSourcename
```

Description

This property specifies the full path and file name to the control file template that is configured for Unica Campaign. The path to the template is relative to the current partition. For example: `loadscript.db2`.

When this property is set, Unica Campaign dynamically builds a temporary control file based on the specified template. The path and name of this temporary control file is available to the `<CONTROLFILE>` token that is available to the **LoaderCommand** property.

Before you use Unica Campaign in the database loader utility mode, you must configure the control file template that is specified by this parameter. The control file template supports the following tokens, which are dynamically replaced when the temporary control file is created by Unica Campaign.

For the correct syntax required for your control file, see your database loader utility documentation.

This property is undefined by default.

Tokens available to **LoaderControlFileTemplate** are the same as those described for the **LoaderCommand** property, plus the following special tokens, which are repeated once for each field in the outbound table.

Token	Description
<DBCOLUMNNUMBER>	This token is replaced with the column ordinal in the database.

Token	Description
<FIELDLENGTH>	This token is replaced with the length of the field being loaded into the database.
<FIELDNAME>	This token is replaced with the name of the field being loaded into the database.
<FIELDNUMBER>	This token is replaced with the number of the field being loaded into the database.
<FIELDTYPE>	This token is replaced with the literal CHAR(). The length of this field is specified between the parentheses (). If your database does not understand the field type CHAR, you can manually specify the appropriate text for the field type and use the <FIELDLENGTH> token. For example, for SQLSVR and SQL2000 you would use SQLCHAR(<FIELDLENGTH>).
<NATIVETYPE>	This token is replaced with the actual database type that this field is loaded into.
<xyz>	This token places the specified character(s) on all fields being loaded into the database, except the last. A typical use is < , > which repeats a comma for all fields except the last.
<~xyz>	This token places the specified characters only on the last repeated line.
<!xyz>	This token places the specified character(s), including the angle brackets < >, on all lines.

Default value

No default value defined.

LoaderControlFileTemplateForAppend

Configuration category

```
Campaign|partitions|partition[n] |  
dataSources|dataSourceName
```

Description

This property specifies the full path and file name to the control file template that is configured in Unica Campaign. The path to the template is relative to the current partition. For example: `loadappend.db2`

When this property is set, Unica Campaign dynamically builds a temporary control file based on the specified template. The path and name of this temporary control file is available to the `<CONTROLFILE>` token that is available to the **LoaderCommandForAppend** property.

Before you use Unica Campaign in the database loader utility mode, you must configure the control file template that is specified by this property. See your database loader utility documentation for the correct syntax required for your control file.

The available tokens are the same as the tokens for the **LoaderControlFileTemplate** property.

This property is undefined by default.

Default value

No default value defined.

LoaderDelimiter

Configuration category

```
Campaign|partitions|partition[n] |  
dataSources|dataSourceName
```

Description

This property specifies whether the temporary data file is a fixed-width or delimited flat file, and, if it is delimited, the characters that Unica Campaign uses as delimiters.

If the value is undefined, Unica Campaign creates the temporary data file as a fixed width flat file.

If you specify a value, it is used when the loader is invoked to populate a table that is known to be empty. Unica Campaign creates the temporary data file as a delimited flat file, using the value of this property as the delimiter. The delimiter is a character such as comma (,) or semi-colon (;) that separates fields in the temporary data files that are loaded into the user data source.

 **Important:** The following fields, if used, must use the same character as specified for **LoaderDelimiter**: **SuffixOnTempTableCreation**, **SuffixOnSegmentTableCreation**, **SuffixOnSnapshotTableCreation**, **SuffixOnExtractTableCreation**, **SuffixOnUserBaseTableCreation**, **SuffixOnUserTableCreation**.

 **Important:** For big data, such as Hadoop Hive or Amazon Redshift, the delimiter value must match the ROW format delimiter that was used when the big data database table was created. In this example, a comma is used: **ROW FORMAT DELIMITED FIELDS TERMINATED BY**
";"

This property is undefined by default.

Default value

No default value defined.

Valid Values

Characters, which can be enclosed in double quotation marks, if wanted. Hive-based Hadoop big data does not support the Tab (/t) character.

LoaderDelimiterAtEnd

Configuration category

```
Campaign|partitions|partition[n] |  
dataSources|dataSourceName
```

Description

Some external load utilities require that the data file be delimited and that each line end with the delimiter. To accommodate this requirement, set the **LoaderDelimiterAtEnd** value to `TRUE`, so that when the loader is invoked to populate a table that is known to be empty, Unica Campaign uses delimiters at the end of each line. For example, DB2® on Unix expects each record to be terminated by a line feed character only; Unica Campaign Unica Campaign on Windows uses carriage return and line feed characters. Putting a delimiter at the end of every record ensures that the last column in the data file will load properly.

```
FALSE
```

Default value

```
FALSE
```

Valid Values

```
TRUE | FALSE
```

LoaderDelimiterAtEndForAppend

Configuration category

```
Campaign|partitions|partition[n] |  
dataSources|dataSourceName
```

Description

Some external load utilities require that the data file be delimited and that each line end with the delimiter. To accommodate this requirement, set the **LoaderDelimiterAtEndForAppend** value to `TRUE`, so that when the loader is invoked to populate a table that is not known to be empty, Unica Campaign

uses delimiters at the end of each line. For example, DB2® on Unix expects each record to be terminated by a line feed character only; Unica Campaign on Windows uses carriage return and line feed characters. Putting a delimiter at the end of every record ensures that the last column in the data file will load properly.

Default value

FALSE

Valid Values

TRUE | FALSE

LoaderDelimiterForAppend

Configuration category

*Campaign|partitions|partition[n] |
dataSources|dataSourcename*

Description

This property specifies whether the temporary Unica Campaign data file is a fixed-width or delimited flat file, and, if it is delimited, the character or set of characters used as delimiters.

If the value is undefined, Unica Campaign creates the temporary data file as a fixed width flat file.

If you specify a value, it is used when the loader is invoked to populate a table that is not known to be empty. Unica Campaign creates the temporary data file as a delimited flat file, using the value of this property as the delimiter.

This property is undefined by default.

Default value

No default value defined.

Valid Values

Characters, which you may enclose in double quotation marks, if wanted.

LoaderPostLoadDataFileRemoveCmd

Configuration category

```
Campaign|partitions|partition[n] |
dataSources|dataSourceName
```

Description

This property is used only for Hive-based Hadoop data sources (BigDataODBC HiveTemplate). This property is used together with LoaderPreLoadDataFileCopyCmd. After data files are copied from Unica Campaign to the `/tmp` folder on the Hive-based Hadoop system, the LoaderPostLoadDataFileRemoveCmd property uses the SSH "rm" command to remove the temporary data file.

For example: `ssh mapr@example.com "rm/tmp/<DATAFILE>"`

For important information, read about exporting data from Unica Campaign to a Hive-based Hadoop system.

Default value

none

LoaderPreLoadDataFileCopyCmd

Configuration category

```
Campaign|partitions|partition[n] |
dataSources|dataSourceName
```

Description

This property is used only for Hive-based Hadoop data sources (BigDataODBC HiveTemplate). This property uses SCP to copy data from Unica Campaign to a temp folder called `/tmp` on your Hive-based Hadoop system. The location must be called `/tmp` and it must be on the Hive server (the file system location, not the HDFS location). You can either specify an SCP command or call a script that specifies the SCP command.

Example #1: `scp <DATAFILE> mapr@example.com:/tmp`

Example #2: `/opt/HCL/CampaignBigData/bin/copyToHive.sh <DATAFILE>`

In addition to this property, use `LoaderPostLoadDataFileRemove` to remove the temporary data file from the Hive server after it has been copied.

For important information, read about exporting data from Unica Campaign to a Hive-based Hadoop system.

Default value

none

LoaderNULLValueInDelimitedData

Configuration category

`Campaign|partitions|partition[n]|
dataSources|dataSourcename`

Description

This property supports null values in delimited data for database loaders, specifically Netezza®. Enter the string that represents a null value for the column.

Default value

null

LoaderUseLocaleDP

Configuration category

`Campaign|partitions|partition[n]|
dataSources|dataSourcename`

Description

This property specifies, when Unica Campaign writes numeric values to files to be loaded by a database load utility, whether the locale-specific symbol is used for the decimal point.

Set this value to `FALSE` to specify that the period (.) is used as the decimal point.

Set this value to `TRUE` to specify that the decimal point symbol appropriate to the locale is used.

Default value

`FALSE`

Valid Values

`TRUE` | `FALSE`

MaxItemsInList**Configuration category**

`Campaign|partitions|partition[n]|
dataSources|dataSourcename`

Description

Allows you to specify the maximum number of items that Unica Campaign is allowed to include in a single list in SQL (for example, the list of values following an IN operator in a WHERE clause).

Default value

1000 (Oracle only), 0 (unlimited) for all other databases

Valid Values

integers

MaxQueryThreads**Configuration category**

`Campaign|partitions|partition[n]|
dataSources|dataSourcename`

Description

This property specifies the upper limit on the number of simultaneous queries allowed to run against each database source from a single Unica Campaign flowchart. Higher values generally improve performance.

Unica Campaign runs database queries using independent threads. Because Unica Campaign processes run in parallel, it is common to have multiple queries running simultaneously against a single data source. If the number of queries to be run in parallel exceeds the `MaxQueryThreads`, the Unica Campaign server limits the number of simultaneous queries to the specified value.

The maximum value is unlimited.



Note: If `maxReuseThreads` is set to a non-zero value, it should be greater than or equal to the value of `MaxQueryThreads`.

Default value

Varies depending on the database

MaxRowFetchRecords

Configuration category

```
Campaign|partitions|partition[n]|
dataSources|dataSourceName
```

Description

For performance reasons, it is best to keep this number low.

When the selected number of IDs is less than the value specified by the `MaxRowFetchRecords` property, Unica Campaign passes the IDs to the database one at a time, in separate SQL queries. This process can be very time-consuming. If the number of selected IDs is greater than the value specified by this property, Unica Campaign uses temporary tables (if allowed on the database source), or it pulls down all the values from the table, not including any unnecessary values.

Default value

100

MaxTempTableJoinPctSelectAll

Configuration category

```
Campaign|partitions|partition[n] |  
dataSources|dataSourcename
```

Description

When a query is issued, Unica Campaign creates a temporary table on the database containing the exact list of IDs, as a result of the query. When an additional query that selects all records is issued against the database, the `MaxTempTableJoinPctSelectAll` property specifies whether a join is performed with the temporary table.

If the relative size of the temporary table (specified as a percentage) is greater than the value of the `MaxTempTableJoinPctSelectAll` property, no join is performed. All records are selected first, then unwanted records are discarded.

If the relative size of the temporary table (specified as a percentage) is less than or equal to the value of `MaxTempTableJoinPctSelectAll` property, the join is performed with the temporary table first, and then the resulting IDs are retrieved to the server.

This property is applicable only if the value of the `AllowTempTables` property is set to `TRUE`. This property is ignored if the `useInDbOptimization` property is set to `YES`.

Default value

90

Valid Values

Integers between 0-100. A value of 0 means that temporary table joins are never used; a value of 100 means that table joins are always used, regardless of the size of the temporary table.

Example

Assume that `MaxTempTableJoinPctSelectAll` is set to 90. First, you might want to select customers (`CustID`) with account balances (`Accnt_balance`) greater than \$1,000 from the database table (`Customer`).

The corresponding SQL expression generated by the Select process may look like this:

```
SELECT CustID FROM Customer
WHERE Accnt_balance > 1000
```

The Select process may retrieve 100,000 IDs from the total table size of 1,000,000, which is 10%. If temporary tables are allowed, Unica Campaign writes the selected IDs (`TempID`) into a temporary table (`Temp_table`) in the database.

Then, you might want to snapshot the selected IDs (`CustID`) together with the actual balance (`Accnt_balance`). Since the relative size of the temporary table (`Temp_table`) is less than 90 percent (`MaxTempTableJoinPctSelectAll`), the join is done with the temporary table first. The SQL expression generated by the Snapshot process may look like this:

```
SELECT CustID, Accnt_balance FROM Customer, Temp_table WHERE CustID = TempID
```

If the Select process retrieves more than 90 percent, the subsequent Snapshot process retrieves all the records, and matches them with the first set of IDs, discarding the unnecessary ones.

The SQL expression generated by the Snapshot process may look like this:

```
SELECT CustID, Accnt_balance FROM Customer
```

MaxTempTableJoinPctWithCondition

Configuration category

`Campaign|partitions|partition[n]|
dataSources|dataSourcename`

Description

When a query is issued, Unica Campaign creates a temporary table on the database containing the exact list of IDs, as a result of the query. When an additional query, selecting records with limitation conditions is issued against the database, the `MaxTempTableJoinPctWithCondition` property specifies whether a join should be performed with the temporary table.

If the relative size of the temporary table (specified as a percentage) is greater than the value of `MaxTempTableJoinPctWithCondition`, no join is performed. This avoids the overhead in the database where it may not be needed. In this case, the query is issued against the database, the resulting list of IDs retrieved, and then unwanted records are discarded as they are matched to the list in server memory.

If the relative size of the temporary table (in percentage) is less than or equal to the value of `MaxTempTableJoinPctWithCondition`, the join is done with the temporary table first, and then the resulting IDs are retrieved to the server.

This property is applicable only if the value of the `AllowTempTables` property is set to `TRUE`.

Default value

20

Valid Values

Integers between 0-100. A value of 0 means that temporary table joins are never used; a value of 100 means that table joins are always used, regardless of the size of the temporary table.

MinReqForLoaderCommand**Configuration category**

```
Campaign|partitions|partition[n] |
dataSources|dataSourcename
```

Description

Use this property to set the threshold for using the bulk loader. Unica Campaign invokes the script assigned to the `LoaderCommand` property when the number of unique IDs in the input cell exceeds the value defined here. The value of this property does not represent the number of records that will be written.

If this property is not configured, Unica Campaign assumes that the value is the default value (zero). If this property is configured but a negative value or non-integer value is set as the value, a value of zero is assumed.

Default value

0 (zero)

Valid Values

Integers

MinReqForLoaderCommandForAppend**Configuration category**

```
Campaign|partitions|partition[n] |  
dataSources|dataSourcename
```

Description

Use this property to set the threshold for using the bulk loader. Unica Campaign invokes the script assigned to the `LoaderCommandForAppend` parameter when the number of unique IDs in the input cell exceeds the value defined here. The value of this property does not represent the number of records that will be written.

If this property is not configured, Unica Campaign assumes that the value is the default value (zero). If this property is configured but a negative value or non-integer value is set as the value, a value of zero is assumed.

Default value

0 (zero)

Valid Values

Positive integers

NumberOfRetries

Configuration category

```
Campaign|partitions|partition[n] |  
dataSources|dataSourcename
```

Description

The `NumberOfRetries` property specifies the number of times Unica Campaign automatically retries a database operation on failure. Unica Campaign automatically resubmits queries to the database this number of times before reporting a database error or failure.

Default value

0 (zero)

ODBCTableTypes

Configuration category

```
Campaign|partitions|partition[n] |  
dataSources|dataSourcename
```

Description

This property is empty by default, which is appropriate for all currently supported data sources.

Default value

Not defined

Valid Values

(empty)

ODBCUnicode

Configuration category

`Campaign|partitions|partition[n]|
dataSources|dataSourcename`

Description

The `ODBCUnicode` property specifies the type of encoding used in Unica Campaign ODBC calls. It is used only with ODBC data sources and is ignored when used with Oracle or DB2® native connectivity.



Important: If this property is set to `UTF-8` or `UCS-2`, the data source's `StringEncoding` value must be set to either `UTF-8` or `WIDEUTF-8`, otherwise the `ODBCUnicode` property's setting is ignored.

Default value

disabled

Valid Values

Possible values for this property are:

- `Disabled`: Unica Campaign uses ANSI ODBC calls.
- `UTF-8`: Unica Campaign uses Unicode ODBC calls and assumes that a `SQLWCHAR` is a single byte. This is compatible with DataDirect ODBC drivers.
- `UCS-2`: Unica Campaign uses Unicode ODBC calls and assumes that a `SQLWCHAR` is 2 bytes. This is compatible with Windows™ and unixODBC ODBC drivers.

ODBCv2

Configuration category

`Campaign|partitions|partition[n]|
dataSources|dataSourcename`

Description

Use the `ODBCv2` property to specify which ODBC API specification Unica Campaign should use for the data source.

The default value of `FALSE` allows Unica Campaign to use the v3 API specification, while a setting of `TRUE` causes Unica Campaign to use the v2 API specification. Set the `ODBCv2` property to `TRUE` for data sources that do not support the ODBC v3 API specification.

When the `ODBCv2` property is set to `TRUE`, Unica Campaign does not support the ODBC Unicode API, and values other than `disabled` for the `ODBCUnicode` property are not recognized.

Default value

`FALSE`

Valid Values

`TRUE` | `FALSE`

OwnerForTableDisplay

Configuration category

`Campaign|partitions|partition[n] |
dataSources|dataSourcename`

Description

Use this property to limit the table mapping display in Unica Campaign to tables in a specified schema. For example, to specify tables in the schema "dbo", set `OwnerForTableDisplay=dbo`.

Default value

No default value defined.

PadTextWithSpaces

Configuration category

`Campaign|partitions|partition[n] |
dataSources|dataSourcename`

Description

When set to `TRUE`, the `PadTextWithSpaces` property causes Unica Campaign to pad text values with spaces until the string is the same width as the database field.

Default value

`FALSE`

Valid Values

`TRUE` | `FALSE`

PostExtractTableCreateRunScript

Configuration category

`Campaign|partitions|partition[n]|
dataSources|dataSourcename`

Description

Use this property to specify a script or executable for Unica Campaign to run after an Extract table has been created and populated.

Tokens available to **PostExtractTableCreateRunScript** are described below.

Token	Description
<DBUSER>	This token is replaced with the database user name for the database where the Extract table was created.
<AMUSER>	This token is replaced with the Unica user name associated with the flowchart for which the Extract table was created.
<CAMPAIGNNAME>	This token is replaced with the name of the campaign associated

Token	Description
	with the flowchart for which the Extract table was created.
<CAMPAIGNCODE>	This token is replaced with the code for the campaign associated with the flowchart for which the Extract table was created.
<FLOWCHARTNAME>	This token is replaced with the name of the flowchart associated with the Extract table creation.
<PASSWORD>	This token is replaced with the database password from the current flowchart connection to the data source.
<KEYCOLUMNS>	This token is replaced with the Extract table column name(s).

Default value

Not defined

Valid Values

File name of a shell script or executable

PostSegmentTableCreateRunScript**Configuration category**

```
Campaign|partitions|partition[n] |
dataSources|dataSourcename
```

Description

Specifies a script or executable that Unica Campaign runs after a Segment temp table has been created and populated.

Tokens available to **PostSegmentTableCreateRunScript** are described below.

Token	Description
<DBUSER>	This token is replaced with the database user name for the database where the Segment temp table was created.
<AMUSER>	This token is replaced with the Unica user name associated with the flowchart for which the Segment temp table was created.
<CAMPAIGNNAME>	This token is replaced with the name of the campaign associated with the flowchart for which the Segment temp table was created.
<CAMPAIGNCODE>	This token is replaced with the code for the campaign associated with the flowchart for which the Segment temp table was created.
<FLOWCHARTNAME>	This token is replaced with the name of the flowchart associated with the Segment temp table creation.
<PASSWORD>	This token is replaced with the database password from the current flowchart connection to the data source.
<KEYCOLUMNS>	This token is replaced with the Segment temp table column name(s).

Default value

Not defined

Valid Values

File name of a script or executable

PostSnapshotTableCreateRunScript**Configuration category**

*Campaign|partitions|partition[n]|
dataSources|dataSourcename*

Description

Use the **PostSnapshotTableCreateRunScript** property to specify a script or executable that Unica Campaign runs after a Snapshot table has been created and populated. The property is only called when snapshot process writes to "Extract Tables"

Tokens available to **PostSnapshotTableCreateRunScript** are described below.

Token	Description
<DBUSER>	This token is replaced with the database user name for the database where the Snapshot table was created.
<AMUSER>	This token is replaced with the Unica user name associated with the flowchart for which the Snapshot table was created.
<CAMPAIGNNAME>	This token is replaced with the name of the campaign associated with the flowchart for which the Snapshot table was created.

Token	Description
<CAMPAIGNCODE>	This token is replaced with the code for the campaign associated with the flowchart for which the Snapshot table was created.
<FLOWCHARTNAME>	This token is replaced with the name of the flowchart associated with the Snapshot table creation.
<PASSWORD>	This token is replaced with the database password from the current flowchart connection to the data source.
<KEYCOLUMNS>	This token is replaced with the Snapshot table column name(s).

Default value

Not defined

Valid Values

File name of a shell script or executable

PostTempTableCreateRunScript**Configuration category**

*Campaign|partitions|partition[n] |
dataSources|dataSourcename*

Description

Use the **PostTempTableCreateRunScript** property to specify a script or executable for Unica Campaign to run after a temp table has been created and populated in a user data source or in the system tables database.

Tokens available to **PostTempTableCreateRunScript** are described below.

Token	Description
<DBUSER>	This token is replaced with the database user name for the database where the temp tables were created.
<AMUSER>	This token is replaced with the Unica user name associated with the flowchart for which temp tables were created.
<CAMPAIGNNAME>	This token is replaced with the name of the campaign associated with the flowchart for which temp tables were created.
<CAMPAIGNCODE>	This token is replaced with the code for the campaign associated with the flowchart for which temp tables were created.
<FLOWCHARTNAME>	This token is replaced with the name of the flowchart associated with the temp table creation.
<PASSWORD>	This token is replaced with the database password from the current flowchart connection to the data source.
<KEYCOLUMNS>	This token is replaced with the temp table column name(s).

Default value

No default value defined.

PostUserTableCreateRunScript

Configuration category

*Campaign|partitions|partition[n]|
dataSources|dataSourcename*

Description

Specifies a script or executable that Unica Campaign runs after a User table has been created and populated.

Tokens available to `PostUserTableCreateRunScript` are described below.

Token	Description
<DBUSER>	This token is replaced with the database user name for the database where the User table was created.
<AMUSER>	This token is replaced with the Unica user name associated with the flowchart for which the User table was created.
<CAMPAIGNNAME>	This token is replaced with the name of the campaign associated with the flowchart for which the User table was created.
<CAMPAIGNCODE>	This token is replaced with the code for the campaign associated with the flowchart for which the User table was created.
<FLOWCHARTNAME>	This token is replaced with the name of the flowchart associated with the User table creation.

Token	Description
<PASSWORD>	This token is replaced with the database password from the current flowchart connection to the data source.
<KEYCOLUMNS>	This token is replaced with the User table column name(s).

Default value

Not defined

Valid Values

File name of a script or executable

PrefixOnSelectSQL**Configuration category**

*Campaign|partitions|partition[n]|
dataSources|dataSourcename*

Description

Use the `PrefixOnSelectSQL` property to specify a string that is automatically prepended to all `SELECT` SQL expressions generated by Unica Campaign.

This property applies only to SQL generated by Unica Campaign, and does not apply to SQL in raw SQL expressions used in the Select process.

This property is automatically added to the `SELECT` SQL expression without checking its syntax. If you use this property, make sure that it is a legal expression.

This property is undefined by default.

Tokens available to **PrefixOnSelectSQL** are described below.

Token	Description
<AMUSER>	This token is replaced with the Unica user name associated with the flowchart for which temp tables were created.
<CAMPAIGNCODE>	This token is replaced with the code for the campaign associated with the flowchart for which temp tables were created.
<CAMPAIGNNAME>	This token is replaced with the name of the campaign associated with the flowchart for which temp tables were created.
<DBUSER>	This token is replaced with the database user name for the database where the temp tables were created.
<FLOWCHARTNAME>	This token is replaced with the name of the flowchart associated with the temp table creation.
<USER>	This token is replaced with the Unica Campaign user name of the user running the flowchart.

Default value

No default value defined.

QueryThreadSleep**Configuration category**

Campaign|partitions|partition[n] |
dataSources|dataSourcename

Description

The `QueryThreadSleep` property affects the CPU utilization of the Unica Campaign server process (`UNICA_ACSVR`). When the value is `TRUE`, the thread that the Unica Campaign server process uses to check for query completion sleeps between checks. When the value is `FALSE`, the Unica Campaign server process checks continuously for query completion.

Default value

`TRUE`

ReaderLogSize

Configuration category

Campaign|partitions|partition[n] |
dataSources|dataSourcename

Description

The `ReaderLogSize` parameter defines when Unica Campaign makes a new entry in the log file when reading data from the database. Every time the number of records read from the database reaches a multiple of the number defined by this parameter, a log entry is written in the log file.

This parameter can help you determine how far a process has progressed in its run. Setting this value too low may create large log files.

Default value

1000000 (one million records)

Valid Values

Integers

SegmentTablePostExecuteSQL

Configuration category

`Campaign|partitions|partition[n]|
dataSources|dataSourcename`

Description

Use the `SegmentTablePostExecutionSQL` property to specify a complete SQL statement that Unica Campaign runs after a Segment temp table has been created and populated.

Tokens available to **SegmentTablePostExecutionSQL** are described below.

Token	Description
<AMUSER>	This token is replaced with the Unica user name associated with the flowchart for which the Segment temp table was created.
<CAMPAIGNCODE>	This token is replaced with the code for the campaign associated with the flowchart for which the Segment temp table was created.
<CAMPAIGNNAME>	This token is replaced with the name of the campaign associated with the flowchart for which the Segment temp table was created.
<DBUSER>	This token is replaced with the database user name for the database where the Segment temp table was created.
<FLOWCHARTNAME>	This token is replaced with the name of the flowchart associated with the Segment temp table creation.

Token	Description
<KEYCOLUMNS>	This token is replaced with the Segment temp table column name(s).
<TABLENAME>	This token is replaced with the Segment temp table name.
<USER>	This token is replaced with the Unica Campaign user name of the user running the flowchart.

Default value

Not defined

Valid Values

A valid SQL statement

SegmentTempTablePrefix**Description**

Sets the prefix for Segment tables created by the CreateSeg process in this data source. This property is useful when two or more data sources point to the same database. For details, see the `TempTablePrefix` description.

Default value

UACS

SnapshotTablePostExecuteSQL**Configuration category**

```
Campaign|partitions|partition[n] |
dataSources|dataSourcename
```

Description

Use the `SnapshotTablePostExecuteSQL` property to specify one or more complete SQL statements to run immediately after a Snapshot table has

been created and populated. This property is invoked only when a Snapshot process box writes out to an extract table.

Tokens available to **SnapshotTablePostExecuteSQL** are described below.

Token	Description
<AMUSER>	This token is replaced with the Unica user name associated with the flowchart for which the Snapshot table was created.
<CAMPAIGNCODE>	This token is replaced with the code for the campaign associated with the flowchart for which the Snapshot table was created.
<CAMPAIGNNAME>	This token is replaced with the name of the campaign associated with the flowchart for which the Snapshot table was created.
<DBUSER>	This token is replaced with the database user name for the database where the Snapshot table was created.
<FLOWCHARTNAME>	This token is replaced with the name of the flowchart associated with the Snapshot table creation.
<KEYCOLUMNS>	This token is replaced with the Snapshot table column name(s).
<TABLENAME>	This token is replaced with the Snapshot table name.

Token	Description
<USER>	This token is replaced with the Unica Campaign user name of the user running the flowchart.

Default value

Not defined

Valid Values

A valid SQL statement

SQLOnConnect**Configuration category**

*Campaign|partitions|partition[n] |
dataSources|dataSourcename*

Description

The `SQLOnConnect` property defines a complete SQL statement that Unica Campaign runs immediately after each database connection.

The SQL statement generated by this property is automatically passed to your database without checking its syntax. If you use this property, make sure that it is a legal expression. The string may be enclosed in quotation marks, but this is not required.

This property is undefined by default.

Tokens available to `SQLOnConnect` are described below.

Token	Description
<AMUSER>	This token is replaced with the Unica user name associated with the flowchart for which temp tables were created.

Token	Description
<CAMPAIGNCODE>	This token is replaced with the code for the campaign associated with the flowchart for which temp tables were created.
<CAMPAIGNNAME>	This token is replaced with the name of the campaign associated with the flowchart for which temp tables were created.
<DBUSER>	This token is replaced with the database user name for the database where the temp tables were created.
<FLOWCHARTNAME>	This token is replaced with the name of the flowchart associated with the temp table creation.
<USER>	This token is replaced with the Unica Campaign user name of the user running the flowchart.

Default value

No default value defined.

StringEncoding**Configuration category**

*Campaign|partitions|partition[n]|
dataSources|dataSourcename*

Description

The `StringEncoding` property specifies the character encoding of the database. When Unica Campaign retrieves data from the database, the data is transcoded from the encoding specified to the internal encoding of Unica Campaign (`UTF-8`). When Unica Campaign sends a query to the database, character data is transcoded from the internal encoding of Unica Campaign (`UTF-8`) to the encoding specified in the `StringEncoding` property.

The value of this property must match the encoding used on the database client.

Do not leave this value blank although it is undefined by default.

If you use ASCII data, set this value to `UTF-8`.

If your database client encoding is `UTF-8`, the preferred setting for this value is `WIDEUTF-8`. The `WIDE-UTF-8` setting works only if your database client is set to `UTF-8`.

If you use the `partitions > partition[n] > dataSources > data_source_name > ODBCUnicode` property, set the `StringEncoding` property to either `UTF-8` or `WIDEUTF-8`. Otherwise, the `ODBCUnicode` property value is ignored.

For a list of supported encodings, see Character encodings in Unica Campaign in the Unica Campaign Administrator's Guide.



Important: See the following sections for important exceptions and additional considerations.

Default value

No default value defined.

Database-specific considerations

This section describes how to set the correct values for DB2®, SQL Server, or Teradata databases.

DB2®

Identify the DB2® database code page and code set. For localized environments, the DB2® database must have the following configuration:

- Database code set = UTF-8
- Database code page = 1208

Set the `StringEncoding` property values in Unica Campaign to the DB2® database code set value.

Set the `DB2CODEPAGE` DB2® environment variable to the DB2® database code page value:

- On Windows™: Add the following line to the Unica Campaign Listener startup script (`<CAMPAIGN_HOME>\bin\cmpServer.bat`):

```
db2set DB2CODEPAGE=1208
```

- On UNIX™: After DB2® is started, the system administrator must type the following command from the DB2® instance user:

```
$ db2set DB2CODEPAGE=1208
```

Then start the Unica Campaign listener by running this command:

```
./rc.unica_ac start
```

This setting affects all DB2® data sources and can affect other running programs.

SQL Server

For SQL Server, use a code page instead of an iconv encoding. To determine the correct the value for the `StringEncoding` property with a SQL Server database, look up the code page that corresponds to the regional settings of the server's operating system.

For example, to use code page 932 (Japanese `Shift-JIS`):

```
StringEncoding=CP932
```

Teradata

For Teradata, you must override some default behavior. Teradata supports per-column character encoding, while Unica Campaign supports only per-data source encoding. `UTF-8` cannot be used with Unica Campaign due to a bug in the Teradata ODBC driver. Teradata sets a default character encoding for each login. You can override this using a parameter in the ODBC data source configuration on Windows™ or in the `odbc.ini` on UNIX™ platforms as follows:

```
CharacterSet=UTF8
```

The default encoding for a Teradata table is `LATIN`. Teradata has very few built-in encodings, but it supports user-defined encodings.

The default value of the `StringEncoding` property is `ASCII`.



Important: For many situations involving a UTF-8 database, you should use `WIDEUTF-8` pseudo-encoding, described in the `WIDEUTF-8` section.

WIDEUTF-8

Unica Campaign is normally responsible for transcoding between its internal encoding, `UTF-8`, and the encoding of the database. When the database is encoded in `UTF-8`, the value `UTF-8` can be specified for `StringEncoding` (except for `SQLServer`), and no transcoding will be needed. Traditionally, these have been the only viable models for Unica Campaign to access non-English data within a database.

In the 7.0 version of Unica Campaign, a new database encoding called `WIDEUTF-8` was introduced as a value for the `StringEncoding` property. By using this encoding, Unica Campaign still uses `UTF-8` to communicate with the database client, but allows the client to perform the task of transcoding between `UTF-8` and the encoding of the actual database. This enhanced version of `UTF-8` is needed to alter the widths of table column mappings so that they will be wide enough for transcoded text.



Note: The WIDEUTF-8 pseudo-encoding may be used only in the database configuration. It should not be used for any other purpose.



Note: Oracle does not support transcoding through the client.

SuffixOnAllOtherSQL

Configuration category

```
Campaign|partitions|partition[n]|
dataSources|dataSourcename
```

Description

The `SuffixOnAllOtherSQL` property specifies a string that is automatically appended to every SQL expression, generated by Unica Campaign, which are not covered by the `SuffixOnInsertSQL`, `SuffixOnSelectSQL`, `SuffixOnTempTableCreation`, `SuffixOnUserTableCreation`, or `SuffixOnUserBaseTableCreation` properties.

This property applies only to SQL generated by Unica Campaign, and does not apply to SQL in raw SQL expressions used in the Select process.

`SuffixOnAllOtherSQL` is used for the following expression types, when generated by Unica Campaign:

```
TRUNCATE TABLE table
DROP TABLE table
DELETE FROM table [WHERE ...]
UPDATE table SET ...
```

This property is automatically added to the SQL expression without checking its syntax. If you use this parameter, make sure that it is a legal expression.

The string may be enclosed in quotation marks, but this is not required.

This property is undefined by default.

Tokens available to **SuffixOnAllOtherSQL** are described below.

Token	Description
<AMUSER>	This token is replaced with the Unica user name associated with the flowchart for which temp tables were created.
<CAMPAIGNCODE>	This token is replaced with the code for the campaign associated with the flowchart for which temp tables were created.
<CAMPAIGNNAME>	This token is replaced with the name of the campaign associated with the flowchart for which temp tables were created.
<DBUSER>	This token is replaced with the database user name for the database where the temp tables were created.
<FLOWCHARTNAME>	This token is replaced with the name of the flowchart associated with the temp table creation.
<USER>	This token is replaced with the Unica Campaign user name of the user running the flowchart.

Default value

No default value defined.

SuffixOnCreateDateField**Configuration category**

`Campaign|partitions|partition[n] |
dataSources|dataSourcename`

Description

The `SuffixOnCreateDateField` property specifies a string that Unica Campaign automatically appends to any `DATE` fields in the `CREATE TABLE` SQL statement.

For example, you might set this property as follows:

```
SuffixOnCreateDateField = FORMAT 'YYYY-MM-DD'
```

If this property is undefined (the default), the `CREATE TABLE` command is unchanged.



Note: See the table in the description of the `DateFormat` property.

Default value

No default value defined.

SuffixOnExtractTableCreation

Configuration category

`Campaign|partitions|partition[n] |
dataSources|dataSourcename`

Description

Use the `SuffixOnExtractTableCreation` property to specify a string that is automatically appended to the SQL expression generated by Unica Campaign when an Extract table is created.

Tokens available to **SuffixOnExtractTableCreation** are described below.

Token	Description
<AMUSER>	This token is replaced with the Unica user name associated with the

Token	Description
	flowchart for which the Extract table was created.
<CAMPAIGNCODE>	This token is replaced with the code for the campaign associated with the flowchart for which the Extract table was created.
<CAMPAIGNNAME>	This token is replaced with the name of the campaign associated with the flowchart for which the Extract table was created.
<DBUSER>	This token is replaced with the database user name for the database where the Extract table was created.
<FLOWCHARTNAME>	This token is replaced with the name of the flowchart associated with the Extract table creation.
<KEYCOLUMNS>	This token is replaced with the Extract table column name(s).
<TABLENAME>	This token is replaced with the Extract table name.
<USER>	This token is replaced with the Unica Campaign user name of the user running the flowchart.

Default value

Not defined

Valid Values

Valid SQL

SuffixOnInsertSQL

Configuration category

```
Campaign|partitions|partition[n]|
dataSources|dataSourcename
```

Description

The `SuffixOnInsertSQL` property specifies a string that is automatically appended to all `INSERT` SQL expressions generated by Unica Campaign. This property applies only to SQL generated by Unica Campaign, and does not apply to SQL in raw SQL expressions used in the Select process.

`SuffixOnInsertSQL` is used for the following expression type, when generated by Unica Campaign:

```
INSERT INTO table ...
```

This property is automatically added to the SQL expression without checking its syntax. If you use this property, make sure that it is a legal expression. The string may be enclosed in quotation marks, but this is not required.

This property is undefined by default.

Tokens available to `SuffixOnInsertSQL` are described below.

Token	Description
<AMUSER>	This token is replaced with the Unica user name associated with the flowchart for which temp tables were created.
<CAMPAIGNCODE>	This token is replaced with the code for the campaign associated with the flowchart for which temp tables were created.

Token	Description
<CAMPAIGNNAME>	This token is replaced with the name of the campaign associated with the flowchart for which temp tables were created.
<DBUSER>	This token is replaced with the database user name for the database where the temp tables were created.
<FLOWCHARTNAME>	This token is replaced with the name of the flowchart associated with the temp table creation.
<USER>	This token is replaced with the Unica Campaign user name of the user running the flowchart.

Default value

No default value defined.

SuffixOnSegmentTableCreation**Configuration category**

*Campaign|partitions|partition[n]|
dataSources|dataSourcename*

Description

Specifies a string that is automatically appended to the SQL expression generated by Unica Campaign when a Segment temp table is created.

Tokens available to **SuffixOnSegmentTableCreation** are described below.

Token	Description
<AMUSER>	This token is replaced with the Unica user name associated with the flowchart for which the Segment temp table was created.
<CAMPAIGNCODE>	This token is replaced with the code for the campaign associated with the flowchart for which the Segment temp table was created.
<CAMPAIGNNAME>	This token is replaced with the name of the campaign associated with the flowchart for which the Segment temp table was created.
<DBUSER>	This token is replaced with the database user name for the database where the Segment temp table was created.
<FLOWCHARTNAME>	This token is replaced with the name of the flowchart associated with the Segment temp table creation.
<KEYCOLUMNS>	This token is replaced with the Segment temp table column name(s).
<TABLENAME>	This token is replaced with the Segment temp table name.
<USER>	This token is replaced with the Unica Campaign user name of the user running the flowchart.

Default value

Not defined

Valid Values

Valid SQL

SuffixOnSelectSQL**Configuration category**

*Campaign|partitions|partition[n] |
dataSources|dataSourcename*

Description

The `SuffixOnSelectSQL` property specifies a string that is automatically appended to all `SELECT` SQL expressions generated by Unica Campaign. This property applies only to SQL generated by Unica Campaign, and does not apply to SQL in "raw SQL" expressions used in the Select process.

This property is automatically added to the SQL expression without checking its syntax. If you use this property, make sure that it is a legal expression. The string may be enclosed in quotation marks, but this is not required.

This property is undefined by default.

Tokens available to **SuffixOnSelectSQL** are described below.

Token	Description
<AMUSER>	This token is replaced with the Unica user name associated with the flowchart for which temp tables were created.
<CAMPAIGNCODE>	This token is replaced with the code for the campaign associated with the flowchart for which temp tables were created.

Token	Description
<CAMPAIGNNAME>	This token is replaced with the name of the campaign associated with the flowchart for which temp tables were created.
<DBUSER>	This token is replaced with the database user name for the database where the temp tables were created.
<FLOWCHARTNAME>	This token is replaced with the name of the flowchart associated with the temp table creation.
<USER>	This token is replaced with the Unica Campaign user name of the user running the flowchart.

Default value

No default value defined.

SuffixOnSnapshotTableCreation

Configuration category

*Campaign|partitions|partition[n] |
dataSources|dataSourcename*

Description

Use the `SuffixOnSnapshotTableCreation` property to specify a string that is automatically appended to the SQL expression generated by Unica Campaign when a Snapshot table is created.

Tokens available to **SuffixOnSnapshotTableCreation** are described below.

Token	Description
<AMUSER>	This token is replaced with the Unica user name associated with the flowchart for which the Snapshot table was created.
<CAMPAIGNCODE>	This token is replaced with the code for the campaign associated with the flowchart for which the Snapshot table was created.
<CAMPAIGNNAME>	This token is replaced with the name of the campaign associated with the flowchart for which the Snapshot table was created.
<DBUSER>	This token is replaced with the database user name for the database where the Snapshot table was created.
<FLOWCHARTNAME>	This token is replaced with the name of the flowchart associated with the Snapshot table creation.
<TABLENAME>	This token is replaced with the Snapshot table name.
<USER>	This token is replaced with the Unica Campaign user name of the user running the flowchart.

Default value

Not defined

Valid Values

Valid SQL

SuffixOnTempTableCreation

Configuration category

```
Campaign|partitions|partition[n]|
dataSources|dataSourcename
```

Description

Use this property to specify a string that is automatically appended to the SQL expression generated by Unica Campaign when a temp table is created. This property applies only to SQL generated by Unica Campaign, and does not apply to SQL in "raw SQL" expressions used in the Select process. To use this property, the `AllowTempTables` property must be set to `TRUE`.

You may want to use tokens to substitute the table name and the column name(s) (`<TABLENAME>` and `<KEYCOLUMNS>`) in this SQL statement, since these are generated dynamically during the execution of the campaign.

This property is automatically added to the SQL expression without checking its syntax. If you use this property, make sure that it is a legal expression. The string may be enclosed in quotation marks, but this is not required.

This property is undefined by default.



Note: For Oracle databases, the configuration parameter is appended to the temp table creation SQL expression after the table name.

Tokens available to `SuffixOnTempTableCreation` are described below.

Token	Description
<AMUSER>	This token is replaced with the Unica user name associated with the flowchart for which temp tables were created.

Token	Description
<CAMPAIGNCODE>	This token is replaced with the code for the campaign associated with the flowchart for which temp tables were created.
<CAMPAIGNNAME>	This token is replaced with the name of the campaign associated with the flowchart for which temp tables were created.
<DBUSER>	This token is replaced with the database user name for the database where the temp tables were created.
<FLOWCHARTNAME>	This token is replaced with the name of the flowchart associated with the temp table creation.
<KEYCOLUMNS>	This token is replaced with the temp table column name(s).
<TABLENAME>	This token is replaced with the temp table name.
<USER>	This token is replaced with the Unica Campaign user name of the user running the flowchart.

Default value

No default value defined.

SuffixOnUserBaseTableCreation**Configuration category**

`Campaign|partitions|partition[n] |
dataSources|dataSourcename`

Description

Use the `SuffixOnUserBaseTableCreation` property to specify a string that is automatically appended to the SQL expression that Unica Campaign generates when a user creates a Base table (for example, in an Extract process). This property applies only to SQL generated by Unica Campaign, and does not apply to SQL in "raw SQL" expressions used in the Select process.

You may want to use tokens to substitute the table name and the column name(s) (<TABLENAME> and <KEYCOLUMNS>) in this SQL statement, since these are generated dynamically during the execution of the campaign.

This property is automatically added to the SQL expression without checking its syntax. If you use this property, make sure that it is a legal expression. The string may be enclosed in quotation marks, but this is not required.

This property is undefined by default.

Tokens available to **SuffixOnUserBaseTableCreation** are described below.

Token	Description
<AMUSER>	This token is replaced with the Unica user name associated with the flowchart for which temp tables were created.
<CAMPAIGNCODE>	This token is replaced with the code for the campaign associated with the flowchart for which temp tables were created.
<CAMPAIGNNAME>	This token is replaced with the name of the campaign associated

Token	Description
	with the flowchart for which temp tables were created.
<DBUSER>	This token is replaced with the database user name for the database where the temp tables were created.
<FLOWCHARTNAME>	This token is replaced with the name of the flowchart associated with the temp table creation.
<KEYCOLUMNS>	This token is replaced with the temp table column name(s).
<TABLENAME>	This token is replaced with the temp table name.
<USER>	This token is replaced with the Unica Campaign user name of the user running the flowchart.

Default value

No default value defined.

SuffixOnUserTableCreation**Configuration category**

```
Campaign|partitions|partition[n]|
dataSources|dataSourcename
```

Description

Use the `SuffixOnUserTableCreation` property to specify a string that is automatically appended to the SQL expression that Unica Campaign generates when a user creates a General table (for example, in a Snapshot

process). This property applies only to SQL generated by Unica Campaign, and does not apply to SQL in "raw SQL" expressions used in the Select process.

This property is automatically added to the SQL expression without checking its syntax. If you use this property, make sure that it is a legal expression. The string may be enclosed in quotation marks, but this is not required.

This property is undefined by default.

Tokens available to **SuffixOnUserTableCreation** are described below.

Token	Description
<AMUSER>	This token is replaced with the Unica user name associated with the flowchart for which temp tables were created.
<CAMPAIGNCODE>	This token is replaced with the code for the campaign associated with the flowchart for which temp tables were created.
<CAMPAIGNNAME>	This token is replaced with the name of the campaign associated with the flowchart for which temp tables were created.
<DBUSER>	This token is replaced with the database user name for the database where the temp tables were created.
<FLOWCHARTNAME>	This token is replaced with the name of the flowchart associated with the temp table creation.

Token	Description
<TABLENAME>	This token is replaced with the temp table name.

Default value

No default value defined.

SystemTableSchema**Configuration category**

*Campaign|partitions|partition[n]|
dataSources|dataSourcename*

Description

Specifies the schema used for Unica Campaign system tables.

The default value is blank. This parameter is only relevant for the `UA_SYSTEM_TABLES` data source.

This property is not required for SQL server. For other data sources, set this property to the user of the database to which you are trying to connect.

You can leave this value blank unless the `UA_SYSTEM_TABLES` data source contains multiple schemas (for example, an Oracle database used by multiple groups). In this context, "schema" indicates the initial portion of a "qualified" table name of the form `x.y`, where `x` is the schema and `y` is the unqualified table name. For example: `dbo.UA_Folder`. This terminology for this syntax differs among the different database systems supported by Unica Campaign.)

If multiple schemas exist in the system tables database, set this value to the name of the schema in which the Unica Campaign system tables were created.

Default value

No default value defined.

TableListSQL

Configuration category

```
Campaign|partitions|partition[n] |  
dataSources|dataSourceName
```

Description

Use the `TableListSQL` property to specify the SQL query to use to include synonyms in the list of tables available to map.

The default value is blank. This property is required if your data source is SQL Server and you want to be able to map synonyms in the returned table schema. This property is optional if you want to use a specific SQL query with other data sources in place of, or in addition to, the table schema information retrieved using the standard methods (such as an ODBC call or native connection).



Note: To ensure that Campaign works with SQL Server synonyms, you must set the `UseSQLToRetrieveSchema` property to `TRUE` in addition to setting this property as described here.

If you set this property with a valid SQL query, Unica Campaign issues the SQL query to retrieve the list of tables for mapping. If the query returns one column, it is treated as a column of names; if the query returns two columns, the first column is assumed to be a column of owner names, and the second column is considered to be a column of table names.

If the SQL query does not begin with an asterisk (*), Unica Campaign merges this list with the list of tables that are normally retrieved (such as through ODBC calls or native connections).

If the SQL query begins with an asterisk (*), the list returned by the SQL replaces the normal list, rather than being merged with it.

Default value

None

Valid Values

A valid SQL query

Example

If the data source is SQL Server, under normal circumstances the ODBC API call that Unica Campaign uses returns a list of tables and views, but no synonyms. To include the list of synonyms as well, set `TableListSQL` similar to the following example:

```
select B.name AS oName, A.name AS tName
from sys.synonyms A LEFT OUTER JOIN sys.schemas B
on A.schema_id = B.schema_id ORDER BY 1, 2
```

To retrieve the list of tables, views, and synonyms, avoiding the ODBC API completely, set `TableListSQL` similar to the following example:

```
*select B.name AS oName, A.name AS tName from
(select name, schema_id from sys.synonyms UNION
select name, schema_id from sys.tables UNION select name,
schema_id from sys.views) A LEFT OUTER JOIN sys.schemas B on
A.schema_id = B.schema_id ORDER BY 1, 2
```

If the data source is Oracle, you can use a query similar to the following to retrieve the list of tables, views, and synonyms in place of the data retrieved using the native connection method that looks at the `ALL_OBJECTS` view:

```
*select OWNER, TABLE_NAME from (select OWNER, TABLE_NAME
from ALL_TABLES UNION select OWNER, SYNONYM_NAME AS TABLE_NAME
FROM ALL_SYNONYMS UNION select OWNER,
VIEW_NAME AS TABLE_NAME from ALL_VIEWS) A ORDER BY 1, 2
```

TempTablePostExecuteSQL

Configuration category

`Campaign|partitions|partition[n]|
dataSources|dataSourcename`

Description

Use this property to specify a complete SQL statement that Unica Campaign runs immediately after the creation of a temporary table in a user data source or in the system tables database. For example, to improve performance, you can create an index on a temporary table immediately after its creation (see examples below). To enable the creation of temporary tables in a data source, the `AllowTempTables` property must be set to `TRUE`.

You can use tokens to substitute the table name (`<TABLENAME>`) and column names (`<KEYCOLUMNS>`) in the SQL statement, because the values are generated dynamically when the campaign runs.

This property is automatically added to the SQL expression without checking its syntax. If you use this property, make sure that it is a legal expression. You can enclose the string in quotation marks, but this is not required.

This property treats semicolons as delimiters to run multiple SQL statements. If your SQL statement contains semicolons and you want it to run as one statement, use a backslash as an escape character before the semicolons.



Note: If you are using stored procedures with this property, be sure that you use the correct syntax for your database.

Tokens available to **TempTablePostExecutionSQL** are described below.

Token	Description
<code><AMUSER></code>	This token is replaced with the Unica user name associated with the flowchart for which temp tables were created.

Token	Description
<CAMPAIGNCODE>	This token is replaced with the code for the campaign associated with the flowchart for which temp tables were created.
<CAMPAIGNNAME>	This token is replaced with the name of the campaign associated with the flowchart for which temp tables were created.
<DBUSER>	This token is replaced with the database user name for the database where the temp tables were created.
<FLOWCHARTNAME>	This token is replaced with the name of the flowchart associated with the temp table creation.
<KEYCOLUMNS>	This token is replaced with the temp table column name(s).
<TABLENAME>	This token is replaced with the temp table name.
<USER>	This token is replaced with the Unica Campaign user name of the user running the flowchart.

Default value

No default value defined.

Examples

The following value creates an index on the temp table just after its creation, to improve the data retrieval process: `CREATE INDEX IND_<TABLENAME> ON <TABLENAME> (<KEYCOLUMNS>)`

The following example for Oracle calls a stored procedure and uses backslashes to escape the semicolon: `begin dbms_stats.collect_table_stats()\; end\;`

TempTablePrefix

Configuration category

`Campaign|partitions|partition[n]|
dataSources|dataSourceName`

Description

This property specifies a string that is automatically prepended to the names of all temporary tables created by Unica Campaign. Use this property to help identify and manage temp tables. You also can use this property to cause temp tables to be created in a particular location.

For example, if the user token corresponds to a schema, you can set

```
TempTablePrefix="<USER>"
```

and all temp tables will be created in the schema of whatever user is connected to the data source.

If two or more data sources point to the same database, errors and incorrect search results can occur during flowchart runs due to usage of the same temporary tables by different process boxes and flowcharts. This situation can also occur with Extract process tables and Strategic Segment tables. To avoid this situation, use `TempTablePrefix` (or `ExtractTablePrefix` for Extract tables) to define different schemas for each data source. This approach ensures that the initial part of the name is different, so the table names will always be different.

For example, give each data source a unique TempTablePrefix such as UAC_DS1 and UAC_DS2 to distinguish between temp tables for each data source. The same concept applies if you are sharing data source schemas. For example, the following prefixes allow the temp tables to be unique for both data sources that write temp tables to the same database:

DS1 TempTablePreFix: schemaA.UAC_DS1

DS2 TempTablePreFix: schemaA.UAC_DS2

The following table describes the tokens that are available to **TempTablePrefix**.



Note: You must make sure that the final temp table name after resolving tokens does not exceed any database-specific name length restrictions.



Note: In tokens used for TempTablePrefix, any characters that are not valid for database table names will be stripped. After tokens are resolved, the resulting temp table prefixes must start with an alphabetic character, and must contain only alphanumeric characters or underscore characters. Illegal characters will be removed silently. If any resulting temp table prefix does not begin with an alphabetic character, Unica Campaign prepends the letter "U" to the prefix.

Token	Description
<AMUSER>	This token is replaced with the Unica user name associated with the flowchart for which temp tables were created.
<CAMPAIGNCODE>	This token is replaced with the code for the campaign associated

Token	Description
	with the flowchart for which temp tables were created.
<CAMPAIGNNAME>	This token is replaced with the name of the campaign associated with the flowchart for which temp tables were created.
<DBUSER>	This token is replaced with the database user name for the database where the temp tables were created.
<FLOWCHARTNAME>	This token is replaced with the name of the flowchart associated with the temp table creation.
<USER>	This token is replaced with the Unica Campaign user name of the user running the flowchart.

Default value

UAC

TempTablePreTruncateExecutionSQL

Configuration category

*Campaign|partitions|partition[n]|
dataSources|dataSourcename*

Description



Note: This property is supported only for Teradata data sources. For all other supported databases, this property should not be set.

Use this property to specify a SQL query to run before a temp table is truncated. The query that you specify can be used to negate the effect of a SQL statement specified in the **TempTablePostExecuteSQL** property.

For example, with the **TempTablePostExecuteSQL** property, you could specify the following SQL statement to create an index:

```
CREATE INDEX <TABLENAME>Idx_1 (<KEYCOLUMNS>) ON <TABLENAME>
```

Then, specify the following query in the **TempTablePreTruncateExecutionSQL** property to drop the index:

```
DROP INDEX <TABLENAME>Idx_1 ON <TABLENAME>
```

Default value

Not defined

Valid Values

A valid SQL query

TempTablePreTruncateRunScript

Configuration category

```
Campaign|partitions|partition[n] |
dataSources|dataSourcename
```

Description



Note: This property is supported only for Teradata data sources. For all other supported databases, this property should not be set.

Use this property to specify a script or executable to run before a temp table is truncated. The script that you specify can be used to negate the effect of a SQL statement specified in the **PostTempTableCreateRunScript** property.

For example, with the **PostTempTableCreateRunScript** property, you could specify a script that includes the following SQL statement to create an index:

```
CREATE INDEX <TABLENAME>Idx_1 (<KEYCOLUMNS>) ON <TABLENAME>
```

Then, specify another script with the following statement in the **TempTablePreTruncateRunScript** property to drop the index:

```
DROP INDEX <TABLENAME>Idx_1 ON <TABLENAME>
```

Default value

Not defined

Valid Values

File name of a shell script or executable

TeradataDeleteBeforeDrop

Configuration category

```
Campaign|partitions|partition[n]|
dataSources|dataSourceName
```

Description

This property applies only to Teradata data sources. It specifies whether records are deleted before a table is dropped.

Set the value to `TRUE` to delete all records from a table before dropping the table.



Note: If Unica Campaign is unable to delete the records for any reason, it will not drop the table.

Set the value to `FALSE` to drop a table without first deleting all records.

Default value

`TRUE`

TruncateSQL

Configuration category

```
Campaign|partitions|partition[n]|
dataSources|dataSourceName
```

Description

This property is available for use with DB2® data sources, and allows you to specify alternate SQL for table truncation. This property applies only when **DeleteAsTruncate** is TRUE. When **DeleteAsTruncate** is TRUE, any custom SQL in this property is used to truncate a table. When this property is not set, Unica Campaign uses the TRUNCATE TABLE <TABLENAME> syntax.

This property is undefined by default.

Tokens available to **TruncateSQL** are described below.

Token	Description
<TABLENAME>	This token is replaced with the database table name that Unica Campaign is truncating.

Default value

No default value defined.

Type

Configuration category

*Campaign|partitions|partition[n]|
dataSources|dataSourcename*

Description

This property specifies the database type of this data source.

Default value

The default value depends on the database template that was used to create the data source configuration.

Valid Values

Valid Types for system tables are:

- DB2
- DB2ODBC
- ORACLE
- ORACLE8
- ORACLE9
- SQLServer

Valid Types for customer tables are:

- BigDataODBC_Hive
- DB2
- DB2ODBC
- NETEZZA
- ORACLE
- ORACLE8
- ORACLE9
- PostgreSQL
- SQLServer
- TERADATA

UOSQLOnConnect

Configuration category

*Campaign|partitions|partition[n]|
dataSources|dataSourcename*

Description

The `SQLOnConnect` property defines a complete SQL statement that Unica Campaign runs immediately after each database connection. The `UOSQLOnConnect` property is similar to this, but specifically applicable to Unica Optimize.

The SQL statement generated by this property is automatically passed to your database without checking its syntax. If you use this property, make sure that

it is a legal expression. The string may be enclosed in quotation marks, but this is not required.

This property is undefined by default.

Tokens available to **UOSQLOnConnect** are described below.

Token	Description
<AMUSER>	This token is replaced with the Unica user name associated with the flowchart for which temp tables were created.
<CAMPAIGNCODE>	This token is replaced with the code for the campaign associated with the flowchart for which temp tables were created.
<CAMPAIGNNAME>	This token is replaced with the name of the campaign associated with the flowchart for which temp tables were created.
<DBUSER>	This token is replaced with the database user name for the database where the temp tables were created.
<FLOWCHARTNAME>	This token is replaced with the name of the flowchart associated with the temp table creation.
<USER>	This token is replaced with the Unica Campaign user name of the user running the flowchart.

Default value

No default value defined.

UseAliasForPredicate

Configuration category

```
Campaign|partitions|partition[n]|
dataSources|dataSourcename
```

Description

This property is used only for Hive-based Hadoop data sources (BigDataODBCHiveTemplate). Set the value to TRUE if you are connecting to IBM BigInsight Hadoop instance. Set to FALSE if you are connecting to any other Hive based Hadoop instance.



Note: If you are upgrading to version 11.1 and you have already configured and are using a Hive based Hadoop data source, you do not need to make any changes for the existing instance.

Default value

FALSE

Valid Values

TRUE | FALSE


UseExceptForMerge

Configuration category

```
Campaign|partitions|partition[n]|
dataSources|dataSourcename
```

Description

When Unica Campaign performs exclusions in the Merge process or in the Segment process, by default it uses `NOT EXISTS` syntax, as:



```
SELECT IncludeTable.ID FROM IncludeTable WHERE NOT EXISTS
(SELECT * FROM ExcludeTable WHERE IncludeTable.ID = ExcludeTable
.ID)
```

If **UseExceptForMerge** is TRUE and you cannot use `NOT IN` (because **UseNotInForMerge** is disabled or because the audience level consists of multiple fields and the data source is not Oracle), then the syntax is altered as follows:

Oracle

```
SELECT IncludeTable.ID FROM IncludeTable
MINUS (SELECT ExcludeTable.ID FROM ExcludeTable)
```

Others

```
SELECT IncludeTable.ID FROM IncludeTable
EXCEPT (SELECT ExcludeTable.ID FROM ExcludeTable)
```

For Hive-based Hadoop big data, this property must be `FALSE`. Hive does not support the `EXCEPT` clause, so a setting of `TRUE` can result in process failures.

Default value

FALSE

Valid Values

TRUE | FALSE

UseGroupByForDistinct

Configuration category

*Campaign|partitions|partition[n] |
dataSources|dataSourcename*

Description

The **UseGroupByForDistinct** property is available for the Teradata datasource template. By default, this property is FALSE. When this property is enabled, <select query> uses a GROUP BY statement instead of DISTINCT.

The purpose of this property: Flowcharts execute the query "select DISTINCT <audience id> from <table>" to fetch unique records when a table is not mapped as a normalized table in Unica Campaign. When such queries are submitted against Teradata, it causes additional sorting of data on the database and high CPU consumption. The Teradata DBA recommendation is to use GROUP BY instead of DISTINCT, because GROUP BY can take advantage of Teradata multi AMP processing architecture.

Default value

FALSE

Valid Values

TRUE | FALSE

UseMergeForTrack

Configuration category

*Campaign|partitions|partition[n] |
dataSources|dataSourcename*

Description

This property implements SQL MERGE syntax to improve the performance of the Track process in flowcharts. This property can be set to `TRUE` for DB2®, Oracle, SQL Server 2008, and Teradata 12. It can also be used with other databases that support the SQL MERGE statement.

Default value

TRUE (DB2 and Oracle) | FALSE (all others)

Valid Values

TRUE | FALSE

UseNonANSIJoin

Configuration category

```
Campaign|partitions|partition[n]|
dataSources|dataSourcename
```

Description

The `UseNonANSIJoin` property specifies whether this data source uses non-ANSI join syntax. If the data source type is set to Oracle7 or Oracle8, and the value of `UseNonANSIJoin` is set to `TRUE`, the data source uses non-ANSI join syntax appropriate for Oracle.

Default value

```
FALSE
```

Valid Values

```
TRUE | FALSE
```

UseNotInForMerge

Configuration category

```
Campaign|partitions|partition[n]|
dataSources|dataSourcename
```

Description

When Unica Campaign performs exclusions in the Merge process or in the Segment process, by default it uses `NOT EXISTS` syntax, as:

```
SELECT IncludeTable.ID FROM IncludeTable WHERE NOT EXISTS (SELEC
T *
FROM ExcludeTable WHERE IncludeTable.ID = ExcludeTable.ID)
```

If **UseNotInForMerge** is enabled and either (1) the audience level is composed of a single ID field, or (2) the data source is Oracle, then the syntax is altered as follows:

```
SELECT IncludeTable.ID FROM IncludeTable WHERE IncludeTable.ID NOT IN
(SELECT ExcludeTable.ID FROM ExcludeTable)
```

Default value

FALSE

Valid Values

TRUE | FALSE

UseNotInToDeleteCH

Configuration category

*Campaign|partitions|partition[n]|
dataSources|dataSourcename*

Description

This property affects the Unica Campaign system table data source (UA_SYSTEM_TABLES). It affects the SQL query syntax for how the MailList and CallList processes remove records from the Unica Campaign system tables.

The default value of FALSE typically improves database performance. The default behavior uses EXISTS / NOT EXISTS when removing Contact History records (either after a failed run or in response to the user's action in the GUI). The removal process involves deleting from UA_OfferHistAttrib and updating UA_OfferHistory.

You can change this value to TRUE if you prefer to use the SQL syntax of IN / NOT IN. Prior versions of Unica Campaign used IN / NOT IN.

Default value

FALSE

Valid Values

TRUE | FALSE

UserBaseTablePostExecutionSQL

Configuration category

`Campaign|partitions|partition[n]|
dataSources|dataSourcename`

Description

This property is invoked when a process box is configured to write to a **New Mapped Table > Base Record Table > Create New Table in Selected Database**. This property is invoked only when the table is created (during the creation and mapping process). This property is not invoked during process box runtime.

This property is automatically added to the SQL expression without checking its syntax. If you use this property, make sure that it is a legal expression. You can enclose the string in quotation marks, but this is not required.

This property treats semicolons as delimiters to run multiple SQL statements. If your SQL statement contains semicolons and you want it to run as one statement, use a backslash as an escape character before the semicolons.



Note: If you are using stored procedures with this property, be sure to use the correct syntax for your database. The following example for Oracle calls a stored procedure and uses backslashes to escape the semicolon: `begin dbms_stats.collect_table_stats()\; end\;`

You can use tokens to substitute the `<TABLENAME>` in this SQL statement because the name is generated dynamically when the campaign runs. For available tokens, see **UserTablePostExecutionSQL**.

UserTablePostExecutionSQL

Configuration category

`Campaign|partitions|partition[n]|
dataSources|dataSourcename`

Description

Use this property to specify a complete SQL statement that Unica Campaign runs immediately after the creation of a user table in a user data source or in the system tables database. This property is invoked when a process box writes to one of the following tables:

- **New mapped table > General table > Create new table in selected datasource:** The property is invoked during the creation/mapping process; not during Snapshot runtime.
- **New mapped table > Dimension table > Create new table in selected database:** The property is invoked during the creation/mapping process; not during Snapshot runtime.
- **Database table:** The property is invoked during process box runtime.

This property is automatically added to the SQL expression without checking its syntax. If you use this property, make sure that it is a legal expression. You can enclose the string in quotation marks, but this is not required.

This property treats semicolons as delimiters to run multiple SQL statements. If your SQL statement contains semicolons and you want it to run as one statement, use a backslash as an escape character before the semicolons.



Note: If you are using stored procedures with this property, be sure to use the correct syntax for your database. The following example for Oracle calls a stored procedure and uses backslashes to escape the semicolon: `begin dbms_stats.collect_table_stats()\; end\;`

You can use tokens to substitute the `<TABLENAME>` in this SQL statement, because the name is generated dynamically when the campaign runs.

Tokens available to **UserTablePostExecuteSQL** are described below.

Token	Description
<AMUSER>	This token is replaced with the Unica user name associated with the flowchart for which the user tables were created.
<CAMPAIGNCODE>	This token is replaced with the code for the campaign associated with the flowchart for which the user tables were created.
<CAMPAIGNNAME>	This token is replaced with the name of the campaign associated with the flowchart for which the user tables were created.
<DBUSER>	This token is replaced with the database user name for the database where the user tables were created.
<FLOWCHARTNAME>	This token is replaced with the name of the flowchart associated with the user table creation.
<TABLENAME>	This token is replaced with the user table name.
<USER>	This token is replaced with the Unica Campaign user name of the user running the flowchart.

Default value

No default value defined.

UseSQLToProfile

Configuration category

```
Campaign|partitions|partition[n]|
dataSources|dataSourcename
```

Description

This property allows you to configure Unica Campaign to submit the SQL query `GROUP BY` to the database to compute profiles (using `SELECT field, count(*) FROM table GROUP BY field`), rather than fetching records.

- A value of `FALSE` (the default) causes Unica Campaign to profile a field by retrieving the field value for all records in the table and to track the count of each distinct value.
- A value of `TRUE` causes Unica Campaign to profile a field by issuing a query similar to the following:

```
SELECT field, COUNT(*) FROM table GROUP BY field
```

which pushes the burden to the database.

Default value

```
FALSE
```

Valid Values

```
TRUE | FALSE
```

UseSQLToRetrieveSchema

Configuration category

```
Campaign|partitions|partition[n]|
dataSources|dataSourcename
```

Description

This property determines whether Unica Campaign uses a SQL query, rather than an ODBC or native API call, to retrieve the schema to use as the table schema for this data source.

The default value is FALSE, indicating that Unica Campaign should use its standard method (ODBC or native connection, for example) to retrieve the schema. Setting this property to TRUE causes Unica Campaign to prepare a SQL query similar to `select * from <table>` to retrieve the table schema.

This can provide advantages that are specific to each data source. For example, some data sources (Netezza®, SQL Server) do not properly report SQL synonyms (alternative names for database objects, defined using the `create synonym` syntax) through the default ODBC or native connections. By setting this property to TRUE, SQL synonyms are retrieved for data mapping within Unica Campaign.

The following list describes the behavior of this setting for a number of data sources:

- Hive-based Hadoop big data: Use the default setting of FALSE.
- Netezza®: Set this property to TRUE to allow support for SQL synonyms. No other settings or values are needed to support synonyms in Netezza® data sources.
- SQL Server: To allow support for synonyms, set this property to TRUE **and** enter valid SQL in the `TableListSQL` property for this data source. See the description for the `TableListSQL` property for more details.
- Oracle: Set this property to TRUE to tell Unica Campaign to prepare the SQL query to retrieve the table schema. The result set identifies `NUMBER` fields (no precision/scale specified, which may cause issues in Unica Campaign) as `NUMBER(38)`, which avoids those possible issues.
- For other data sources, you can optionally set this property to TRUE to use the default SQL select query described above, or to specify valid SQL in the `TableListSQL` property to use instead of, or in addition to, the ODBC API or native connection that is used by default. See the description for the `TableListSQL` property for more details.

Default value

FALSE

Valid Values

TRUE | FALSE

Example

To allow Unica Campaign to work with Netezza® or SQL Server synonyms:

```
UseSQLToRetrieveSchema=TRUE
```

UseTempTablePool**Configuration category**

Campaign | *partitions* | *partition[n]* |
dataSources | *dataSourcename*

Description

When `UseTempTablePool` is set to `FALSE`, temp tables are dropped and re-created every time a flowchart is run. When the property is set to `TRUE`, temp tables are not dropped from the database. Temp tables are truncated and reused from the pool of tables maintained by Unica Campaign. The temp table pool is most effective in environments where you rerun flowcharts many times, such as during a design and test phase.

Default value

FALSE

Valid Values

TRUE | FALSE

Campaign | partitions | partition[n] | systemTableMapping

Properties in the `systemTableMapping` category are populated automatically if you remap any system tables or map Contact or Response history tables. You should not edit properties in this category.

Campaign | partitions | partition[n] | server

This category contains properties to configure the Unica Campaign server for the selected partition.

Campaign | partitions | partition[n] | server | systemCodes

Properties in this category specify, for Unica Campaign, whether variable length codes are allowed, the format and generator of the campaign and cell codes, whether offer codes are displayed, and the offer code delimiter.

offerCodeDelimiter

Configuration category

`Campaign|partitions|partition[n]|server|systemCodes`

Description

The `offerCodeDelimiter` property is used internally to concatenate multiple code parts (for example, to output the OfferCode field in Unica Campaign Generated Fields) and for incoming offer codes in the Unica Campaign Response process, to split the offer code into multiple parts. The value must be only a single character.

Older versions of Unica Campaign included a `NumberOfOfferCodesToUse` parameter. However, in more recent versions, this value comes from the offer template (every offer template can have a different number of offer codes).

Default value

-

allowVariableLengthCodes

Configuration category

`Campaign|partitions|partition[n]|server|systemCodes`

Description

The `allowVariableLengthCodes` property specifies whether variable length codes are allowed in Unica Campaign.

If the value is `TRUE`, and if the trailing part of the code format is `x`, the length of the code can vary. For example, if the code format is `nnnnxxxx`, then the code can be from 4 to 8 characters long. This applies to campaign, offer, version, tracking, and cell codes.

If the value is `FALSE`, variable length codes are not allowed.

Default value

`FALSE`

Valid Values

`TRUE` | `FALSE`

displayOfferCodes

Configuration category

`Campaign` | `partitions` | `partition[n]` | `server` | `systemCodes`

Description

The `displayOfferCodes` property specifies whether to show offer codes beside their names in the Unica Campaign GUI.

If the value is `TRUE`, offer codes are displayed.

If the value is `FALSE`, offer codes are not displayed.

Default value

`FALSE`

Valid Values

`TRUE` | `FALSE`

cellCodeFormat

Configuration category

`Campaign` | `partitions` | `partition[n]` | `server` | `systemCodes`

Description

The `cellCodeFormat` property is used by the campaign code generator to define the format of the cell code that is automatically created by the default cell code generator. For a list of valid values, see `campCodeFormat`.

Default value

`Annnnnnnnn`

campCodeFormat**Configuration category**

`Campaign|partitions|partition[n]|server|systemCodes`

Description

The `campCodeFormat` property is used by the campaign code generator to define the format of the campaign code that is automatically generated by the default campaign code generator when you create a campaign.

Default value

`Cnnnnnnnnn`

Valid Values

The possible values are:

- `A-Z` or any symbol - treated as a constant
- `a` - random letters A-Z (upper case only)
- `c` - random letters A-Z or numbers 0-9
- `n` - random digit 0-9
- `x` - any single ASCII character from `0-9` or `A-Z`. You can edit the generated campaign code and replace the ASCII character that Unica Campaign substituted for the `x` with any ASCII character, and Unica Campaign will use that character instead.

cellCodeGenProgFile**Configuration category**

Campaign|partitions|partition[n]|server|systemCodes

Description

The `cellCodeGenProgFile` property specifies the name of the cell code generator. The properties that control the format of the code generated are set in the `cellCodeFormat` property. See `campCodeGenProgFile` for a list of supported options.

If you write your own cell code generator, replace the default value with the absolute path of your custom program, including the file name and extension, and using forward slashes (/) for UNIX™ and backslashes (\) for Windows™.

Default value

`uaccampcodegen` (the code generator supplied by Unica Campaign)

campCodeGenProgFile

Configuration category

Campaign|partitions|partition[n]|server|systemCodes

Description

This property specifies the name of the campaign code generator. The properties that control the format of the generated code are set in the `campCodeFormat` property.

If you write your own campaign code generator, replace the default value with the absolute path of your custom program, including the file name and extension, using forward slashes (/) for UNIX™ and backslashes (\) for Windows™.

The default campaign code generator can be called with the following options:

- `-y` Year (four integers)
- `-m` Month (one or two integers, cannot exceed value of twelve)
- `-d` Day (one or two integers, cannot exceed value of 31)
- `-n` Campaign name (any string, cannot exceed 64 characters)
- `-o` Campaign owner (any string, cannot exceed 64 characters)

- `-u` Campaign code (any integer). Allows you to specify the exact campaign ID rather than having the application generate one for you.
- `-f` Code format if overriding the default. Takes the values specified in `campCodeFormat`.
- `-i` Other integer.
- `-s` Other string.

Default value

`uaccampcodegen` (the code generator supplied by Unica Campaign)

cellCodeBulkCreation

Configuration category

`Campaign|partitions|partition[n]|server|systemCodes`

Description

A value of TRUE improves performance of the cell code generation utility during bulk creation of cell codes, because multiple cell codes are generated with a single invocation of the cell code generator. This is more efficient and is the recommended setting. A value of TRUE also improves performance when copying flowcharts, templates, and process boxes.

When the value is FALSE, the cell code generator is invoked once for each cell code generation. If cell code generation seems to take a long time for Segment, Sample, and Decision process boxes, or for the target cell spreadsheet, set this value to TRUE.

The default setting is FALSE to support existing customized implementations. If you are using a legacy custom-made cell code generation utility, leave this setting at its default value of FALSE until you implement a new custom utility. Then you can change its value to TRUE.

If you are not using a custom cell code generation utility, change the value to TRUE to take advantage of the efficiency improvements.

Default value

FALSE

Valid Values

TRUE | FALSE

Campaign | partitions | partition[n] | server | encoding

The property in this category specifies the text encoding for values written to files, to support non-English data.

stringEncoding**Description**

The `partition[n] > server > encoding > stringEncoding` property how Unica Campaign reads in and writes out flat files. It should match the encoding used for all flat files. If not configured elsewhere, this is the default setting for flat file encoding.



Note: `WIDEUTF-8` is not supported for this setting.

By default, no value is specified, and outgoing text files are encoded as UTF-8, which is the default encoding for Unica Campaign.

It is a best practice to explicitly set this value to an encoding appropriate for your system, even if the value is UTF-8, the same as the implicit default.



Note: If you do not set the value of the `StringEncoding` property for data sources in the `dataSources` category, the value of this `stringEncoding` property is used as the default value. This can cause unnecessary confusion -- you should always explicitly set the `StringEncoding` property in the `dataSources` category.

See the Unica Campaign Administrator's Guide for a list of supported encodings.

Default value

No default value defined.

forceDCTOneBytePerChar**Description**

The `forceDCTOneBytePerChar` property specifies whether Unica Campaign should use the original field width for output files, rather than the potentially expanded width reserved to allow sufficient space for transcoding into UTF-8.

A text value may have different lengths, depending on the encoding used to represent it. When the text value comes from a data source whose `stringEncoding` property is neither ASCII nor UTF-8, Unica Campaign reserves three times the field width in order to ensure sufficient space for transcoding into UTF-8. For example, if the `stringEncoding` property is set to `LATIN1`, and the field in the database is defined as `VARCHAR(25)`, Unica Campaign will reserve 75 bytes to hold the transcoded UTF-8 value. Set the `forceDCTOneBytePerChar` property to `TRUE` if you want to use the original field width.

Default value

FALSE

Valid Values

TRUE | FALSE

Campaign | partitions | partition[n] | server | timeout

The properties in this category specify the number of seconds an Unica Campaign flowchart waits, after the user has disconnected and all runs have completed, before exiting, and the Unica Campaign server process waits for a response from external servers before reporting an error.

waitForGracefulDisconnect**Description**

The `waitForGracefulDisconnect` property specifies whether the Unica Campaign server process continues to run until the user gracefully disconnects, or exits regardless of whether the user intended to disconnect.

If the value is `yes`, the default, the server process continues to run until it can determine that the user wants it to exit. This option prevents changes from being lost, but can result in server processes accumulating.

If the value is `no`, the server process shuts down and server processes are prevented from accumulating, but users can lose work if a network interruption occurs or if they do not follow the recommended sequence of actions to exit gracefully.

Default value

TRUE

Valid Values

TRUE | FALSE

urlRequestTimeout**Description**

The `urlRequestTimeout` property specifies the number of seconds the Unica Campaign server process waits for a response from external servers. Currently, this applies to requests to Unica servers and IBM eMessage components that operate with Unica Campaign.

If the Unica Campaign server process does not receive a response within this period, a communication timeout error is reported.

Default value

60

delayExitTimeout**Description**

The `delayExitTimeout` property specifies the number of seconds an Unica Campaign flowchart waits, after the user has disconnected and all runs have completed, before exiting.

Setting this property to a non-0 value enables subsequent Unica Campaign flowcharts to make use of existing instances rather than starting a new instance.

Default value

10

Campaign | partitions | partition[n] | server | collaborate

This category applies to Unica Collaborate.

collaborateInactivityTimeout

Configuration category

Campaign | partitions | partition[n] | server | collaborate

Description

The `collaborateInactivityTimeout` property specifies the number of seconds the `unica_acsvr` process waits after it finishes servicing a Unica Collaborate request before it exits. This waiting period allows the process to remain available in the typical scenario in which Unica Collaborate makes a series of requests prior to running the flowchart.

The minimum value is 1. Setting this property to 0 causes it to default to 60.

Default value

60

logToSeparateFiles

Configuration category

Campaign | partitions | partition[n] | server | collaborate

Description

This property was introduced in v8.6.0.6. By default and upon upgrade, the value of this parameter is False.

When True, flowchart logs for runs initiated from Unica Collaborate are logged to separate log files. Log files are created under folders with the current date to avoid an excessive number of log files in a single folder. The format of the folder name is "FlowchartRunLogs_<YYYYMMDD>".

The format of the log file name is:

<CAMP_NAME>_<CAMP_CODE>_<FC_NAME>_<PID>_<LIST_CODE>_<DATE>_<TIMESTAMP>.log, where PID is the Unica Campaign server process ID that ran the flowchart. LIST_CODE is the object code of the Unica Collaborate list, ONDC or corporate campaign from which the flowchart was run.

All user variables that are passed to the flowchart run process are logged for troubleshooting purposes.



Note: When a flowchart is opened, it initially logs to the traditional flowchart log file. When a flowchart run is initiated from Unica Collaborate, if logToSeparateFiles is True, logging is done in the new directory and file at that time.

Default value

False

Valid Values

True | False

Campaign | partitions | partition[n] | server | spss

Properties in this category affect IBM SPSS Modeler Advantage Enterprise Marketing Management Edition integration for the specified partition in Unica Campaign.

SharedDirectoryPathCampaign

Description

The path to the directory that is used to transfer data between Unica Campaign and SPSS Modeler Server, as seen from Unica Campaign.

- Unica Campaign puts input data files to IBM SPSS Modeler Advantage Enterprise Marketing Management Edition in this directory.
- IBM SPSS Modeler Advantage Enterprise Marketing Management Edition puts output data files in this directory to be read and processed by Unica Campaign.

Default value

None

Valid values

Any valid Windows path (such as `Z:\SPSS_Shared`) or a mount directory (for UNIX).

SharedDirectoryPathSPSS

Description

The path to the directory that is used to transfer data between Unica Campaign and SPSS Modeler Server, as seen from SPSS Modeler Server. This is the same shared directory referenced by `SharedDirectoryPathCampaign` but is the local directory path used by SPSS Modeler Server.

For example, Unica Campaign might be installed on Windows with `SharedDirectoryPathCampaign = Z:\SPSS_Shared`, where `Z:\SPSS_Shared` is a mapped network drive, while SPSS® Modeler Server is installed on UNIX with a mount to that directory defined as `SharedDirectoryPathSPSS = /share/CampaignFiles`.

Default value

None

Valid values

Any valid Windows™ path (such as `Z:\SPSS_Shared`) or a mount directory (such as `/share/CampaignFiles`) for UNIX.

C&DS_URL

Description

The URL for the IBM SPSS Collaboration and Deployment Services repository.

Default value

`http://localhost:7001/cr-ws/services/ContentRepository`

Valid values

The URL for the IBM SPSS Collaboration and Deployment Services repository.

SPSS_Integration_Type

Description

This property determines the type of integration between Unica Campaign and IBM SPSS Modeler Advantage Enterprise Marketing Management Edition.

Default value

None

Valid values

- `None`: No integration
- `SPSS MA Marketing Edition`: Full integration of modeling and scoring. This option is only available if IBM SPSS Modeler Advantage Enterprise Marketing Management Edition is installed and configured.
- `Scoring only`: Scoring, but not modeling, is enabled.

Campaign | partitions | partition[n] | server | permissions

The properties in this category specify the permissions for folders that are created by Unica Campaign and the UNIX™ group and permissions for files in the `profile` directory.

userFileGroup (UNIX™ only)

Description

This property specifies a group associated with user-generated Unica Campaign files. The group will be set only if the user is a member of the specified group.

This property is undefined by default.

Default value

No default value defined.

createFolderPermissions

Description

The `createFolderPermissions` parameter specifies the permissions of directories that are created by Unica Campaign on the Unica Campaign server (partition[n] location) by using the Create Folder icon on the Open Data Source File dialog in the table mapping.

Default value

755 (owner has read/write/execute access, group and world have execute/read access)

catalogFolderPermissions

Description

The `catalogFolderPermissions` property specifies the permissions of directories created by Unica Campaign through the Stored table catalogs > Create folder window.

Default value

755 (owner has read/write/execute access, group and world have execute/read access)

templateFolderPermissions

Description

The `templateFolderPermissions` property specifies the permissions of template directories created by Unica Campaign through the **Stored templates > Create folder** window.

Default value

755 (owner has read/write/execute access, group and world have read/execute access)

adminFilePermissions (UNIX™ only)

Description

The `adminFilePermissions` property specifies a permission bit mask for the files contained in the `profile` directory.

Default value

660 (owner and group have read/write access only)

userFilePermissions (UNIX™ only)

Description

The `userFilePermissions` property specifies a permission bit mask for user generated Unica Campaign files (for example, log files, summary files, exported flat files).

Default value

666 (everyone can read and write files created by Unica Campaign in the server)

adminFileGroup (UNIX™ only)

Description

The `adminFileGroup` property specifies a UNIX™ admin group associated with files contained in the `profile` directory.

This property is undefined by default.

Default value

No default value defined.

Campaign | partitions | partition[n] | server | flowchartConfig

Properties in this category specify the behavior of the Unica Campaign Generated Field, whether duplicate cell codes are allowed, and whether the Log to Contact History option defaults to enabled.

allowDuplicateCellcodes

Description

The `allowDuplicateCellcodes` property specifies whether the cell codes in the Unica Campaign Snapshot process can have duplicate values.

If the value is `FALSE`, the Unica Campaign server enforces unique cell codes.

If the value is `TRUE`, the Unica Campaign server does not enforce unique cell codes.

Default value

`TRUE`

Valid Values

`TRUE` | `FALSE`

allowResponseNDaysAfterExpiration

Description

The `allowResponseNDaysAfterExpiration` property specifies the maximum number of days after all offer expiration dates that responses can be tracked.

These late responses can be included in performance reports.

Default value

agfProcessnameOutput

Description

The `agfProcessnameOutput` property specifies the output behavior of the Unica Campaign Generated Field (ICGF) in the List, Optimize, Response, and Snapshot processes.

If the value is `PREVIOUS`, the ICGF contains the process name associated with the incoming cell.

If the value is `CURRENT`, the ICGF holds the process name of the process in which it is used.

Default value

`PREVIOUS`

Valid Values

`PREVIOUS` | `CURRENT`

logToHistoryDefault

Description

The `logToHistoryDefault` property specifies whether the Log to Contact History and Tracking Tables option in the Log tab of the Unica Campaign contact processes defaults to enabled.

If the value is `TRUE`, the option is enabled.

If the value is `FALSE`, the option is disabled in any newly created contact processes.

Default value

`TRUE`

Valid Values

`TRUE` | `FALSE`

overrideLogToHistory

Description

This property controls whether users with the appropriate permissions can change the Log to Contact History Tables setting when they configure a contact or Track process. To make all flowchart production runs always write to contact history, enable logToHistoryDefault and disable overrideLogToHistory

Default value

TRUE

Valid Values

TRUE | FALSE

defaultBehaviorWhenOutputToFile

Description

Specifies the behavior for contact processes in Unica Campaign when outputting to a file. This property applies only within the current partition. This default behavior (if set) is only applied for processes when they are newly added to flowcharts; once a process is added to a flowchart, the output behavior can be changed in the process configuration.

Default value

Replace All Records

Valid Values

- Append to Existing Data
- Create New File
- Replace All Records

defaultBehaviorWhenOutputToDB

Description

Specifies the behavior for contact processes in Unica Campaign when outputting to a database table. This property applies only within the current partition. This default behavior (if set) is only applied for processes when they are newly added to flowcharts; once a process is added to a flowchart, the output behavior can be changed in the process configuration.

Default value

Replace All Records

Valid Values

- Append to Existing Data
- Replace All Records

replaceEmbeddedNames**Description**

When `replaceEmbeddedNames` is `TRUE`, Unica Campaign replaces user variable and ICGF names embedded in query text with actual values, although these names must be separated by a non-alphanumeric character, such as an underscore (for example, `ABC_UserVar.v1` will be substituted but `ABCUserVar.v1` will not). Set this property to `TRUE` for backwards compatibility with Unica Campaign 7.2 and earlier.

When set to `FALSE`, Unica Campaign replaces only distinct user variable and ICGF names with actual values (in both Unica and raw SQL expressions). Set this property to `FALSE` for backwards compatibility with Unica Campaign 7.3 and higher.

Default value

`FALSE`

Valid Values

`TRUE` | `FALSE`

legacyMultifieldAudience

Description

In most cases, you can leave this property set to the default value of `FALSE`. Unica Campaign v8.5.0.4 and newer name multifield Audience ID fields according to the audience definition, regardless of the source of the fields. When you configure processes to use multifield Audience ID fields, you now see the new Audience ID naming convention for multifield audiences. Already-configured processes in flowcharts created in previous Unica Campaign versions should continue to work. However, if old flowcharts fail because of the change in the naming convention, you can revert Unica Campaign behavior by setting this property to `TRUE`.

Default value

`FALSE`

Valid Values

`TRUE` | `FALSE`

Campaign | partitions | partition[n] | server | flowchartSave

The properties in this category specify the default settings for the auto-save and checkpoint properties of a new Unica Campaign flowchart.

checkpointFrequency

Description

The `checkpointFrequency` property specifies (in minutes) the default setting for a new Unica Campaign flowchart's checkpoint property, configurable for each flowchart through the client-side Advanced Settings window. The checkpoint feature provides the ability to capture a snapshot of a running flowchart for recovery purposes.

Default value

0 (zero)

Valid Values

Any integer

autosaveFrequency**Description**

The `autosaveFrequency` property specifies (in minutes) the default setting for a new Unica Campaign flowchart's auto-save property, configurable for each flowchart through the client-side Advanced Settings window. The auto-save function performs a forced save of flowcharts during editing and configuration.

Default value

0 (zero)

Valid Values

Any integer

Campaign | partitions | partition[n] | server | dataProcessing

Properties in this category specify how Unica Campaign handles string comparisons and empty fields in flat files, and the behavior of the macro `STRING_CONCAT`.

longNumericIdsAsText**Description**

The `longNumericIdsAsText` property specifies whether the Unica Campaign macro language will treat numeric IDs longer than 15 digits as text. This property affects ID fields. It has no effect on non-ID fields. This property is useful if you have numeric ID fields with more than 15 digits AND you want to include ID values in criteria.

- Set the value to `TRUE` to specify that numeric IDs longer than 15 digits will be treated as text.
- When the value is `FALSE`, numeric IDs longer than 15 digits are treated as numeric values (and thus might lose precision or uniqueness if truncated or rounded). If you do anything that treats the ID values as numeric (such as profiling, or using in a Derived Field), the text is converted to numeric, and precision beyond the 15th digit is lost.



Note: For non-ID numeric fields, if you do anything that treats the value as numeric (such as profiling, rounding, or using in a Derived Field), precision beyond 15 digits is lost.

This setting is ignored if the `partitions > partition[n] > dataSources > [data_source_name] > ForceNumeric` property is set to `TRUE` for fields coming from this data source.

Default value

`FALSE`

Valid Values

`TRUE` | `FALSE`

stringConcatWithNullIsNull

Description

The `stringConcatWithNullIsNull` property controls the behavior of the Unica Campaign macro `STRING_CONCAT`.

When the value is `TRUE`, `STRING_CONCAT` returns `NULL` if any of its inputs is `NULL`.

When the value is `FALSE`, `STRING_CONCAT` returns the concatenation of all of its non-`NULL` properties; in this case, `STRING_CONCAT` returns `NULL` only if all of its inputs are `NULL`.

Default value

TRUE

Valid Values

TRUE | FALSE

performCaseInsensitiveComparisonAs**Description**

The `performCaseInsensitiveComparisonAs` property specifies how Unica Campaign compares data values when the `compareCaseSensitive` property is set to `no` (that is, during case-insensitive comparisons). This property is ignored if the value of `compareCaseSensitive` is `yes`.

When the value is `UPPER`, Unica Campaign converts all data to upper case before comparing.

When the value is `LOWER`, Unica Campaign converts all data to lower case before comparing.

Default value

LOWER

Valid Values

UPPER | LOWER

upperAllowsDate**Description**

The `upperAllowsDate` property specifies whether the `UPPER` database function allows a `DATE/DATETIME` parameter, and therefore whether the operation may be performed in the database or must be performed by the Unica Campaign server.

Set the value to `TRUE` if the database is SQL Server or Oracle. The `UPPER` function in these databases allows a `DATE/DATETIME` parameter.

Set the value to `FALSE` if the database is DB2® or Teradata. The `UPPER` function in these databases does not allow a `DATE/DATETIME` parameter.

Note that this setting is global, not per data source. If a value of `no` is recommended for any data source in use, set the value to `no`. If a value of `yes` is recommended for all data sources in use, set the value to `yes`.

Default value

`TRUE`

Valid Values

`TRUE` | `FALSE`

compareCaseSensitive

Description

The `compareCaseSensitive` property specifies whether the Unica Campaign data comparisons are sensitive to alphabetic case (UPPER vs. lower).

When the value is `FALSE`, Unica Campaign ignores case differences when comparing data values and sorts textual data in a binary, case-insensitive manner. This setting is strongly recommended when English data is used.

When the value is `TRUE`, Unica Campaign distinguishes data values based on case differences, performing a true binary-value comparison of each character. This setting is strongly recommended when non-English data is used.

Default value

`FALSE`

Valid Values

`TRUE` | `FALSE`

lowerAllowsDate

Description

The `lowerAllowsDate` property specifies whether the `LOWER` database function allows a `DATE/DATETIME` parameter, and therefore whether the operation may

be performed in the database or must be performed by the Unica Campaign server.

Set the value to `TRUE` if the database is SQL Server or Oracle. The `LOWER` function in these databases allows a `DATE/DATETIME` parameter.

Set the value to `FALSE` if the database is DB2® or Teradata. The `LOWER` function in these databases does not allow a `DATE/DATETIME` parameter.

Note that this setting is global, not per data source. If a value of `no` is recommended for any data source in use, set the value to `no`. If a value of `yes` is recommended for all data sources in use, set the value to `yes`. Typically, only one database type is in use at a customer site, but there are some installations in which multiple database types are in use.

Default value

`TRUE`

Valid Values

`TRUE` | `FALSE`

substrAllowsDate

Description

The `substrAllowsDate` property specifies whether the `SUBSTR/SUBSTRING` database function allows a `DATE/DATETIME` parameter, and therefore whether the operation may be performed in the database or must be performed by the Unica Campaign server.

Set the value to `TRUE` if the database is Oracle or Teradata. The `SUBSTR/SUBSTRING` function in these databases allows a `DATE/DATETIME` parameter.

Set the value to `FALSE` if the database is SQL Server or DB2®. The `SUBSTR/SUBSTRING` function in these databases does not allow a `DATE/DATETIME` parameter.

Note that this setting is global, not per data source. If a value of `no` is recommended for any data source in use, set the value to `no`. If a value of `yes` is recommended for all data sources in use, set the value to `yes`.

Default value

`TRUE`

Valid Values

`TRUE` | `FALSE`

ltrimAllowsDate**Description**

The `ltrimAllowsDate` property specifies whether the `LTRIM` database function allows a `DATE/DATETIME` parameter, and therefore whether the operation may be performed in the database or must be performed by the Unica Campaign server.

Set the value to `TRUE` if the database is SQL Server, Oracle, or Teradata. The `LTRIM` function in these databases allows a `DATE/DATETIME` parameter.

Set the value to `FALSE` if the database is DB2®. The `LTRIM` function in this database does not allow a `DATE/DATETIME` parameter.

Note that this setting is global, not per data source. If a value of `no` is recommended for any data source in use, set the value to `no`. If a value of `yes` is recommended for all data sources in use, set the value to `yes`. Typically, only one database type is in use at a customer site, but there are some installations in which multiple database types are in use.

Default value

`TRUE`

Valid Values

`TRUE` | `FALSE`

rtrimAllowsDate

Description

The `rtrimAllowsDate` property specifies whether the `RTRIM` database function allows a `DATE/DATETIME` parameter, and therefore whether the operation may be performed in the database or must be performed by the Unica Campaign server.

Set the value to `TRUE` if the database is SQL Server, Oracle, or Teradata. The `RTRIM` function in these databases allows a `DATE/DATETIME` parameter.

Set the value to `FALSE` if the database is DB2®. The `RTRIM` function in this database does not allow a `DATE/DATETIME` parameter.

Note that this setting is global, not per data source. If a value of `no` is recommended for any data source in use, set the value to `no`. If a value of `yes` is recommended for all data sources in use, set the value to `yes`.

Default value

`TRUE`

Valid Values

`TRUE` | `FALSE`

likeAllowsDate

Description

The `likeAllowsDate` property specifies whether the `LIKE` database function allows a `DATE/DATETIME` parameter, and therefore whether the operation may be performed in the database or must be performed by the Unica Campaign server.

Set the value to `TRUE` if the database is SQL Server or Oracle. The `LIKE` function in these databases allows a `DATE/DATETIME` parameter.

Set the value to `FALSE` if the database is DB2® or Teradata. The `LIKE` function in these databases does not allow a `DATE/DATETIME` parameter.



Note: This setting is global, not per data source. If a value of `no` is recommended for any data source in use, set the value to `no`. If a value of `yes` is recommended for all data sources in use, set the value to `yes`.

Default value

TRUE

Valid Values

TRUE | FALSE

fileAllSpacesIsNull

Description

The `fileAllSpacesIsNull` property controls how Unica Campaign interprets an empty field in a mapped flat file by specifying whether an all-spaces value in a flat file should be considered to be a `NULL` value.

When the value is `TRUE`, an all-spaces value is considered to be a `NULL` value. Unica Campaign matches queries such as `<field> is null`, but fails queries such as `<field> = ""`.

When the value is `FALSE`, an all-spaces value is treated as a non-`NULL` empty string. Unica Campaign matches queries such as `<field> = ""`, but fails `<field> is null`.

Default value

TRUE

Valid Values

TRUE | FALSE

Campaign | partitions | partition[n] | server | optimization

Properties in this category control Unica Campaign server optimization for each partition.



Note: This category is not related to Unica Optimize.

maxVirtualMemory

Configuration category

`Campaign|partitions|partition[n]|server|optimization`

Description

It is used for internal locking of memory which prevents it from being swapped as temporary files.

Set a value equal to $(80\% \times \text{available memory}) / (\text{number of expected concurrent flowcharts})$. For example:

If available virtual memory on server = 32 GB

Number of concurrent flowcharts = 10

Set virtual Memory = $(80\% \times 32) / 10 = \text{approximately } 2.5 \text{ GB} / \text{flowchart}$

Default value

128 (MB)

maxVirtualMemory is a global configuration setting. To override the value for a specific flowchart, open the flowchart in Edit mode, select **Advanced settings** from the **Admin** menu



, select the **Server optimization** tab, and change the **Campaign virtual memory usage** value.

useInDbOptimization

Configuration category

`Campaign|partitions|partition[n]|server|optimization`

Description

This property specifies whether Unica Campaign tries to perform as many operations as possible in the database instead of in the Unica Campaign server.

Setting the value to `TRUE` can improve flowchart performance. When the value is `TRUE`, Unica Campaign avoids pulling the ID lists if possible.

When the value is `FALSE`, Unica Campaign maintains lists of IDs in the Unica Campaign server at all times.

Default value

`FALSE`

Valid Values

`TRUE` | `FALSE`

maxReuseThreads

Configuration category

```
Campaign | partitions | partition[n] | server |  
optimization
```

Description

This property specifies the number of operating system threads that are cached by the server process (`unica_acsvr`) for reuse. By default, the cache is disabled.

It is a best practice to use the cache when you want to reduce the overhead of thread allocation, or with operating systems that exhibit an inability to release threads when asked to do so by an application.

If the **maxReuseThreads** property is a non-zero value, set it to be greater than or equal to the value of **MaxQueryThreads**.

Default value

0 (zero), which disables the cache

threadStackSize

Configuration category

`Campaign|partitions|partition[n]|server|optimization`

Description

This property determines the number of bytes allocated for each thread's stack. Do not change this property except under guidance from HCL. The minimum value is 128 K. The maximum value is 8 MB.

Default value

1048576

tempTableDataSourcesForSegments

Configuration category

`Campaign|partitions|partition[n]|server|optimization`

Description

This property defines the list of data sources where persistent Segment temp tables can be created by the Create Seg process. This list is comma-separated. By default, this property is blank.

Default value

No default value defined.

doNotCreateServerBinFile

Configuration category

`Campaign|partitions|partition[n]|server|optimization`

Description

To improve performance, set this property to `TRUE`. When this property is `TRUE`, strategic segments create Segment temp tables in the data source rather than creating binary files on the Unica Campaign server. You must specify at least one data source in the Create Segment (CreateSeg) process configuration

dialog to hold the temp tables. Also, you must set the `AllowTempTables` property to `TRUE` to enable the creation of temporary tables in a data source.

Default value

`FALSE`

Valid Values

`TRUE` | `FALSE`

forceViewForPreOptDates

Configuration category

`Campaign|partitions|partition[n]|server|optimization`

Description

The default value (`TRUE`) forces creation of a parameterized offer attribute view in a Mail List process whose offers are assigned from Optimize. A value of `FALSE` causes the parameterized offer attribute view to be created only if the Mail List exports at least one parameterized offer attribute.

If this value is set to `FALSE`, a Mail List process that is configured to get its input from an Extract process (whose source is an Optimize session) may write NULL values for EffectiveDate and ExpirationDate into the `UA_Treatment` table, even when the offer includes parameterized Effective and Expiration Dates. In this case, set it back to `TRUE`.

Default value

`TRUE`

Valid Values

`TRUE` | `FALSE`

httpCompressionForResponseLength

Configuration category

`Campaign|partitions|partition[n]|server|optimization`

Description

This property enables and configures compression for HTTP responses from the Unica Campaign web application to the client browser for flowchart-specific messages. The Unica Campaign web application reads this property only once for each partition. If you modify this property, you must restart the web application for the change to take effect.

Compression can improve page load and interaction times by reducing the amount of data that is sent over HTTP.

All responses that have a data length greater than or equal to the `httpCompressionForResponseLength` value (in KB) are candidates for compression. Any other responses are not compressed.

Compression reduces network transfer, but it requires resources on the server side. Therefore, compression makes sense only for large amounts of data, when sufficient server-side resources are available. If you typically have network delays that can slow large data transfers, you can analyze how much time it takes to load a given amount of data. For example, suppose that some of your HTTP requests are <100 KB in size, but most are 300 to 500 KB. In this case, you would increase the value of this property to 500 KB so that only responses \geq 500 KB in size are compressed.

To disable compression, set the value to 0.

Default value

100 (KB)

Valid Values

0 (disables compression) or higher

cacheSystemDSQueries**Configuration category**

`Campaign|partitions|partition[n]|server|optimization`

Description

To improve performance, set this value to TRUE. When set to TRUE, this property reduces multiple execution of queries on the Unica Campaign system tables by caching the query results. When set to FALSE, query results are not cached.

Default value

TRUE

Valid Values

TRUE | FALSE

Campaign | partitions | partition[n] | server | logging

Properties in this category affect flowchart logging behavior for the specified partition on the Unica Campaign server.

enableWindowsEventLogging**Description**

This property enables or disables Unica Campaign server logging to the Windows™ event log.

If the value is `TRUE`, logging to the Windows™ event log is enabled.

If the value is `FALSE`, logging to the Windows™ event log is disabled, and the **windowsEventLoggingLevel** and **windowsEventLoggingCategory** settings are ignored.



Attention: Windows™ Event logging can cause issues with flowchart runs. Avoid enabling this feature unless advised by Technical Support.

Default value

FALSE

Valid Values

TRUE | FALSE

logFileBufferSize

Configuration category

Campaign|partitions|partition[n]|server|logging

Description

This property is used when **keepFlowchartLogOpen** is `TRUE`. Specify a value to indicate the number of messages to buffer before writing to the log. If the value is `1`, every log message is written immediately to file, effectively disabling buffering but having a negative impact on performance.

This property is ignored if **keepFlowchartLogOpen** is `FALSE`.

Default value

5

keepFlowchartLogOpen

Configuration category

Campaign|partitions|partition[n]|server|logging

Description

This property specifies whether Unica Campaign opens and closes the flowchart log file each time a line is written to the log file.

A value of `TRUE` can improve performance of real-time interactive flowcharts. When the value is `TRUE`, Unica Campaign opens the flowchart log file only once, and closes it when the flowchart's server process exits. A side effect of using the `TRUE` value is that recently-logged messages may not be immediately visible in the log file, as Unica Campaign flushes the log messages to file only when its internal buffer becomes full or when the number of logged messages equals the value of the `logFileBufferSize` property.

If the value is `FALSE`, Unica Campaign opens and closes the flowchart log file.

Default value

FALSE

Valid Values

TRUE | FALSE

logProcessId

Configuration category

Campaign|partitions|partition[n]|server|logging

Description

This property controls whether the process ID (pid) of the Unica Campaign Server process is included in the log file.

If the value is `TRUE`, the process ID is logged.

If the value is `FALSE`, the process ID is not logged.

Default value

TRUE

Valid Values

TRUE | FALSE

logMaxBackupIndex

Configuration category

Campaign|partitions|partition[n]|server|logging

Description

This property specifies the number of backup Unica Campaign server log files that are kept before the oldest is erased.

If the value is 0 (zero), no backup files are created, and the log file is truncated when it reaches the size specified by the `logFileMaxSize` property.

For a value of `n`, where `n` is greater than zero, the files `{File.1, ..., File.n-1}` are renamed to `{File.2, ..., File.n}`. Also, `File` is renamed `File.1` and closed. A new `File` is created to receive further log output.

Default value

1 (creates one backup log file)

loggingCategories**Configuration category**

`Campaign|partitions|partition[n]|server|logging`

Description

This property specifies the category of messages written to the Unica Campaign server flowchart log file. This property works in conjunction with **loggingLevels**, which determines the severity of messages to log for all selected categories.

Specify one or more categories in a comma-separated list. Use `ALL` as shorthand to indicate that you want to log all categories.

The values that you specify determine which events are logged by default for all flowcharts. Users can override the default selections by opening a flowchart for editing and choosing **Options > Logging options**. The corresponding Logging Options are indicated below in parentheses, after each configuration value.

Default value

`ALL`

Valid Values

`ALL`

`BAD_ORDER` (Log ID ordering errors)

`CELL_ACCESS` (Cell level operations)

`CONFIG` (Log config settings at start of run)

`DATA_ERRORS` (Log data conversion errors)

`DBLOAD` (External DB loader operations)

`FILE_ACCESS`(File operations)

`GENERAL` (Others)

COMMANDS (External interface)
 MEMORY (Memory allocation)
 PROCRUN (Process Run)
 QUERY (Queries issues against user tables)
 SORT (Log data sorting progress)
 SYSQUERY (Queries issued against system tables)
 TABLE_ACCESS (Table level operations)
 TABLE_MAPPING (Log table mapping info at start of run)
 TABLE_IO (Log data I/O process)
 WEBPROC (Web server interface)

loggingLevels

Configuration category

`Campaign|partitions|partition[n]|server|logging`

Description

The **loggingLevels** property controls the amount of detail written to the Unica Campaign server log file, based on severity.

Default value

MEDIUM

Valid Values

LOW: represents the least detail (the most severe errors only)

MEDIUM

HIGH

ALL: includes trace messages and is intended primarily for diagnostic purposes



Note: You may want to set **loggingLevels** to ALL during configuration and testing. This value generates a large amount of data and therefore



may not be advisable for production operation. Setting any logging level higher than its default can adversely affect performance.

You can adjust these settings from within a flowchart by using **Tools > Logging options**.

windowsEventLoggingCategories

Configuration category

`Campaign|partitions|partition[n]|server|logging`

Description

This property specifies the category of messages written to the Windows™ event log for the Unica Campaign server. This property works in conjunction with **windowsEventLoggingLevels**, which determines which messages are logged based on severity (for all selected categories).

You can specify multiple categories in a comma-separated list. The category `a11` provides a shorthand for specifying all logging categories.

Default value

ALL

Valid Values

ALL
 BAD_ORDER
 CELL_ACCESS
 CONFIG
 DATA_ERRORS
 DBLOAD
 FILE_ACCESS
 GENERAL
 COMMANDS
 MEMORY
 PROCRUN

QUERY
SORT
SYSQUERY
TABLE_ACCESS
TABLE_MAPPING
TABLE_IO
WEBPROC

logFileMaxSize

Configuration category

Campaign|partitions|partition[n]|server|logging

Description

This property specifies the maximum size, in bytes, that the Unica Campaign server log file is allowed to reach before being rolled over to backup files.

Default value

10485760 (10 MB)

windowsEventLoggingLevels

Configuration category

Campaign|partitions|partition[n]|server|logging

Description

This property controls the amount of detail written to the Windows™ event log for the Unica Campaign server, based on severity.

Default value

MEDIUM

Valid Values

LOW: represents the least detail (the most severe errors only)

MEDIUM

HIGH

ALL: includes trace messages and is intended for diagnostic purposes.

enableLogging

Configuration category

Campaign|partitions|partition[n]|server|logging

Description

This property specifies whether Unica Campaign server logging is turned on at session startup.

If the value is `TRUE`, logging is turned on.

If the value is `FALSE`, logging is turned off.

Default value

`TRUE`

Valid Values

`TRUE` | `FALSE`

AllowCustomLogPath

Configuration category

Campaign|partitions|partition[n]|server|logging

Description

This property allows users to change the log path for each flowchart that generates flowchart-specific logging information when it is run. By default, all flowchart log files are saved in `Campaign_home/partitions/partition_name/logs`.

A setting of `TRUE` allows users to change the path through the user interface or when using `unica_svradm` to run the flowchart.

A setting of `FALSE` prevents users from changing the path to which the flowchart log file is written.

Default value

FALSE

Valid Values

TRUE | FALSE

Campaign | partitions | partition[n] | server | flowchartRun

Properties in this category specify how many errors are allowed in a Unica Campaign Snapshot export, what files are saved when you save a flowchart, and the maximum number of IDs for each top-level process in a test run.

maxDataErrorsAllowed

Description

The `maxDataErrorsAllowed` property specifies the maximum number of data conversion errors allowed in an Unica Campaign Snapshot export.

Default value

0 (zero), which allows no errors

saveRunResults

Description

This property lets you save Unica Campaign flowchart run results in the temporary folder and database temp tables. You can adjust this option for individual flowcharts by using **Admin > Advanced Settings** when editing a flowchart.

For flowcharts that create artifacts that you want to save, you must set **saveRunResults** to `TRUE`. For example, if you have flowcharts that include **CreateSeg** processes, you must save run results. If you do not save run results, strategic segments do not persist.

When the value is `TRUE`, the flowchart ("underscore") files are saved and, if you are using **useInDbOptimization**, database temp tables persist.

When the value is `FALSE`, only the `.ses` file is saved. Therefore, you cannot view intermediate results if you reload the flowchart.

Unica Campaign creates many temporary files in the temporary directory, which can cause file systems to be highly utilized or even full. Setting this property to `FALSE` makes the flowchart clean up those files after run completion. However, using a setting of `FALSE` is not always feasible because it prevents you from doing partial flowchart runs.

To save disk space, you can create your own script to delete files in the temporary folder, but you must never delete files for flowcharts that are currently running. To avoid flowchart failures, never delete any files from the temporary folder that are being updated or created today. For maintenance purposes, you can delete files from the temp folder if they are older than 2 days.

Default value

`TRUE`

Valid Values

`TRUE` | `FALSE`

testRunDefaultSize

Description

The `testRunDefaultSize` property specifies the default maximum number of IDs for each top-level process in a Unica Campaign test run. A value of 0 (zero) removes the limitation on the number of IDs.

Default value

0 (zero)

Campaign | partitions | partition[n] | server | profile

Properties in this category specify the maximum number of categories that are created during profiling for numeric and text values in Unica Campaign.

profileMaxTextCategories

Description

The `profileMaxTextCategories` and `profileMaxNumberCategories` properties specify the maximum number of categories created in Unica Campaign during profiling for text and numeric values, respectively.

These values are different from the setting for the number of bins displayed to the user, which can be modified through the user interface.

Default value

1048576

profileMaxNumberCategories

Description

The `profileMaxNumberCategories` and `profileMaxTextCategories` properties specify the maximum number of categories created in Unica Campaign during profiling for numeric and text values, respectively.

These values are different from the setting for the number of bins displayed to the user, which can be modified through the user interface.

Default value

1024

Campaign | partitions | partition[n] | server | internal

Properties in this category specify integration settings and the internalID limits for the selected Unica Campaign partition. If your Unica Campaign installation has multiple partitions, set these properties for each partition that you want to affect.

internalIdLowerLimit

Configuration category

Campaign | partitions | partition[n] | server | internal

Description

The `internalIdUpperLimit` and `internalIdLowerLimit` properties constrain the Unica Campaign internal IDs to be within the specified range. Note that the values are inclusive: that is, Unica Campaign may use both the lower and upper limit.

Default value

0 (zero)

internalIdUpperLimit**Configuration category**

`Campaign|partitions|partition[n]|server|internal`

Description

The `internalIdUpperLimit` and `internalIdLowerLimit` properties constrain the Unica Campaign internal IDs to be within the specified range. The values are inclusive: that is, Unica Campaign may use both the lower and upper limit. If Unica Collaborate is installed, set the value to 2147483647.

Default value

4294967295

eMessageInstalled**Configuration category**

`Campaign|partitions|partition[n]|server|internal`

Description

Indicates that IBM eMessage is installed. When you select `Yes`, IBM eMessage features are available in the Unica Campaign interface.

The installer sets this property to `Yes` for the default partition in your IBM eMessage installation. For additional partitions where you installed IBM eMessage, you must configure this property manually.

Default value

No

Valid Values

Yes | No

interactInstalled

Configuration category

`Campaign|partitions|partition[n]|server|internal`

Description

After installing the Unica Interact design environment, this configuration property should be set to `Yes` to enable the Unica Interact design environment in Unica Campaign.

If Unica Interact is not installed, set to `No`. Setting this property to `No` does not remove Unica Interact menus and options from the user interface. To remove menus and options, you must manually unregister Unica Interact using the `configTool` utility.

Default value

No

Valid Values

Yes | No

Availability

This property is applicable only if you installed Unica Interact.

MO_UC_integration

Configuration category

`Campaign|partitions|partition[n]|server|internal`

Description

Enables integration with Unica Plan for this partition, if the integration is enabled in the **Platform** configuration settings. For more information, see the Unica Plan and Unica Campaign Integration Guide.

Default value

No

Valid Values

Yes | No

MO_UC_BottomUpTargetCells**Configuration category**`Campaign|partitions|partition[n]|server|internal`**Description**

For this partition, allows bottom-up cells for Target Cell Spreadsheets, if **MO_UC_integration** is enabled. When set to `Yes`, both top-down and bottom-up target cells are visible, but bottom-up target cells are read-only. For more information, see the Unica Plan and Unica Campaign Integration Guide.

Default value

No

Valid Values

Yes | No

Legacy_campaigns**Configuration category**`Campaign|partitions|partition[n]|server|internal`**Description**

For this partition, enables access to campaigns created before Unica Plan and Unica Campaign were integrated. Applies only if **MO_UC_integration** is set to `Yes`. Legacy campaigns also include campaigns created in Unica Campaign 7.x and linked to Plan 7.x projects. For more information, see the Unica Plan and Unica Campaign Integration Guide.

Default value

No

Valid Values

Yes | No

Unica Plan - Offer integration

Configuration category

`Campaign|partitions|partition[n]|server|internal`

Description

Enables the ability to use Unica Plan to perform offer lifecycle management tasks on this partition, if **MO_UC_integration** is enabled for this partition. Offer integration must be enabled in your **Platform** configuration settings. For more information, see the Unica Plan and Unica Campaign Integration Guide.

Default value

No

Valid Values

Yes | No

UC_CM_integration

Configuration category

`Campaign|partitions|partition[n]|server|internal`

Description

Enables Digital Analytics online segment integration for a Unica Campaign partition. If you set this value to `Yes`, the Select process box in a flowchart provides the option to select **Digital Analytics Segments** as input. To configure the Digital Analytics integration for each partition, choose **Settings > Configuration > Unica Campaign | partitions | partition[n] | Coremetrics**.

Default value

No

Valid Values

Yes | No

numRowsReadToParseDelimitedFile

Configuration category

`Campaign|partitions|partition[n]|server|internal`

Description

This property is used when mapping a delimited file as a user table. It is also used by the Score process box when importing a score output file from IBM SPSS Modeler Advantage Enterprise Marketing Management Edition. To import or map a delimited file, Unica Campaign needs to parse the file to identify the columns, data types (field types), and column widths (field lengths).

The default value of 100 means Unica Campaign examines the first 50 and the last 50 line entries in the delimited file. Unica Campaign then allocates the field length based on the largest value it finds within those entries. In most cases, the default value is sufficient to determine field lengths. However, in very large delimited files, a later field might exceed the estimated length that Unica Campaign computes, which can cause an error during flowchart runtime. Therefore, if you are mapping a very large file, you can increase this value to make Unica Campaign examine more line entries. For example, a value of 200 makes Unica Campaign examine the first 100 line entries and the last 100 line entries of the file.

A value of 0 examines the entire file. Typically, this is necessary only if you are importing or mapping files that have variable data widths of fields which cannot be identified by reading the first and last few lines. Reading the entire file for extremely large files can increase the required processing time for table mapping and Score process box runs.

Default value

100

Valid Values

0 (all lines) or any positive integer

Campaign | partitions | partition[n] | server | fileDialog

Properties in this category specify the default directories for Unica Campaign input and output data files.

defaultOutputDirectory

Description

The `defaultOutputDirectory` property specifies the path used to initialize the Unica Campaign File Selection dialog. The `defaultOutputDirectory` property is used when an output data file is mapped into Unica Campaign. If no value is specified, the path is read from the environment variable `UNICA_ACDFDIR`.

Default value

No default value defined.

defaultInputDirectory

Description

The `defaultInputDirectory` property specifies the path used to initialize the Unica Campaign File Selection dialog. The `defaultInputDirectory` property is used when an input data file is mapped into Unica Campaign. If no value is specified, the path is read from the environment variable `UNICA_ACDFDIR`.

Default value

No default value defined.

Campaign | partitions | partition[n] | offerCodeGenerator

Properties in this category specify the class, classpath, and configuration string for the offer code generator, and also the cell code generator used to assign a contact process to a Target Cell Spreadsheet cell.

offerCodeGeneratorClass

Description

The `offerCodeGeneratorClass` property specifies the name of the class Unica Campaign uses as its offer code generator. The class must be fully qualified with its package name.

Default value

Note that line breaks have been added for print.

```
com.unica.campaign.core.codegenerator.samples.  
ExecutableCodeGenerator
```

offerCodeGeneratorConfigString

Description

The `offerCodeGeneratorConfigString` property specifies a string that is passed into the offer code generator plug-in when it is loaded by Unica Campaign. By default, the `ExecutableCodeGenerator` (shipped with Unica Campaign) uses this property to indicate the path (relative to Unica Campaign application home directory) to the executable to run.

Default value

```
./bin
```

defaultGenerator

Description

The `defaultGenerator` property specifies the generator for the cell codes that appear in contact-style process boxes and are used to assign cells to Target Control Spreadsheet cells. The Target Control Spreadsheet manages cell and offer mappings for campaigns and flowcharts.

Default value

```
uacoffercodegen.exe
```

offerCodeGeneratorClasspath

Description

The `offerCodeGeneratorClasspath` property specifies the path to the class Unica Campaign uses as its offer code generator. It can be either a full path or a relative path.

If the path ends in a slash (forward slash `/` for UNIX™ or backslash `\` for Windows™), Unica Campaign assumes it to be a path to a directory that contains the Java™ plug-in class that should be used. If the path does not end in a slash, Unica Campaign assumes it is the name of a `jar` file that contains the Java™ class.

If the path is relative, Unica Campaign assumes it is relative to the Unica Campaign application home directory.

Default value

`codeGenerator.jar` (packaged in the `Campaign.war` file)

Campaign | monitoring

Properties in the this category specify whether the Operational Monitoring feature is enabled, the URL of the Operational Monitoring server, and caching behavior. Operational Monitoring displays and allows you to control active flowcharts.

cacheCleanupInterval

Description

The `cacheCleanupInterval` property specifies the interval, in seconds, between automatic cleanups of the flowchart status cache.

This property is not available in versions of Unica Campaign earlier than 7.0.

Default value

600 (10 minutes)

cacheRunCompleteTime

Description

The `cacheRunCompleteTime` property specifies the amount of time, in minutes, that completed runs are cached and display on the Monitoring page.

This property is not available in versions of Unica Campaign earlier than 7.0.

Default value

4320

monitorEnabled

Description

The `monitorEnabled` property specifies whether the monitor is turned on.

This property is not available in versions of Unica Campaign earlier than 7.0.

Default value

FALSE

Valid values

TRUE | FALSE

serverURL

Description

The `Campaign > monitoring > serverURL` property specifies the URL of the Operational Monitoring server. This is a mandatory setting; modify the value if the Operational Monitoring server URL is not the default.

If Unica Campaign is configured to use Secure Sockets Layer (SSL) communications, set the value of this property to use HTTPS. For example:
`serverURL=https://host:SSL_port/Campaign/OperationMonitor` where:

- *host* is the name or IP address of the machine on which the web application is installed
- *SSL_Port* is the SSL port of the web application.

Note the `https` in the URL.

Default value

`http://localhost:7001/Campaign/OperationMonitor`

monitorEnabledForInteract

Description

If set to `TRUE`, enables Unica Campaign JMX connector server for Unica Interact. Unica Campaign has no JMX security.

If set to `FALSE`, you cannot connect to the Unica Campaign JMX connector server.

This JMX monitoring is for the Unica Interact contact and response history module only.

Default value

`FALSE`

Valid Values

`TRUE` | `FALSE`

Availability

This property is applicable only if you have installed Unica Interact.

protocol

Description

Listening protocol for the Unica Campaign JMX connector server, if `monitorEnabledForInteract` is set to `yes`.

This JMX monitoring is for the Unica Interact contact and response history module only.

Default value

`JMXMP`

Valid Values

JMXMP | RMI

Availability

This property is applicable only if you have installed Unica Interact.

port

Description

Listening port for the Unica Campaign JMX connector server, if `monitorEnabledForInteract` is set to yes.

This JMX monitoring is for the Unica Interact contact and response history module only.

Default value

2004

Valid Values

An integer between 1025 and 65535.

Availability

This property is applicable only if you have installed Unica Interact.

Campaign | ProductReindex

The creator of an offer can specify the products that are associated with that offer. When the list of products available for association with offers changes, the offer/product associations must be updated. Properties in the Unica Campaign > ProductReindex category specify the frequency of these updates and the time of day that the first update runs.

startTime

Description

The `startTime` property specifies the time of day when offer/product associations are updated for the first time. The first update occurs on the day after the Unica Campaign server is started, and subsequent updates occur at

intervals specified in the `interval` parameter. The format is `HH:mm:ss`, using a 24-hour clock.

Note that when Unica Campaign first starts up, the `startTime` property is used according to the following rules:

- If the time of day specified by `startTime` is in the future, the first offer/product associations update will occur at `startTime` of the current day.
- If `startTime` is in the past for the current day, the first update will occur at `startTime` tomorrow, or at `interval` minutes from the current time, whichever is earlier.

Default value

12:00:00 (noon)

interval

Description

The `interval` property specifies the time, in minutes, between updates of offer/product associations. The update occurs for the first time at the time specified in the `startTime` parameter, on the day after the Unica Campaign server is started.

Default value

3600 (60 hours)

Campaign | unicaACLlistener

If you are configuring a single-node listener cluster, use this category, and only this category, to define configuration settings for your non-clustered listener. For clustered listeners, the properties in this category pertain to all of the listener nodes in the cluster, except for the following properties, which are ignored: `serverHost`, `serverPort`, `useSSLForPort2`, `serverPort2`. (Instead, set these properties for each individual node, under Campaign|unicaACLlistener|node[n].)

These properties must be set only once per instance of Unica Campaign, they do not need to be set for every partition.

enableWindowsImpersonation

Configuration category

Campaign | unicaACLlistener

Description

This property applies to both clustered and non-clustered listener configurations. For a clustered configuration, this property applies to all of the listener nodes in the cluster.

The `enableWindowsImpersonation` property specifies whether Windows™ impersonation is enabled in Unica Campaign.

Set the value to `TRUE` if you are using Windows™ impersonation. You must configure Windows™ impersonation separately if you want to leverage the Windows™-level security permissions for file access.

Set the value to `FALSE` if you are not using Windows™ impersonation.

Default value

`FALSE`

Valid Values

`TRUE` | `FALSE`

enableWindowsEventLogging

Configuration category

Campaign | unicaACLlistener

Description

This property applies to both clustered and non-clustered listener configurations. For a clustered configuration, this property applies to all of the listener nodes in the cluster.

The `Campaign | unicaACLlistener | enableWindowsEventLogging` property turns Windows™ event logging on or off for Unica Campaign listener events. Set this property to `TRUE` to log to the Windows™ event log.



Attention: Windows™ Event logging can cause issues with flowchart runs. Avoid enabling this feature unless advised by Technical Support.

Default value

`FALSE`

Valid Values

`TRUE | FALSE`

serverHost

Configuration category

`Campaign|unicaACLlistener`

Description

If you have a single-node listener configuration, this property identifies the listener. If you have a clustered listener configuration, this property is ignored. (Instead, set this property for each individual node, under `Campaign|unicaACLlistener|node[n].`)

The `serverHost` property specifies the name or IP address of the machine where the Unica Campaign listener is installed. If the Unica Campaign listener is not installed on the same machine where Unica is installed, change the value to the machine name or IP address of the machine where the Unica Campaign listener is installed.

Default value

`localhost`

logMaxBackupIndex

Configuration category

Campaign|unicaACLlistener

Description

This property applies to both clustered and non-clustered listener configurations. For a clustered configuration, this property applies to all of the listener nodes in the cluster.

The `logMaxBackupIndex` property specifies how many backup files can exist before the oldest one is deleted. If you set this property to 0 (zero), Unica Campaign does not create any backup files and the log file stops logging when it reaches the size you specified in the `logMaxFileSize` property.

If you specify a number (N) for this property, when the log file (`File`) reaches the size you specified in the `logMaxFileSize` property, Unica Campaign renames the existing backup files (`File.1 ... File.N-1`) to `File.2 ... File.N`, renames the current log file `File.1`, closes it, and starts a new log file named `File`.

Default value

1 (creates one backup file)

logStringEncoding

Configuration category

Campaign|unicaACLlistener

Description

This property applies to both clustered and non-clustered listener configurations. For a clustered configuration, this property applies to all of the listener nodes in the cluster.

The `logStringEncoding` property controls the encoding used for all log files. This value must match the encoding used on the operating system. For multi-locale environments, UTF-8 is the preferred setting.

If you change this value, you should empty or remove all affected log files to prevent writing multiple encodings into a single file.



Note: `WIDEUTF-8` is not supported for this setting.

Default value

`native`

Valid Values

See "Character encodings in Unica Campaign" in the Unica Campaign Administrator's Guide.

systemStringEncoding

Configuration category

`Campaign|unicaACLlistener`

Description

This property applies to both clustered and non-clustered listener configurations. For a clustered configuration, this property applies to all of the listener nodes in the cluster.

The `systemStringEncoding` property indicates which encodings Unica Campaign uses to interpret values received from and sent to the operating system, such as file system paths and filenames. In most cases, you can set this value to `native`. For multi-locale environments, use `UTF-8`.

You can specify more than one encoding, separated by commas. For example:

`UTF-8,ISO-8859,CP950`



Note: `WIDEUTF-8` is not supported for this setting.

Default value

`native`

Valid Values

See Character encodings in Unica Campaign in the Unica Campaign Administrator's Guide.

loggingLevels

Configuration category

Campaign | unicaACLlistener

Description

This property applies to both clustered and non-clustered listener configurations. For a clustered configuration, this property applies to all of the listener nodes in the cluster.

The Campaign > unicaACLlistener > loggingLevels property controls the amount of detail written to the log file.

This property applies to both clustered and non-clustered configurations.

Default value

MEDIUM

Valid Values

- LOW
- MEDIUM
- HIGH

maxReuseThreads

Configuration category

Campaign | unicaACLlistener

Description

This property applies to both clustered and non-clustered listener configurations. For a clustered configuration, this property applies to all of the listener nodes in the cluster.

This property sets the number of operating system threads cached by the Unica Campaign listener process (`unica_aclsnr`) for reuse.

It is a best practice to use the cache when you want to reduce the overhead of thread allocation, or with operating systems that can exhibit an inability to release threads when asked to do so by an application.

This property applies to both clustered and non-clustered configurations.

Default value

0 (zero), which disables the cache

logMaxFileSize

Configuration category

`Campaign|unicaACLlistener`

Description

This property applies to both clustered and non-clustered listener configurations. For a clustered configuration, this property applies to all of the listener nodes in the cluster.

The `logMaxFileSize` property specifies the maximum size, in bytes, that the log file can reach before rolling into the backup file.

This property applies to both clustered and non-clustered configurations.

Default value

10485760 (10 MB)

windowsEventLoggingLevels

Configuration category

`Campaign|unicaACLlistener`

Description

This property applies to both clustered and non-clustered listener configurations. For a clustered configuration, this property applies to all of the listener nodes in the cluster.

The `windowsEventLoggingLevels` property controls the amount of detail written to the Windows™ event log file based on severity.

This property applies to both clustered and non-clustered configurations.

Default value

MEDIUM

Valid Values

- LOW
- MEDIUM
- HIGH
- ALL

The `ALL` level includes trace messages intended for diagnostic purposes.

serverPort

Configuration category

`Campaign|unicaACLlistener`

Description

If you have a single-node listener configuration, this property identifies the listener port. If you have a clustered listener configuration, this property is ignored. (Instead, set this property for each individual node, under `Campaign|unicaACLlistener|node[n].`)

The `serverPort` property specifies the port where a single (non-clustered) Unica Campaign listener is installed.

Default value

4664

useSSL

Configuration category

Campaign|unicaACLlistener

Description

This property applies to both clustered and non-clustered listener configurations. For a clustered configuration, this property applies to all of the listener nodes in the cluster.

The `useSSL` property specifies whether to use Secure Sockets Layer for communications between the Unica Campaign listener and the Unica Campaign web application.

Also see the description for the `serverPort2` property, in this category.

Default value

no

Valid Values

yes | no

serverPort2

Configuration category

Campaign|unicaACLlistener

Description

This property is optional.

This property applies only to a single-node listener configuration. If you have a clustered listener configuration, this property is ignored. (Instead, define `serverPort2` for each individual node, under Campaign|unicaACLlistener|node[n].)

The `serverPort2` property, in conjunction with the `useSSLForPort2` property, also in this category, enables you to specify the use of SSL for communication between the Unica Campaign listener and flowchart processes, separately

from the communication between the Unica Campaign web application and listener, which is specified by the `serverPort` and `useSSL` properties in this category.

All communication between Unica Campaign components, (between the web application and listener and between the listener and server) use the mode specified by the `useSSL` property under any of the following conditions.

- `serverPort2` is set to its default value of 0, **or**
- `serverPort2` is set to the same value as `serverPort`, **or**
- `useSSLForPort2` is set to the same value as `useSSL`

In these cases, a second listener port is not enabled, and communication between the Unica Campaign listener and the flowchart (server) processes and communication between the listener and the Unica Campaign web application use the same mode: either both non-SSL or both SSL, depending on the value of the `useSSL` property.

The listener uses two different modes of communication when both of the following conditions exist.

- `serverPort2` is set to a non-0 value different from the value of `serverPort`, **and**
- `useSSLForPort2` is set to a value different from the value of `useSSL`

In this case, a second listener port is enabled, and the listener and flowchart processes use the mode of communication specified by `useSSLForPort2`.

The Unica Campaign web application always uses the communication mode specified by `useSSL` when communicating to the listener.

When SSL is enabled for communication between the Unica Campaign listener and flowchart processes, set the value of this property (`serverPort2`) to an appropriate port.

Default value

0

useSSLForPort2

Configuration category

`Campaign|unicaACLlistener`

Description

This property applies only to a single-node listener configuration. If you have a clustered listener configuration, this property is ignored. (Instead, define `useSSLForPort2` for each individual node, under `Campaign|unicaACLlistener|node[n].`)

For information, see the description for `serverPort2`, in this category.

Default value

FALSE

Valid Values

TRUE | FALSE

keepalive

Configuration category

`Campaign|unicaACLlistener`

Description

This property applies to both clustered and non-clustered listener configurations. For a clustered configuration, this property applies to all of the listener nodes in the cluster.

Use the `keepalive` property to specify, in seconds, the frequency with which the Unica Campaign web application server sends keep alive messages on otherwise-inactive socket connections to the Unica Campaign listener.

Using the `keepalive` configuration parameter enables socket connections to remain open through extended periods of application inactivity in environments configured to close inactive connections between the web application and the listener (for example, a firewall).

When there is activity on a socket, the keep alive period is automatically reset. At the DEBUG logging level in the web application server, the `campaignweb.log` will show evidence of the keep alive messages as they are sent to the listener.

Default value

0, which disables the keepalive feature

Valid Values

positive integers

loggingCategories

Configuration category

`Campaign|unicaACLListener`

Description

This property specifies the category of messages written to the Unica Campaign listener log file.

The `loggingCategories` property in conjunction with the `loggingLevels` property determines the severity of the messages that are logged for all selected categories.

Specify one or more categories in a comma separated list. Use the `ALL` option to include logs for all categories.

Default value

`ALL`

Valid Values



Note: The corresponding Logging Options are indicated in parentheses after each configuration value.

`ALL`

`GENERAL (Others)`

COMMANDS (External interface)

SYS CALL (System Call)

UDB (udb)

XML (xml)

Campaign | unicaACLlistener | node [n]

A non-clustered listener configuration should not have any nodes under this category. Nodes are created and used only for clustered listener configurations. For a clustered listener configuration, configure an individual child node for each listener in the cluster.

If clustering is enabled, you must configure at least one child node or an error occurs during startup.



Important: Never remove a node from the configuration unless you first stop all of the clustered listener nodes. Otherwise, any existing sessions on the removed listener continue to run but the master listener will not be able to contact the removed listener node. This can cause unexpected results.

serverHost

Configuration category

Campaign | unicaACLlistener | node [n]

Description

This property applies only if you have a clustered listener configuration. This property identifies each individual listener node in a cluster.

For each node, specify the hostname of the machine where the Unica Campaign listener is installed.

Default value

No default value assigned.

serverPort

Configuration category

`Campaign|unicaACListener|node[n]`

Description

This property applies only if you have a clustered listener configuration. This property identifies the port that is used for communication between each clustered listener node and the Unica Campaign web application server.

The specified port is also used for communication between listener nodes.

Default value

No default value assigned.

useSSLForPort2

Configuration category

`Campaign|unicaACListener|node[n]`

Description

Optional. This property applies only if you have a clustered listener configuration. You can set this property for each clustered listener node.

For information about how to use this property, read the description for

`Campaign|unicaACListener|serverPort2`.

Default value

FALSE

Valid Values

TRUE | FALSE

serverPort2

Configuration category

`Campaign|unicaACListener|node[n]`

Description

Optional. This property applies only if you have a clustered listener configuration. You can set this property for each clustered listener node. For information about how to use this property, read the description for `Campaign|unicaACListener|serverPort2`.

Default value

3

masterListenerPriority**Configuration category**`Campaign|unicaACListener|node[n]`**Description**

This property applies only if you have a clustered listener configuration.

A cluster always includes one master listener. All clients, including the Unica Campaign web server application, the Unica Campaign Server Manager (unica_svradm), and utilities such as unica_acsesutil, use the masterListenerPriority to identify the master listener.

Any node in the cluster can act as the master listener. The masterListenerPriority determines which node initially acts as the master listener. It also determines which listener will take over as the master listener in failover situations. Ideally, the listener node with the most processing power should be assigned the highest priority.

Priority 1 is the highest priority. Assign a 1 to the machine that you want to be the master listener. That machine will serve as the master listener unless it goes down or cannot be contacted, for example due to a network issue. Assign a 2 to the next machine, and so on.

You must assign a priority to every listener in the cluster. If you do not want a machine to serve as the master listener, assign it the lowest priority (10). However, you cannot prohibit a listener from being designated as master. In a clustered listener configuration, one listener must always serve as the master.

If the designated master listener cannot be contacted, then the next machine becomes the master listener, based on its assigned priority.

If multiple nodes have the same priority, the system selects the first of those nodes from the list of nodes in this category.



Note: After you change the priority, run the `unica_svradm refresh` command to inform the master listener of the change.

Default value

No default value assigned.

Valid Values

1 (high) through 10 (low)

loadBalanceWeight

Configuration category

`Campaign|unicaACLlistener|node[n]`

Description

This property applies only if you have a clustered listener configuration. This property controls load balancing among clustered nodes. Each node in a cluster can process a portion of the total application traffic. Adjust the weight for each listener node to determine how much load the node will get. A higher value assigns a greater proportion of the load, so more transactions are given to that listener node.

Assign higher values to machines that have more processing capacity. Assign lower values to less powerful or more heavily loaded machines. A value of 0 prohibits the listener from processing any transactions and typically is not used. If multiple nodes have the same weight, the system selects the first of those nodes from the list of nodes in this category.



Note: After you change the weight, run the `unica_svradm refresh` command to inform the master listener of the change.

Example

You have four physical hosts: A, B, C and D.

Host A is the most powerful machine and Host D is the least capable, so you assign weights as: A=4, B=3, C=2, D=1 In terms of loads handled, listeners will process loads in these proportions: A - 40%, B - 30%, C - 20%, D - 10% For each incoming request to handle Campaign flowchart or Optimize session executions, the master listener will try to see that the listeners have loads in above proportion. For example, if after calculating total load across all the listeners A is having 30% of load then the next request will go to A.

Default value

No default value assigned.

Valid Values

0 through 10 (highest priority)

ListenerType

Configuration Category

Campaign | unicaACLlistener | node[n]

Description

This property applies, if you have a clustered listener configuration. This property controls execution of flowchart and optimize session among clustered nodes. Each node in a cluster can execute either flowchart or optimize session or both. Choose a type for each listener node to determine what a node can execute.

Value-1 shows that this particular node executes only flowcharts. No Optimize session execution request can be redirected to this type of listener node.

Value-2 shows that this particular node only executes Optimize sessions. No flowchart execution request can be redirected to this type of listener node.

Value-3 shows that this particular node executes both flowcharts and optimize sessions. So any request can be redirected to this type of node.



Note: After you change the listenerType, run the `unica_svradm refresh` command to inform the master listener of the change.

Default value

No default value assigned

Valid value

1|2|3

Campaign | campaignClustering

Set these properties if you have a clustered listener configuration. Set these properties once per instance of Unica Campaign; you do not need to set them for every partition.

enableClustering

Configuration category

`Campaign|campaignClustering`

Description

If you have a single listener, leave the value set to `FALSE`. This causes all of the other properties in this category to be ignored, because they do not apply to a single-node configuration.

For a clustered listener configuration, set the value to `TRUE`, configure the other properties in this category, then configure listener nodes under `Campaign|unicaACLlistener|node[n]`. When the value is `TRUE`, you must define at least one child node. If you do not define at least one child node, an error occurs during startup.

When the value is `TRUE`, the following properties are ignored for `Campaign|unicaACLListener` and are instead defined for each individual node under `Campaign|unicaACLListener|node[n]: serverHost, serverPort, serverPort2, useSSLForPort2`.

Default value`FALSE`**Valid Values**`TRUE | FALSE`**masterListenerLoggingLevel****Configuration category**`Campaign|campaignClustering`**Description**

This property applies only if `enableClustering` is `TRUE`. This property controls the amount of detail that is written to the master listener log file (`<campaignSharedHome>/logs/masterlistener.log`).

The default value of `LOW` provides the least detail (only the most severe error messages are written). `ALL` includes trace debug messages and is intended for diagnostic purposes.

Default value`MEDIUM`**Valid Values**`LOW | MEDIUM | HIGH | ALL`**masterListenerHeartbeatInterval****Configuration category**`Campaign|campaignClustering`**Description**

This property applies only if `enableClustering` is `TRUE`. This property affects the master listener. Specify how often the master listener tries to connect to all of the configured listener nodes to identify their availability. When the master listener connects to the nodes for availability, it also sends a heartbeat message to inform them that the master listener is alive. Therefore, this property serves two purposes (1) Heartbeat from master listener (2) Status response from each listener node.

Default value

10 seconds

webServerDelayBetweenRetries**Configuration category**

`Campaign|campaignClustering`

Description

This property applies only if `enableClustering` is `TRUE`. This property specifies the time delay between retries for the Unica Campaign web application server to attempt to connect to the Unica Campaign listener.

Default value

5 seconds

webServerRetryAttempts**Configuration category**

`Campaign|campaignClustering`

Description

This property applies only if `enableClustering` is `TRUE`. This property indicates how many times the Unica Campaign web application server attempts to connect to the Unica Campaign listener.

Default value

3

campaignSharedHome

Configuration category

Campaign|campaignClustering

Description

This property applies only if `enableClustering` is TRUE.

In a clustered configuration, listener nodes share the files and folders indicated below. The shared location is specified at installation time.

```
campaignSharedHome
|--->/conf
|-----> activeSessions.udb
|-----> deadSessions.udb
|-----> etc.
|--->/logs
|-----> masterlistener.log
|-----> etc.
|--->/partitions
|-----> partition[n]
|-----> {similar to <Campaign_home> partition folder
structure}
```



Note: Each listener also has its own set of folders and files that are not shared, at `<Campaign_home>` (the Unica Campaign application installation directory).

masterListenerLoggingCategories

Configuration category

Campaign|campaignClustering

Description

This property specifies the category of messages written to the Unica Campaign master listener log file.

The `masterListenerLoggingCategories` property in conjunction with the `masterListenerLoggingLevel` property determines the severity of the messages that are logged for all selected categories.

Specify one or more categories in a comma separated list. Use the `ALL` option to include logs for all categories.

Default value

`ALL`

Valid Values



Note: The corresponding Logging Options are indicated in parentheses after each configuration value.

`ALL`

`FILE_ACCESS` (File operations)

`GENERAL` (Others)

`COMMANDS` (External interface)

Campaign | unicaACOOptAdmin

These configuration properties define settings for the unicaACOOptAdmin tool.

getProgressCmd

Description

Specifies a value that is used internally. Do not change this value.

Default value

`optimize/ext_optimizeSessionProgress.do`

Valid Values

```
optimize/ext_optimizeSessionProgress.do
```

runSessionCmd

Description

Specifies a value that is used internally. Do not change this value.

Default value

```
optimize/ext_runOptimizeSession.do
```

Valid Values

```
optimize/ext_runOptimizeSession.do
```

loggingLevels

Description

The `loggingLevels` property controls the amount of detail that is written to the log file for the Unica Optimize command-line tool, which is based on severity. Available levels are LOW, MEDIUM, HIGH, and ALL, with LOW providing the least detail (that is, only the most severe messages are written). The ALL level includes trace messages and is intended primarily for diagnostic purposes.

Default value

HIGH

Valid Values

LOW | MEDIUM | HIGH | ALL

cancelSessionCmd

Description

Specifies a value that is used internally. Do not change this value.

Default value

```
optimize/ext_stopOptimizeSessionRun.do
```

Valid Values

`optimize/ext_stopOptimizeSessionRun.do`

logoutCmd**Description**

Specifies a value that is used internally. Do not change this value.

Default value

`optimize/ext_doLogout.do`

Valid Values

`optimize/ext_doLogout.do`

getProgressWaitMS**Description**

Set this value to the number (integer) of milliseconds between two successive polls to the web application to get progress information. This value is not used if you do not set `getProgressCmd`.

Default value

1000

Valid Values

An integer greater than zero

Campaign | server

The property in this category specifies a URL that is used internally, and does not need to be changed.

fullContextPath**Description**

The `fullContextPath` specifies the URL that Unica Campaign flowcharts use to communicate to the application server Listener proxy. This property

is undefined by default, which causes the system to determine the URL dynamically. When Unica Platform is integrated with the Tivoli® web access control platform, you must set this property to the Unica Campaign URL in Tivoli®.

Default value

No default value defined.

numRetryServerCommand**Description**

The `numRetryServerCommand` specifies the maximum number of times the Campaign web application can call the Campaign analytical server (listener) command until it receives a successful result. If the Campaign application continues to receive a non-success response after the maximum number of tries, a `Server Busy` error is displayed on the user interface.

Modify this parameter based on the Campaign Analytics server response time, the network speed and latency.

Default value

5

Campaign | logging

This category specifies the location of the Unica Campaign `log4jConfig` properties file.

log4jConfig**Description**

The Unica Campaign web application uses the Apache log4j utility for logging configuration, debugging, and error information.

The `log4jConfig` property specifies the location of the Unica Campaign log properties file, `campaign_log4j.properties`. Specify the path relative to the Unica Campaign home directory, including the file name. Use forward slashes (/) for UNIX™ and backslashes (\) for Windows™.

Default value

```
./conf/campaign_log4j.properties
```

Campaign | proxy

The Unica Campaign, Engage, and UBX integration is supported with outbound proxy connections.

To access these properties, choose **Settings > Configuration**.

Proxy host name**Description**

Specify the hostname or the IP address of your proxy server.

Proxy port number**Description**

Specify the port number of your proxy server.

Proxy type**Description**

Select the proxy server type.

Default value

HTTP

Valid value

HTTP, SOCK5

Data source for credentials**Description**

Specify the datasource name that contains the proxy server user name and password details.

Platform user with data source for proxy credentials

Description

Specify the name of the Platform user that has the specified datasource in the **Data source for credentials** property.



Note: When you deploy Campaign on a WebLogic server and HTTP proxy is configured, you need to add the variable `DUseSunHttpHandler=true` in `JAVA_OPTION` to the `setDomainEnv.cmd` file.

IBM eMessage configuration properties

This section describes the IBM eMessage configuration properties found on the Configuration page.

IBM eMessage | serverComponentsAndLocations | hostedServices

Define properties to specify the URLs for connecting to IBM Hosted Services. IBM eMessage uses separate connections for uploading recipient lists, metadata that describes recipient lists, and for general communication sent to the hosted environment.

You must change the default values if you are connecting to IBM Hosted Services through the data center.

uiHostName

Description

The address that IBM eMessage uses for all communication to IBM Hosted Services, except uploading recipient lists and related metadata.

Default value

`em.unicaondemand.com`

If you are connecting to the UK data center, change this value to `em-eu.unicaondemand.com`.

dataHostName

Description

The address that IBM eMessage uses for uploading metadata that is related to recipient lists to IBM Hosted Services.

Default value

`em.unicaondemand.com`

If you are connecting to the UK data center, change this value to `em-eu.unicaondemand.com`.

ftpHostName

Description

The address that IBM eMessage uses for uploading recipient list data (except list metadata) to IBM Hosted Services.

Default value

`ftp-em.unicaondemand.com`

If you are connecting to the UK data center, change this value to `ftp-em-eu.unicaondemand.com`.

IBM eMessage | partitions | partition[n] | hostedAccountInfo

Define properties in this category to define user credentials for the database that contains account information that is required to access IBM Hosted Services. Values that you specify here must be defined as user settings in the Unica Platform.

amUserForAcctCredentials

Description

Use this property to specify the Unica Platform user that contains a Unica Platform data source that specifies the account access credentials that are required to access IBM Hosted Services.

Default value

asm_admin

Valid Values

Any Unica Platform user.

amDataSourceForAcctCredentials

Description

Use this property to specify the Unica Platform data source that defines login credentials for IBM Hosted Services.

Default value

UNICA_HOSTED_SERVICES

Valid Values

A data source that is associated with the user you specify in

`amUserForAcctCredentials`

IBM eMessage | partitions | partition[n] | dataSources | systemTables

This category contains configuration properties that define the schema, connection settings, and login credentials for the database that contains the IBM eMessage system tables in your network environment.

type

Description

Type of database that hosts the IBM eMessage system tables.

Default value

No default value defined. You must define this property.

Valid Values

- SQLSERVER
- ORACLE9
- ORACLE10 (also used to indicate Oracle 11 databases)
- DB2

schemaName

Description

Name of the database schema for the IBM eMessage system tables. This is the same as the schema name for the Unica Campaign system tables.

You must include this schema name when referencing system tables in scripts.

Default value

dbo

jdbcBatchSize

Description

The number of execution requests JDBC runs on the database at a time.

Default value

10

Valid Values

An integer greater than 0.

jdbcClassName

Description

JDBC driver for system tables as defined in your Unica Campaign web server.

Default value

No default value defined. You must define this property.

jdbcURI

Description

JDBC connection URI for system tables as defined in your Unica Campaign web server.

Default value

No default value defined. You must define this property.

asmUserForDBCredentials

Description

Use this property to specify an Unica user that will be allowed to access the IBM eMessage system tables.

Default value

No default value defined. You must define this property.

Valid Values

Any user defined in the Unica Platform. This should typically be the name of the system user for Unica Campaign

amDataSourceForDBCredentials

Description

Use this property to specify the data source that defines login credentials for the database that contains the IBM eMessage system tables. This can be the same as the data source for the Unica Campaign system tables.

Default value

UA_SYSTEM_TABLES

Valid Values

A Unica Platform data source associated with the Unica user you specify in `asmUserForDBCredentials`

The data source specifies a database user and credentials used to access the IBM eMessage system tables. If the default schema for the database user is not the schema that contains the system tables you must specify the system table schema in the JDBC connection used to access the system tables.

poolAcquireIncrement

Description

When the database connection pool runs out of connections, the number of new connections IBM eMessage creates for the system tables. IBM eMessage creates new connections up to the number specified in `poolMaxSize`.

Default value

1

Valid Values

An integer greater than 0.

poolIdleTestPeriod

Description

The number of seconds IBM eMessage waits between testing idle connections to the IBM eMessage system tables for activity.

Default value

100

Valid Values

An integer greater than 0.

poolMaxSize

Description

The maximum number of connections IBM eMessage makes to the system tables. A value of zero (0) indicates there is no maximum.

Default value

100

Valid Values

An integer greater than or equal to 0.

poolMinSize

Description

The minimum number of connections IBM eMessage makes to the system tables.

Default value

10

Valid Values

An integer greater than or equal to 0.

poolMaxStatements

Description

The maximum number of statements that IBM eMessage stores in the PrepareStatement cache per connection to the system tables. Setting poolMaxStatements to zero (0) disables statement caching.

Default value

0

Valid Values

An integer equal to or greater than 0.

timeout

Description

The number of seconds IBM eMessage maintains an idle database connection before dropping the connection.

If `poolIdleTestPeriod` is greater than 0, IBM eMessage tests all idle, pooled, but unchecked-out connections, every `timeout` number of seconds.

If `poolIdleTestPeriod` is greater than `timeout`, the idle connections are dropped.

Default value

100

Valid Values

An integer equal to or greater than 0.

IBM eMessage | partitions | partition[n] | recipientListUploader

This configuration category contains an optional property for the location of a user-defined script that runs in response to the actions or status of the Recipient List Uploader.

pathToTriggerScript

Description

You can create a script that triggers an action in response to the upload of a recipient list to IBM Hosted Services. For example, you can create a script to send an email alert to the list designer when the list upload completes successfully.

If you define a value for this property, IBM eMessage passes status information about the Recipient List Uploader to the specified location. IBM eMessage takes no action if you leave this property blank.

Default value

No default value defined.

Valid Values

Any valid network path.

IBM eMessage | partitions | partition[n] | responseContactTracker

Properties in this category specify behavior for the Response and Contact Tracker (RCT). The RCT retrieves and processes data for email contacts, email delivery, and recipient responses, such as link clicks and opens.

pauseCustomerPremisesTracking

Description

IBM eMessage stores contact and response data in a queue in IBM Hosted Services. This property allows you to instruct the RCT to temporarily stop retrieving data from IBM Hosted Services. When you resume tracking, the RCT downloads the accumulated data.

Default value

False

Valid Values

True | False

waitTimeToCheckForDataAvailability

Description

The RCT periodically checks for new data regarding email contacts or recipient responses. This property allows you to specify how often, in seconds, the RCT checks for new data in IBM Hosted Services. The default value is 300 seconds, or every 5 minutes.

Default value

300

Valid Values

Any integer greater than 1.

perfLogInterval

Description

This property allows you to specify how often the RCT logs performance statistics to a log file. The value you enter determines the number of batches between log entries.

Default value

10

Valid Values

An integer greater than 0.

enableSeparatePartialResponseDataTracking**Description**

This property determines if IBM eMessage forwards partial email response data to the tracking tables in your local IBM eMessage installation.

IBM eMessage requires the Mailing Instance ID and Message Sequence Number to properly attribute email responses. When you enable separate partial response data tracking, IBM eMessage places the incomplete responses in separate local tracking tables where you can review them or perform additional processing.

Default value

True

Valid Values

True | False

enableExecutionHistoryDataTracking**Description**

This property controls whether you can download additional mailing execution history data from IBM Hosted Services.

By default, this property is set to **False**, to prevent download of additional data. When you set this property to **True**, you can download data about mailing runs that is not ordinarily entered to the IBM eMessage system tables. You can

use this supplementary information to help automate mailing and database management.

This property is hidden by default. You can display this configuration property in your local IBM eMessage installation by running the `switch_config_visibility.bat` script, located in the `emessage\tools` directory.

Access to mailing execution history data is available by request from IBM. To request access to additional mailing execution history data, contact your IBM representative at eacctsvc@us.ibm.com.

Default value

False

Valid Values

True | False

Unica Interact configuration properties

This section describes the Unica Interact configuration properties found on the Configuration page.

Unica Interact runtime environment configuration properties

This section describes all the configuration properties for the Unica Interact runtime environment.

Interact | general

These configuration properties define general settings for your runtime environment environment, including the default logging level and the locale setting.

log4jConfig

Description

The location of the file containing the log4j properties. This path can be either absolute or relative to the `INTERACT_HOME` environment variable. `INTERACT_HOME` is the location of the Unica Interact installation directory.

Default value

```
./conf/interact_log4j2.xml
```

asmUserForDefaultLocale**Description**

The `asmUserForDefaultLocale` property defines the Unica user from which Unica Interact derives its locale settings.

The locale settings define what language displays in the design time and run time what language advisory messages from the Unica Interact API are in. If the locale setting does not match your machines operating system settings, Unica Interact still functions, however the design time display and advisory messages may be in a different language.

Default value

```
asm_admin
```

configurationRefreshInMins**Description**

The Admin User with Admin Role (Platform) can turn on or off the feature for dynamically update configuration data by setting the configuration refresh in minutes value ≤ 0 (off) or > 0 (on). For example, the current value of configuration refresh in minutes is 5 minute. The configuration changes may need up to 5 minutes to be effective. The new set value of configuration refresh then take effect in minutes. The system will refresh some of the config data as per the new changed value after this.

Note: Auto refresh is not supported for the following configuration parameters:

1. General – all data source config no support, only top level config support
2. Monitoring
3. profile
4. cacheManagement
5. triggeredMessage
6. activityOrchestrator
7. simulator
8. ETL

Interact | general | learningTablesDataSource

These configuration properties define the data source settings for the built-in learning tables. You must define this data source if you are using Unica Interact built-in learning.

If you create your own learning implementation using the Learning API, you can configure your custom learning implementation to read these values using the `ILearningConfig` interface.

jndiName

Description

Use this `jndiName` property to identify the Java™ Naming and Directory Interface (JNDI) data source that is defined in the application server (Websphere or WebLogic) for the learning tables accessed by Unica Interact runtime servers.

The learning tables are created by the `aci_lrntab` ddl file and contain the following tables (among others): `UACI_AttributeValue` and `UACI_OfferStats`.

Default value

No default value defined.

type

Description

The database type for the data source used by the learning tables accessed by the Unica Interact runtime servers.

The learning tables are created by the `aci_lrntab` ddl file and contain the following tables (among others): `UACI_AttributeValue` and `UACI_OfferStats`.

Default value

SQLServer

Valid Values

SQLServer | DB2® | ORACLE | MARIADB| INFORMIX

connectionRetryPeriod**Description**

The `ConnectionRetryPeriod` property specifies the amount of time in seconds Unica Interact automatically retries the database connection request on failure for the learning tables. Unica Interact automatically tries to reconnect to the database for this length of time before reporting a database error or failure. If the value is set to 0, Unica Interact will retry indefinitely; if the value is set to -1, no retry will be attempted.

The learning tables are created by the `aci_lrntab` ddl file and contain the following tables (among others): `UACI_AttributeValue` and `UACI_OfferStats`.

Default value

-1

connectionRetryDelay**Description**

The `ConnectionRetryDelay` property specifies the amount of time in seconds Unica Interact waits before it tries to reconnect to the database after a failure for the learning tables. If the value is set to -1, no retry will be attempted.

The learning tables are created by the `aci_lrntab` ddl file and contain the following tables (among others): `UACI_AttributeValue` and `UACI_OfferStats`.

Default value

-1

schema**Description**

The name of the schema containing the tables for the built-in learning module. Unica Interact inserts the value of this property before all table names, for example, `UACI_IntChannel` becomes `schema.UACI_IntChannel`.

You do not have to define a schema. If you do not define a schema, Unica Interact assumes that the owner of the tables is the same as the schema. You should set this value to remove ambiguity.

Default value

No default value defined.

Interact | general | prodUserDataSource

These configuration properties define the data source settings for the production profile tables. You must define this data source. This is the data source the runtime environment references when running interactive flowcharts after deployment.

jndiName**Description**

Use this `jndiName` property to identify the Java™ Naming and Directory Interface (JNDI) data source that is defined in the application server (Websphere or WebLogic) for the customer tables accessed by Unica Interact runtime servers.

Default value

No default value defined.

type

Description

The database type for the customer tables accessed by Unica Interact runtime servers.

Default value

SQLServer

Valid Values

SQLServer | DB2® | ORACLE | MARIADB| INFORMIX

aliasPrefix

Description

The `AliasPrefix` property specifies the way Unica Interact forms the alias name that Unica Interact creates automatically when using a dimension table and writing to a new table in the customer tables accessed by Unica Interact runtime servers..

Note that each database has a maximum identifier length; check the documentation for the database you are using to be sure that the value you set does not exceed the maximum identifier length for your database.

Default value

A

connectionRetryPeriod

Description

The `ConnectionRetryPeriod` property specifies the amount of time in seconds Unica Interact automatically retries the database connection request on failure for the runtime customer tables. Unica Interact automatically tries to reconnect to the database for this length of time before reporting a database error or failure. If the value is set to 0, Unica Interact will retry indefinitely; if the value is set to -1, no retry will be attempted.

Default value

-1

connectionRetryDelay

Description

The `connectionRetryDelay` property specifies the amount of time in seconds Unica Interact waits before it tries to reconnect to the database after a failure for the Unica Interact runtime customer tables. If the value is set to -1, no retry will be attempted.

Default value

-1

schema

Description

The name of the schema containing your profile data tables. Unica Interact inserts the value of this property before all table names, for example, `UACI_IntChannel` becomes `schema.UACI_IntChannel`.

You do not have to define a schema. If you do not define a schema, Unica Interact assumes that the owner of the tables is the same as the schema. You should set this value to remove ambiguity.

When you use a DB2 database, the schema name must be upper case.

Default value

No default value defined.

Interact | general | systemTablesDataSource

These configuration properties define the data source settings for the system tables for runtime environment. You must define this data source.

jndiName

Description

Use this `jndiName` property to identify the Java™ Naming and Directory Interface (JNDI) data source that is defined in the application server (Websphere or WebLogic) for the runtime environment tables.

The runtime environment database is the database populated with the `aci_runtime` and `aci_populate_runtime` dll scripts and, for example, contains the following tables (among others): `UACI_CHOfferAttrib` and `UACI_DefaultedStat`.

Default value

No default value defined.

type

Description

The database type for the runtime environment system tables.

The runtime environment database is the database populated with the `aci_runtime` and `aci_populate_runtime` dll scripts and, for example, contains the following tables (among others): `UACI_CHOfferAttrib` and `UACI_DefaultedStat`.

Default value

SQLServer

Valid Values

SQLServer | DB2® | ORACLE | MARIADB | INFORMIX

connectionRetryPeriod

Description

The `ConnectionRetryPeriod` property specifies the amount of time in seconds Unica Interact automatically retries the database connection request on failure for the runtime system tables. Unica Interact automatically tries to reconnect to the database for this length of time before reporting a database

error or failure. If the value is set to 0, Unica Interact will retry indefinitely; if the value is set to -1, no retry will be attempted.

The runtime environment database is the database populated with the `aci_runtime` and `aci_populate_runtime` dll scripts and, for example, contains the following tables (among others): `UACI_CHOfferAttrib` and `UACI_DefaultedStat`.

Default value

-1

connectionRetryDelay**Description**

The `ConnectionRetryDelay` property specifies the amount of time in seconds Unica Interact waits before it tries to reconnect to the database after a failure for the Unica Interact runtime system tables. If the value is set to -1, no retry will be attempted.

The runtime environment database is the database populated with the `aci_runtime` and `aci_populate_runtime` dll scripts and, for example, contains the following tables (among others): `UACI_CHOfferAttrib` and `UACI_DefaultedStat`.

Default value

-1

schema**Description**

The name of the schema containing the tables for the runtime environment. Unica Interact inserts the value of this property before all table names, for example, `UACI_IntChannel` becomes `schema.UACI_IntChannel`.

You do not have to define a schema. If you do not define a schema, Unica Interact assumes that the owner of the tables is the same as the schema. You should set this value to remove ambiguity.

Default value

No default value defined.

Interact | general | systemTablesDataSource | loaderProperties

These configuration properties define the settings a database loader utility for the system tables for runtime environment. You need to define these properties if you are using a database loader utility only.

databaseName**Description**

The name of the database the database loader connects to.

Default value

No default value defined.

LoaderCommandForAppend**Description**

The `LoaderCommandForAppend` parameter specifies the command issued to invoke your database load utility for appending records to the contact and response history staging database tables in Unica Interact. You need to set this parameter to enable the database loader utility for contact and response history data.

This parameter is specified as a full path name either to the database load utility executable or to a script that launches the database load utility. Using a script allows you to perform additional setup before invoking the load utility.

Most database load utilities require several arguments to be successfully launched. These can include specifying the data file and control file to load from and the database and table to load into. The tokens are replaced by the specified elements when the command is run.

Consult your database load utility documentation for the correct syntax to use when invoking your database load utility.

This parameter is undefined by default.

Tokens available to `LoaderCommandForAppend` are described in the following table.

Token	Description
<CONTROLFILE>	This token is replaced with the full path and filename to the temporary control file that Unica Interact generates according to the template that is specified in the <code>LoaderControlFileTemplate</code> parameter.
<DATABASE>	This token is replaced with the name of the data source into which Unica Interact is loading data. This is the same data source name used in the category name for this data source.
<DATAFILE>	This token is replaced with the full path and filename to the temporary data file created by Unica Interact during the loading process. This file is in the Unica Interact Temp directory, <code>UNICA_ACTMPDIR</code> .
<DBCOLUMN-NUMBER>	This token is replaced with the column ordinal in the database.
<FIELDLENGTH>	This token is replaced with the length of the field being loaded into the database.
<FIELDNAME>	This token is replaced with the name of the field being loaded into the database.
<FIELDNUMBER>	This token is replaced with the number of the field being loaded into the database.
<FIELDTYPE>	This token is replaced with the literal "CHAR()". The length of this field is specified between the (). If your database happens to not understand the field type, CHAR, you can manually specify the appropriate text

Token	Description
	for the field type and use the <FIELDLENGTH> token. For example, for SQLSVR and SQL2000 you would use "SQLCHAR(<FIELDLENGTH>)"
<NATIVETYPE>	This token is replaced with the type of database into which this field is loaded.
<NUMFIELDS>	This token is replaced with the number of fields in the table.
<PASSWORD>	This token is replaced with the database password from the current flowchart connection to the data source.
<TABLENAME>	This token is replaced with the database table name into which Unica Interact is loading data.
<USER>	This token is replaced with the database user from the current flowchart connection to the data source.

Default value

No default value defined.

LoaderControlFileTemplateForAppend**Description**

The `LoaderControlFileTemplateForAppend` property specifies the full path and filename to the control file template that has been previously configured in Unica Interact. When this parameter is set, Unica Interact dynamically builds a temporary control file based on the template that is specified here. The path and name of this temporary control file is available to the `<CONTROLFILE>` token that is available to the `LoaderCommandForAppend` property.

Before you use Unica Interact in the database loader utility mode, you must configure the control file template that is specified by this parameter. The

control file template supports the following tokens, which are dynamically replaced when the temporary control file is created by Unica Interact.

See your database loader utility documentation for the correct syntax required for your control file. Tokens available to your control file template are the same as those for the `LoaderControlFileTemplate` property.

This parameter is undefined by default.

Default value

No default value defined.

LoaderDelimiterForAppend

Description

The `LoaderDelimiterForAppend` property specifies whether the temporary Unica Interact data file is a fixed-width or delimited flat file, and, if it is delimited, the character or set of characters used as delimiters.

If the value is undefined, Unica Interact creates the temporary data file as a fixed width flat file.

If you specify a value, it is used when the loader is invoked to populate a table that is not known to be empty. Unica Interact creates the temporary data file as a delimited flat file, using the value of this property as the delimiter.

This property is undefined by default.

Default value

Valid Values

Characters, which you may enclose in double quotation marks, if desired.

LoaderDelimiterAtEndForAppend

Description

Some external load utilities require that the data file be delimited and that each line end with the delimiter. To accommodate this requirement, set the `LoaderDelimiterAtEndForAppend` value to `TRUE`, so that when the loader is

invoked to populate a table that is not known to be empty, Unica Interact uses delimiters at the end of each line.

Default value

FALSE

Valid Values

TRUE | FALSE

LoaderUseLocaleDP**Description**

The `LoaderUseLocaleDP` property specifies, when Unica Interact writes numeric values to files to be loaded by a database load utility, whether the locale-specific symbol is used for the decimal point.

Set this value to `FALSE` to specify that the period (.) is used as the decimal point.

Set this value to `TRUE` to specify that the decimal point symbol appropriate to the locale is used.

Default value

FALSE

Valid Values

TRUE | FALSE

Interact | general | testRunDataSource

These configuration properties define the data source settings for the test run tables for the Unica Interact design environment. You must define this data source for at least one of your runtime environments. These are the tables used when you perform a test run of your interactive flowchart.

jndiName**Description**

Use this `jndiName` property to identify the Java™ Naming and Directory Interface (JNDI) data source that is defined in the application server (Websphere or WebLogic) for the customer tables accessed by the design environment when executing interactive flowcharts test runs.

Default value

No default value defined.

type

Description

The database type for the customer tables accessed by the design environment when executing interactive flowcharts test runs.

Default value

SQLServer

Valid Values

SQLServer | DB2® | ORACLE | MARIADB| INFORMIX

aliasPrefix

Description

The `AliasPrefix` property specifies the way Unica Interact forms the alias name that Unica Interact creates automatically when using a dimension table and writing to a new table for the customer tables accessed by the design environment when executing interactive flowcharts test runs.

Note that each database has a maximum identifier length; check the documentation for the database you are using to be sure that the value you set does not exceed the maximum identifier length for your database.

Default value

A

connectionRetryPeriod

Description

The `ConnectionRetryPeriod` property specifies the amount of time in seconds Unica Interact automatically retries the database connection request on failure for the test run tables. Unica Interact automatically tries to reconnect to the database for this length of time before reporting a database error or failure. If the value is set to 0, Unica Interact will retry indefinitely; if the value is set to -1, no retry will be attempted.

Default value

-1

connectionRetryDelay

Description

The `ConnectionRetryDelay` property specifies the amount of time in seconds Unica Interact waits before it tries to reconnect to the database after a failure for the test run tables. If the value is set to -1, no retry will be attempted.

Default value

-1

schema

Description

The name of the schema containing the tables for interactive flowchart test runs. Unica Interact inserts the value of this property before all table names, for example, `UACI_IntChannel` becomes `schema.UACI_IntChannel`.

You do not have to define a schema. If you do not define a schema, Unica Interact assumes that the owner of the tables is the same as the schema. You should set this value to remove ambiguity.

Default value

No default value defined.

Interact | general | contactAndResponseHistoryDataSource

These configuration properties define the connection settings for the contact and response history data source required for the Unica Interact cross-session response tracking. These settings are not related to the contact and response history module.

jndiName

Description

Use this `jndiName` property to identify the Java™ Naming and Directory Interface (JNDI) data source that is defined in the application server (WebSphere® or WebLogic) for the contact and response history data source required for the Unica Interact cross-session response tracking.

Default value

type

Description

The database type for the data source used by the contact and response history data source required for the Unica Interact cross-session response tracking.

Default value

SQLServer

Valid Values

SQLServer | DB2® | ORACLE | MARIADB | INFORMIX

connectionRetryPeriod

Description

The `ConnectionRetryPeriod` property specifies the amount of time in seconds Unica Interact automatically retries the database connection request on failure for the Unica Interact cross-session response tracking. Unica Interact automatically tries to reconnect to the database for this length of

time before reporting a database error or failure. If the value is set to 0, Unica Interact will retry indefinitely; if the value is set to -1, no retry will be attempted.

Default value

-1

connectionRetryDelay**Description**

The `ConnectionRetryDelay` property specifies the amount of time in seconds Unica Interact waits before it tries to reconnect to the database after a failure for the Unica Interact cross-session response tracking. If the value is set to -1, no retry will be attempted.

Default value

-1

schema**Description**

The name of the schema containing the tables for the Unica Interact cross-session response tracking. Unica Interact inserts the value of this property before all table names, for example, `UACI_IntChannel` becomes `schema.UACI_IntChannel`.

You do not have to define a schema. If you do not define a schema, Unica Interact assumes that the owner of the tables is the same as the schema. You should set this value to remove ambiguity.

Default value

No default value defined.

Interact | general | idsByType

These configuration properties define settings for ID numbers used by the contact and response history module.

initialValue

Description

The initial ID value used when generating IDs using the UACI_IDsByType table.

Default value

1

Valid Values

Any value greater than 0.

retries

Description

The number of retries before generating an exception when generating IDs using the UACI_IDsByType table.

Default value

20

Valid Values

Any integer greater than 0.

Interact | flowchart

This section defines configuration settings for interactive flowcharts.

DT_DELIM_XXX formats cannot be used with Interactive Session flowcharts

defaultDateFormat

Description

The default date format used by Unica Interact to convert Date to String and String to Date.

Default value

MM/dd/yy

idleFlowchartThreadTimeoutInMinutes

Description

The number of minutes Unica Interact allows a thread dedicated to an interactive flowchart to be idle before releasing the thread.

Default value

5

idleProcessBoxThreadTimeoutInMinutes

Description

The number of minutes Unica Interact allows a thread dedicated to an interactive flowchart process to be idle before releasing the thread.

Default value

5

maxSizeOfFlowchartEngineInboundQueue

Description

The maximum number of flowchart run requests Unica Interact holds in queue. If this number of requests is reached, Unica Interact will stop taking requests.

Default value

1000

maxNumberOfFlowchartThreads

Description

The maximum number of threads dedicated to interactive flowchart requests.

Default value

25

maxNumberOfProcessBoxThreads

Description

The maximum number of threads dedicated to interactive flowchart processes.

Default value

50

maxNumberOfProcessBoxThreadsPerFlowchart

Description

The maximum number of threads dedicated to interactive flowchart processes per flowchart instance.

Default value

3

minNumberOfFlowchartThreads

Description

The minimum number of threads dedicated to interactive flowchart requests.

Default value

10

minNumberOfProcessBoxThreads

Description

The minimum number of threads dedicated to interactive flowchart processes.

Default value

20

sessionVarPrefix

Description

The prefix for session variables.

Default value

SessionVar

Interact | flowchart | ExternalCallouts

This section defines the class settings for custom external callouts you have written with the external callout API.

class

Description

The name of the Java™ class represented by this external callout.

This is the Java™ class that you can access with the Macro `EXTERNALCALLOUT`.

Default value

No default value defined.

classpath

Description

The classpath for the Java™ class represented by this external callout. The classpath must reference jar files on the runtime environment server. If you are using a server group and all runtime servers are using the same Unica Platform, every server must have a copy of the jar file in the same location. The classpath must consist of absolute locations of jar files, separated by the path delimiter of the operating system of the runtime environment server, for example a semi-colon (;) on Windows™ and a colon (:) on UNIX™ systems. Directories containing class files are not accepted. For example, on a Unix system: `/path1/file1.jar:/path2/file2.jar`.

This classpath must be less than 1024 characters. You can use the manifest file in a .jar file to specify other .jar files so only one .jar file has to appear in your class path

This is the Java™ class that you can access with the Macro `EXTERNALCALLOUT`.

Default value

No default value defined.

value**Description**

The value for any parameter required by the class for the external callout.

Default value

No default value defined.

Example

If the external callout requires host name of an external server, create a parameter category named `host` and define the `value` property as the server name.

Interact | monitoring

This set of configuration properties enables you to define JMX monitoring settings. You need to configure these properties only if you are using JMX monitoring. There are separate JMX monitoring properties to define for the contact and response history module in the configuration properties for Unica Interact design environment.

protocol**Description**

Define the protocol for the Unica Interact messaging service.

If you choose JMXMP you must include the following JAR files in your class path in order:

```
Interact/lib/InteractJMX.jar;Interact/lib/jmxremote_optional.jar
```

Default value

JMXMP

Valid Values

JMXMP | RMI

port

Description

The port number for the messaging service.

Default value

9998

enableSecurity

Description

A boolean which enables or disables JMXMP messaging service security for the Unica Interact runtime server. If set to `true`, you must supply a user name and password to access the Unica Interact runtime JMX service. This user credential is authenticated by the Unica Platform for the runtime server. Jconsole does not allow empty password login.

This property has no effect if the protocol is RMI. This property has no effect on JMX for Unica Campaign (the Unica Interact design time).

Default value

True

Valid Values

True | False

Interact | monitoring | activitySubscribers

This set of configuration properties enables the root node for the settings that are related to remote subscribers that can receive periodic update on basic performance data in the Unica Interact runtime environment.

heartbeatPeriodInSecs

Description

The interval in seconds when each runtime instance sends an update to subscribers.

Default value

60

Interact | monitoring | activitySubscribers | (target)

(target)

Description

The root node for the settings of a subscriber.

URL

Description

The URL of this subscriber. This endpoint must be able to accept JSON messages transported through HTTP.

continuousErrorsForAbort

Description

The number of continuous failed updates before the runtime instance stops sending more updates to this subscriber.

Default value

5

timeoutInMillis

Description

The time-out in milliseconds the send process times out during sending update to this subscriber.

Default value

1000

Valid Values

Enabled

Description

Whether this subscriber is enabled or disabled.

Default value

True

Valid Values

True Or False

type

Description

The type of this data store. When this option is selected, the parameter **className** must be added with the value being the fully qualified name of this implementation class. **classPath** needs to be added with the URI of the JAR file if it is not in the class path of the Interact run time.

Default value

InteractLog

Valid Values

InteractLog, RelationalDB, and Custom

jmxInclusionCycles

Description

The interval in the multiplier of **heartbeatPeriodInSecs** that detailed JMX statistics are sent to this subscriber.

Default value

5

Valid Values

Interact | profile

This set of configuration properties control several of the optional offer serving features, including offer suppression and score override.

enableScoreOverrideLookup

Description

If set to `True`, Unica Interact loads the score override data from the `scoreOverrideTable` when creating a session. If `False`, Unica Interact does not load the marketing score override data when creating a session.

If true, you must also configure the `Interact | profile | Audience Levels | (Audience Level) | scoreOverrideTable` property. You need to define the `scoreOverrideTable` property for the audience levels you require only. Leaving the `scoreOverrideTable` blank for an audience level disables the score override table for the audience level.

Default value

`False`

Valid Values

`True | False`

enableOfferSuppressionLookup

Description

If set to `True`, Unica Interact loads the offer suppression data from the `offerSuppressionTable` when creating a session. If `False`, Unica Interact does not load the offer suppression data when creating a session.

If true, you must also configure the `Interact | profile | Audience Levels | (Audience Level) | offerSuppressionTable` property. You need to define the `enableOfferSuppressionLookup` property for the audience levels you require only.

Default value

False

Valid Values

True | False

enableProfileLookup

Description

In a new installation of Unica Interact, this property is deprecated. In an upgraded installation of Unica Interact, this property is valid until the first deployment.

The load behavior for a table used in an interactive flowchart but not mapped in the interactive channel. If set to `True`, Unica Interact loads the profile data from the `profileTable` when creating a session.

If true, you must also configure the `Interact | profile | Audience Levels | (Audience Level) | profileTable` property.

The **Load this data in to memory when a visit session starts** setting in the interactive channel table mapping wizard overrides this configuration property.

Default value

False

Valid Values

True | False

defaultOfferUpdatePollPeriod

Description

The number of seconds the system waits before updating the default offers in the cache from the default offers table. If set to -1, the system doesn't update the default offers in the cache after the initial list is loaded into the cache when the runtime server starts.

Default value

-1

Interact | profile | Audience Levels | [AudienceLevelName]

This set of configuration properties enables you to define the table names required for additional Unica Interact features. You are only required to define the table name if you are using the associated feature.

New category name

Description

The name of your audience level.

scoreOverrideTable

Description

The name of the table containing the score override information for this audience level. This property is applicable if you have set `enableScoreOverrideLookup` to true. You have to define this property for the audience levels for which you want to enable a score override table. If you have no score override table for this audience level, you can leave this property undefined, even if `enableScoreOverrideLookup` is set to true.

Unica Interact looks for this table in the customer tables accessed by Unica Interact runtime servers, defined by the `prodUserDataSource` properties.

If you have defined the `schema` property for this data source, Unica Interact prepends this table name with the schema, for example, `schema.UACI_ScoreOverride`. If you enter a fully-qualified name, for example, `mySchema.UACI_ScoreOverride`, Unica Interact does not prepend the schema name.

Default value

UACI_ScoreOverride

offerSuppressionTable

Description

The name of the table containing the offer suppression information for this audience level. You have to define this property for the audience levels for which you want to enable an offer suppression table. If you have no offer suppression table for this audience level, you can leave this property undefined. If `enableOfferSuppressionLookup` is set to true, this property must be set to a valid table.

Unica Interact looks for this table in the customer tables accessed by runtime servers, defined by the `prodUserDataSource` properties.

Default value

UACI_BlackList

contactHistoryTable**Description**

The name of the staging table for the contact history data for this audience level.

This table is stored in the runtime environment tables (`systemTablesDataSource`).

If you have defined the `schema` property for this data source, Unica Interact prepends this table name with the schema, for example, `schema.UACI_CHStaging`. If you enter a fully-qualified name, for example, `mySchema.UACI_CHStaging`, Unica Interact does not prepend the schema name.

If contact history logging is disabled, this property does not need to be set.

Default value

UACI_CHStaging

chOfferAttribTable**Description**

The name of the contact history offer attributes table for this audience level.

This table is stored in the runtime environment tables
(`systemTablesDataSource`).

If you have defined the `schema` property for this data source, Unica Interact prepends this table name with the schema, for example, `schema.UACI_CHOfferAttrib`. If you enter a fully-qualified name, for example, `mySchema.UACI_CHOfferAttrib`, Unica Interact does not prepend the schema name.

If contact history logging is disabled, this property does not need to be set.

Default value

UACI_CHOfferAttrib

responseHistoryTable

Description

The name of the response history staging table for this audience level.

This table is stored in the runtime environment tables
(`systemTablesDataSource`).

If you have defined the `schema` property for this data source, Unica Interact prepends this table name with the schema, for example, `schema.UACI_RHStaging`. If you enter a fully-qualified name, for example, `mySchema.UACI_RHStaging`, Unica Interact does not prepend the schema name.

If response history logging is disabled, this property does not need to be set.

Default value

UACI_RHStaging

crossSessionResponseTable

Description

The name of the table for this audience level required for cross-session response tracking in the contact and response history tables accessible for the response tracking feature.

If you have defined the `schema` property for this data source, Unica Interact prepends this table name with the schema, for example, `schema.UACI_XSessResponse`. If you enter a fully-qualified name, for example, `mySchema.UACI_XSessResponse`, Unica Interact does not prepend the schema name.

If cross session response logging is disabled, this property does not need to be set.

Default value

`UACI_XSessResponse`

userEventLoggingTable**Description**

This is the name of the database table that is used for logging user-defined event activities. Users defined events on the Events tab of the Interactive Channel summary pages in the Unica Interact interface. The database table you specify here stores information such as the event ID, name, how many times this event occurred for this audience level since the last time the event activity cache was flushed, and so on.

If you have defined the `schema` property for this data source, Unica Interact prepends this table name with the schema, for example, `schema.UACI_UserEventActivity`. If you enter a fully-qualified name, for example, `mySchema.UACI_UserEventActivity`, Unica Interact does not prepend the schema name.

Default value

`UACI_UserEventActivity`

patternStateTable

Description

This is the name of the database table that is used for logging event pattern states, such as whether the pattern condition has been met or not, whether the pattern is expired or disabled, and so on.

If you have defined the `schema` property for this data source, Unica Interact prepends this table name with the schema, for example, `schema.UACI_EventPatternState`. If you enter a fully-qualified name, for example, `mySchema.UACI_EventPatternState`, Unica Interact does not prepend the schema name.

A `patternStateTable` is required for each audience level even if you do not use event patterns. The `patternStateTable` is based on the ddl of the included `UACI_EventPatternState`. The following is an example where the audience ID has two components; `ComponentNum` and `ComponentStr`.

```
CREATE TABLE UACI_EventPatternState_Composite
(
    UpdateTime bigint NOT NULL,
    State varbinary(4000),
    ComponentNum bigint NOT NULL,
    ComponentStr nvarchar(50) NOT NULL,
    CONSTRAINT PK_CustomerPatternState_Composite PRIMARY KEY
    (ComponentNum,ComponentStr,UpdateTime)
)
```

Default value

`UACI_EventPatternState`

Interact | profile | Audience Levels | [AudienceLevelName] | Offers by Raw SQL

This set of configuration properties enables you to define the table names required for additional Unica Interact features. You are only required to define the table name if you are using the associated feature.

enableOffersByRawSQL

Description

If set to `True`, Unica Interact enables the `offersBySQL` feature for this audience level that allows you to configure SQL code to be executed to create a desired set of candidate offers at runtime.. If `False`, Unica Interact does not use the `offersBySQL` feature.

If you set this property to true, you may also configure the `Interact | profile | Audience Levels | (Audience Level) | Offers by Raw SQL | SQL Template` property to define one or more SQL templates.

Default value

`False`

Valid Values

`True | False`

cacheSize

Description

Size of cache used to store results of the `OfferBySQL` queries. Note that using a cache may have negative impact if query results are unique for most sessions.

Default value

`-1 (off)`

Valid Values

`-1 | Value`

cacheLifeInMinutes

Description

If the cache is enabled, this indicates the number of minutes before the system will clear the cache to avoid staleness.

Default value

-1 (off)

Valid Values

-1 | Value

defaultSQLTemplate

Description

The name of the SQL template to use if one is not specified via the API calls.

Default value

None

Valid Values

SQL template name

name

Configuration category

Interact | profile | Audience Levels |
[AudienceLevelName] | Offers by Raw SQL | (SQL Templates)

Description

The name you want to assign to this SQL query template. Enter a descriptive name that will be meaningful when you use this SQL template in API calls. Note that if you use a name here that is identical to a name defined in the Interact List process box for an offerBySQL treatment, the SQL in the process box will be used rather than the SQL you enter here.

Default value

None

SQL

Configuration category

Interact | profile | Audience Levels |
[AudienceLevelName] | Offers by Raw SQL | (SQL Templates)

Description

Contains the SQL query to be called by this template. The SQL query may contain references to variable names that are part of the visitor's session data (profile). For example, `select * from MyOffers where category = ${preferredCategory}` would rely on the session containing a variable named `preferredCategory`.

You should configure the SQL to query the specific offer tables you created during design time for use by this feature. Note that stored procedures are not supported here.

Default value

None

Interact | profile | Audience Levels | [AudienceLevelName | Profile Data Services | [DataSource]

This set of configuration properties enables you to define the table names required for additional Unica Interact features. You are only required to define the table name if you are using the associated feature. The Profile Data Services category provides information about a built-in data source (called Database) that is created for all audience levels, and which is pre-configured with a priority of 100. However, you can choose to modify or disable it. This category also contains a template for additional external data sources. When you click the template called **External Data Services** you can complete the configuration settings described here.

New category name

Description

(Not available for the default Database entry.) The name of the data source you are defining. The name you enter here must be unique among the data sources for the same audience level.

Default value

None

Valid Values

Any text string is allowed.

enabled

Description

If set to `True`, this data source is enabled for the audience level to which it is assigned. If `False`, Unica Interact does not use this data source for this audience level.

Default value

`True`

Valid Values

`True` | `False`

className

Description

(Not available for the default Database entry.) The fully-qualified name of the data source class that implements `IInteractProfileDataService`.

Default value

None.

Valid Values

A string providing a fully-qualified class name.

classPath

Description

(Not available for the default Database entry.) An optional configuration setting providing the path to load this data source implementation class. If you omit it, the class path of the containing application server is used by default.

Default value

Not shown, but the class path of the containing application server is used by default if no value is provided here.

Valid Values

A string providing the class path.

priority

Description

The priority of this data source within this audience level. It has to be a unique value among all of the data sources for each audience level. (That is, if a priority is set to 100 for a data source, no other data source within the audience level may have a priority of 100.)

Default value

100 for the default Database, 200 for user-defined data source

Valid Values

Any non-negative integer is allowed.

Interact | offerserving

These configuration properties define the generic learning configuration properties. If you are using built-in learning, to tune your learning implementation, use the configuration properties for the design environment.

offerTieBreakMethod

Description

The `offerTieBreakMethod` property defines the behavior of offer serving when two offers have equivalent (tied) scores. If you set this property to its default value of `Random`, Unica Interact presents a random choice from among the offers that have equivalent scores. If you set this configuration to `Newer Offer`, Unica Interact serves up the newer offer (based on having a higher offer ID) ahead of the older offer (lower offer ID) in the case where the scores among the offers are the same.



Note:

Unica Interact has an optional feature that allows the administrator to configure the system to return the offers in random order independent of the score, by setting the `percentRandomSelection` option (`Campaign | partitions | [partition_number] | Interact | learning | percentRandomSelection`). The `offerTieBreakMethod` property described here is used only when `percentRandomSelection` is set to zero (disabled).

Default value

Random

Valid Values

Random | Newer Offer

optimizationType

Description

The `optimizationType` property defines whether Unica Interact uses a learning engine to assist with offer assignments. If set to `NoLearning`, Unica Interact does not use learning. If set to `BuiltInLearning`, Unica Interact uses the Bayesian learning engine built with Unica Interact. If set to `ExternalLearning`, Unica Interact uses a learning engine you provide. If you select `ExternalLearning`, you must define the `externalLearningClass` and `externalLearningClassPath` properties.

Default value

NoLearning

Valid Values

NoLearning | BuiltInLearning | ExternalLearning

segmentationMaxWaitTimeInMS**Description**

The maximum number of milliseconds that the runtime server waits for an interactive flowchart to complete before getting offers.

Default value

5000

treatmentCodePrefix**Description**

The prefix prepended to treatment codes.

Default value

No default value defined.

effectiveDateBehavior**Description**

Determines whether Unica Interact should use an offer's effective date in filtering out offers that are presented to a visitor. Values include:

- -1 tells Unica Interact to ignore the effective date on the offer.
 - 0 tells Unica Interact to use the effective date to filter the offer, so that if the offer effective date is earlier than or equal to the current date, the offer effective date, the offer is served to visitors.
- If there is an **effectiveDateGracePeriod** value set, the grace period is also applied to determine whether to serve the offer.

- Any positive integer tells Unica Interact to use the current date plus the value of this property to determine whether to serve the offer to visitors, so that if the offer effective date is earlier than the current date plus the value of this property, the offer is served to visitors.

If there is an **effectiveDateGracePeriod** value set, the grace period is also applied to determine whether to serve the offer.

Default value

-1

effectiveDateGracePeriodOfferAttr**Description**

Specifies the name of the custom attribute in an offer definition that indicates the effective date grace period. For example, you might configure this property with a value of `AltGracePeriod`. You would then define offers with a custom attribute called `AltGracePeriod` that is used to specify the number of days to use as a grace period with the **effectiveDateBehavior** property.

Suppose you create a new offer template with an effective date of 10 days from the current date, and include a custom attribute called `AltGracePeriod`. When you create an offer using the template, if you set the value of `AltGracePeriod` to 14 days, the offer would be served to visitors, because the current date is within the grace period of the offer effective date.

Default value

Blank

alwaysLogLearningAttributes**Description**

Indicates whether Unica Interact should write information about visitor attributes used by the learning module to the log files. Note that settings this value to true may affect learning performance and log file sizes.

Default value**False**

Consider the following points:

- If Learning is enabled, for version 2, using SampleMethod1, for version 1, using SampleMethod1
- During the interact configuration process, system verifies if the settings are matching.
- During the interact offer treatment optimizer process in learning version2, the offer learning based on SampleMethod1 and SampleMethod2 setting are handles. The offer RWA based on SampleMethod1 and SampleMethod2 setting is also calculated.

Interact | offerserving | Built-in Learning Config

These configuration properties define the database write settings for built-in learning. To tune your learning implementation, use the configuration properties for the design environment.

version**Description**

You can select 1 or 2. Version 1 is the basic configuration version that does not use parameters to set thread and record limits. Version 2 is the enhanced configuration version that lets you set thread and record parameter to improve performance. These parameters perform aggregation and deletion when these parameter limits are reached.

Default value

1

insertRawStatsIntervallInMinutes**Description**

The number of minutes the Unica Interact learning module waits before inserting more rows into the learning staging tables. You may need to modify this time based on the amount of data the learning module is processing in your environment.

Default value

5

Valid Values

A positive integer

aggregateStatsIntervallInMinutes

Description

The number of minutes the Unica Interact learning module waits between aggregating data in the learning stats tables. You may need to modify this time based on the amount of data the learning module is processing in your environment.

Default value

15

Valid Values

An integer greater than zero.

autoAdjustPercentage

Description

The value that determines the percentage of data the run of aggregation tries to process based on the metrics of the previous run. By default, this value is set to zero, which means the aggregator processes all staging records, and this auto adjustment functionality is disabled.

Default value

0

Valid Values

A number between 0 and 100.

excludeAbnormalAttribute

Description

The setting that determines whether to mark those attributes as invalid. If set to `IncludeAttribute`, abnormal attributes are included not marked as invalid. If set to `ExcludeAttribute`, abnormal attributes are excluded and marked as invalid.

Default value

`IncludeAttribute`

Valid Values

`IncludeAttribute` | `ExcludeAttribute`

saveOriginalValues

Description

You can set the values as "All Values", "Binned Values", or "None". This will control what values will be logged in table `UACI_LearningAttributeHist`.

If "All Values" is selected then all learning attributes will be logged in the table. If this parameter is set to "Binned Values" then only those attributes will be logged in the table for which bins are created under "Interact-> Global Learning".

If set to "None" no values will be logged in `UACI_LearningAttributeHist`.

By default this is set to "None".

Default value

`None`

Valid Values

`All Values` | `Binned Values` | `None`

Interact | offerserving | Built-in Learning Config | Parameter Data | [parameterName]

These configuration properties define any parameters for your external learning module.

numberOfThreads

Description

The maximum number of threads the learning aggregator uses to process the data. A valid value is a positive integer, and should not be more than the maximum number of connections that are configured in the learning data source. This parameter is used only by aggregator version 2.

Default value

10

maxLogTimeSpanInMin

Description

If aggregator version 1 is selected, you can process the staging records in iterations to avoid overly large database batches. In this case, those staging records are processed by chunks; iteration by iteration in a single aggregation cycle. The value of this parameter specifies the maximum time span of staging records the aggregator tries to process in each iteration. This time span is based on LogTime field that is associated to each staging record, and only the records whose LogTime falls into the earliest time window is processed. A valid value is an integer that is not negative. If the value is 0, there is no limit, which means all the staging records are processed in a single iteration.

Default value

0

maxRecords

Description

If aggregator version 2 is selected, you can process the staging records in iterations to avoid overly large database batches. In this case, those staging records are processed in chunks; iteration by iteration in a single aggregation cycle. The value of this parameter specifies the maximum number of staging records the aggregator tries to process in each iteration. A valid value is an integer that is not negative. If the value is 0, there is no limit, which means all the staging records are processed in a single iteration.

Default value

0

value**Description**

The value for any parameter that is required by the class for a built-in learning module.

Default value

No default value defined.

Interact | offerserving | External Learning Config

These configuration properties define the class settings for an external learning module you wrote using the learning API.

class**Description**

If `optimizationType` is set to `ExternalLearning`, set `externalLearningClass` to the class name for the external learning engine.

Default value

No default value defined.

Availability

This property is applicable only if `optimizationType` is set to `ExternalLearning`.

classPath

Description

If `optimizationType` is set to `ExternalLearning`, set `externalLearningClass` to the classpath for the external learning engine.

The classpath must reference jar files on the runtime environment server. If you are using a server group and all runtime servers are using the same Unica Platform, every server must have a copy of the jar file in the same location.

The classpath must consist of absolute locations of jar files, separated by the path delimiter of the operating system of the runtime environment server, for example a semi-colon (;) on Windows™ and a colon (:) on UNIX™ systems. Directories containing class files are not accepted. For example, on a Unix system: `/path1/file1.jar:/path2/file2.jar`.

This classpath must be less than 1024 characters. You can use the manifest file in a .jar file to specify other .jar files so only one .jar file has to appear in your class path

Default value

No default value defined.

Availability

This property is applicable only if `optimizationType` is set to `ExternalLearning`.

Interact | offerserving | External Learning Config | Parameter Data | [parameterName]

These configuration properties define any parameters for your external learning module.

value

Description

The value for any parameter required by the class for an external learning module.

Default value

No default value defined.

Example

If the external learning module requires a path to an algorithm solver application, you would create a parameter category called `solverPath` and define the `value` property as the path to the application.

Interact | offerserving | Constraints

These configuration properties define the constraints placed upon the offer serving process.

maxOfferAllocationInMemoryPerInstance

Description

The size of a block of offers. Unica Interact keeps a pool of offers in memory so that the system does not have to query to database each time an offer is returned. Every time an offer is returned, the pool is adjusted. When the pool is exhausted, Unica Interact gets another block of offers to fill the pool.

Default value

1000

Valid Values

An integer greater than 0.

maxDistributionPerIntervalPerInstanceFactor

Description

The constraint percentage for a given offer allocation for a runtime server to support the distribution across runtime servers.

Default value

100

Valid Values

An integer between 0 and 100.

constraintCleanupIntervallnDays

Description

How often the disabled counts from the UACL_OfferCount table are cleaned up. A value less than 1 disables this feature.

Default value

7

Valid Values

An integer greater than 0.

Interact | services

The configuration properties in this category define settings for all the services which manage collecting contact and response history data and statistics for reporting and writing to the runtime environment system tables.

externalLoaderStagingDirectory

Description

This property defines the location of the staging directory for a database load utility.

Default value

No default value defined.

Valid Values

A path relative to the Unica Interact installation directory or an absolute path to a staging directory.

If you enable a database load utility, you must set the `cacheType` property in the `contactHist` and `responstHist` categories to `External Loader File`.

Interact | services | contactHist

The configuration properties in this category define the settings for the service that collects data for the contact history staging tables.

enableLog

Description

If `true`, enables the service which collects data for recording the contact history data. If `false`, no data is collected.

Default value

True

Valid Values

True | False

cacheType

Description

Defines whether the data collected for contact history is kept in memory (Memory Cache) or in a file (External Loader file). You can use `External Loader File` only if you have configured Unica Interact to use a database loader utility.

If you select `Memory Cache`, use the `cache` category settings. If you select `External Loader File`, use the `fileCache` category settings.

Default value

Memory Cache

Valid Values

Memory Cache | External Loader File

Interact | services | contactHist | cache

The configuration properties in this category define the cache settings for the service that collects data for the contact history staging table. **Note:** When `contactHist` or

responseHist is configured to use memoryCache, you can optionally create a data source systemTablesDataSource and configure the settings under Affinium|interact|general|systemTablesDataSource|loaderProperties. When this is done, the contact/response history staging records will be persisted into files in directory as set by Affinium|interact|services|externalLoaderStagingDirectory if the persistence into database fails. Otherwise, an INFO entries will be logged at initialization saying failover is not enabled.

threshold

Description

The number of records accumulated before the flushCacheToDB service writes the collected contact history data to the database.

Default value

100

insertPeriodInSecs

Description

The number of seconds between forced writes to the database.

Default value

3600

Interact | services | contactHist | fileCache

The configuration properties in this category define the cache settings for the service that collects contact history data if you are using a database loader utility. **Prerequisite:** For Configuration Affinium|interact|services|externalLoaderStagingDirectory set loaderStagingData.

threshold

Description

The number of records accumulated before the flushCacheToDB service writes the collected contact history data to the database.

Default value

100

insertPeriodInSecs**Description**

The number of seconds between forced writes to the database.

Default value

3600

Interact | services | defaultedStats

The configuration properties in this category define the settings for the service that collects the statistics regarding the number of times the default string for the interaction point was used.

enableLog**Description**

If `true`, enables the service that collects the statistics regarding the number of times the default string for the interaction point was used to the `UACI_DefaultedStat` table. If `false`, no default string statistics are collected.

If you are not using IBM reporting, you can set this property to `false` since the data collection is not required.

Default value

True

Valid Values

True | False

Interact | services | defaultedStats | cache

The configuration properties in this category define the cache settings for the service that collects the statistics regarding the number of times the default string for the interaction point was used.

threshold

Description

The number of records accumulated before the flushCacheToDB service writes the collected default string statistics to the database.

Default value

100

insertPeriodInSecs

Description

The number of seconds between forced writes to the database.

Default value

3600

Interact | services | eligOpsStats

The configuration properties in this category define the settings for the service that writes the statistics for eligible offers.

enableLog

Description

If `true`, enables the service that collects the statistics for eligible offers. If `false`, no eligible offer statistics are collected.

If you are not using IBM reporting, you can set this property to `false` since the data collection is not required.

Default value

True

Valid Values

True | False

Interact | services | eligOpsStats | cache

The configuration properties in this category define the cache settings for the service that collects the eligible offer statistics.

threshold

Description

The number of records accumulated before the flushCacheToDB service writes the collected eligible offer statistics to the database.

Default value

100

insertPeriodInSecs

Description

The number of seconds between forced writes to the database.

Default value

3600

Interact | services | eventActivity

The configuration properties in this category define the settings for the service that collects the event activity statistics.

enableLog

Description

If `true`, enables the service that collects the event activity statistics. If `false`, no event statistics are collected.

If you are not using IBM reporting, you can set this property to `false` since the data collection is not required.

Default value

True

Valid Values

True | False

Interact | services | eventActivity | cache

The configuration properties in this category define the cache settings for the service that collects the event activity statistics.

threshold

Description

The number of records accumulated before the `flushCacheToDB` service writes the collected event activity statistics to the database.

Default value

100

insertPeriodInSecs

Description

The number of seconds between forced writes to the database.

Default value

3600

Interact | services | eventPattern

The configuration properties in the `eventPattern` category define the settings for the service that collects the event pattern activity statistics.

persistUnknownUserStates

Description

Determines whether the event pattern states for an unknown audience ID (visitor) is retained in the database. By default, when a session ends, the statuses of all the updated event patterns associated with the visitor's audience ID are stored in the database, provided that the audience ID is known (that is, the visitor's profile can be found in the profile data source).

The `persistUnknownUserStates` property determines what happens if the audience ID is not known. By default, this property is set to `False`, and for unknown audience IDs, the event pattern states are discarded at the end of the session.

If you set this property to `True`, the event pattern states of unknown users (whose profile cannot be found in the configured profile data service) will be persisted.

Default value

False

Valid Values

True | False

mergeUnknowUserInSessionStates

Description

Determines how the event pattern states for unknown audience IDs (visitors) are retained. If the audience ID switches in the middle of a session, Unica Interact tries to load the saved event pattern states for the new audience ID from the database table. When the audience ID was unknown previously, and you set the `mergeUnknowUserInSessionStates` property to `True`, the user event activities belonging to the previous audience ID in the same session will be merged into the new audience ID.

Default value

False

Valid Values

True | False

enableUserEventLog

Description

Determines whether user event activities are logged in the database.

Default value

False

Valid Values

True | False

Interact | services | eventPattern | userEventCache

The configuration properties in the `userEventCache` category define the settings that determine when event activity is moved from the cache to persist in the database.

threshold

Description

Determines the maximum number of event pattern states that can be stored in the event pattern state cache. When the limit is reached, the least-recently used states are flushed from the cache.

Default value

100

Valid Values

The desired number of event pattern states to retain in the cache.

insertPeriodInSecs

Description

Determines the maximum length of time in seconds that user event activities are queued in memory. When the time limit specified by this property is reached, those activities are persisted into the database.

Default value

3600 (60 minutes)

Valid Values

The desired number of seconds.

Interact | services | eventPattern | advancedPatterns

The configuration properties in this category control whether integration with Unica Interact Advanced Patterns is enabled, and they define the timeout intervals for connections with Unica Interact Advanced Patterns.

enableAdvancedPatterns

Description

If `true`, enables integration with Unica Interact Advanced Patterns. If `false`, integration is not enabled. If integration was previously enabled, Unica Interact uses the most recent pattern states received from Unica Interact Advanced Patterns.

Default value

True

Valid Values

True | False

connectionTimeoutInMilliseconds

Description

Maximum time it can take to make an HTTP connection from the Unica Interact real time environment to Unica Interact Advanced Patterns. If the request times out, Unica Interact uses the last saved data from patterns.

Default value

30

readTimeoutInMilliseconds

Description

After an HTTP connection is established between the Unica Interact real time environment and Unica Interact Advanced Patterns, and a request is sent to the Unica Interact Advanced Patterns to get the status of an event pattern, the maximum time it can take to receive data. If the request times out, Unica Interact uses the last saved data from patterns.

Default value

100

connectionPoolSize

Description

Size of the HTTP connection pool for communication between the Unica Interact real time environment and Unica Interact Advanced Patterns.

Default value

10

Interact | services | eventPattern | advancedPatterns | autoReconnect

The configuration properties in this category specify parameters for the automatic reconnection feature in the integration with Unica Interact Advanced Patterns.

enable

Description

Determines whether the system to reconnects automatically if connection problems occur between the Unica Interact real time environment and Unica Interact Advanced Patterns. The default value of **True** enables this feature.

Default value

True

Valid Values

True | False

durationInMinutes**Description**

This property specifies the time interval, in minutes, during which the system to evaluates repeated connection problems occurring between the Unica Interact real time environment and Unica Interact Advanced Patterns.

Default value

10

numberOfFailuresBeforeDisconnect**Description**

This property specifies the number of connection failures allowed during the specified time period before the system automatically disconnects from Unica Interact Advanced Patterns.

Default value

3

consecutiveFailuresBeforeDisconnect**Description**

Determines whether the automatic reconnection feature evaluates only consecutive failures of the connection between the Unica Interact real time environment with Unica Interact Advanced Patterns. If you set this value to **False**, all failures within the specified time interval are evaluated.

Default value

True

sleepBeforeReconnectDurationInMinutes

Description

The system waits the number of minutes specified in this property before reconnecting after the system disconnects due to repeated failures as specified in the other properties in this category.

Default value

5

sendNotificationAfterDisconnect

Description

This property determines whether the system sends an email notification when a connection failure occurs. The notification message includes the Unica Interact real time instance name for which failure occurred and the amount of time before reconnection occurs, as specified in the **sleepBeforeReconnectDurationInMinutes** property. The default value of **True** means that notifications are sent.

Default value

True

Interact | services | customLogger

The configuration properties in this category define the settings for the service that collects custom data to write to a table (an event which uses the `UACICustomLoggerTableName` event parameter).

enableLog

Description

If `true`, enables the custom log to table feature. If `false`, the `UACICustomLoggerTableName` event parameter has no effect.

Default value

True

Valid Values

True | False

Interact | services | customLogger | cache

The configuration properties in this category define the cache settings for the service that collects custom data to a table (an event which uses the `UACICustomLoggerTableName` event parameter).

threshold

Description

The number of records accumulated before the `flushCacheToDB` service writes the collected custom data to the database.

Default value

100

insertPeriodInSecs

Description

The number of seconds between forced writes to the database.

Default value

3600

Interact | services | responseHist

The configuration properties in this category define the settings for the service that writes to the response history staging tables.

enableLog

Description

If `true`, enables the service that writes to the response history staging tables.

If `false`, no data is written to the response history staging tables.

The response history staging table is defined by the `responseHistoryTable` property for the audience level. The default is `UACI_RHStaging`.

Default value

True

Valid Values

True | False

cacheType

Description

Defines whether the cache is kept in memory or in a file. You can use `External Loader File` only if you configured Unica Interact to use a database loader utility.

If you select `Memory Cache`, use the `cache` category settings. If you select `External Loader File`, use the `fileCache` category settings.

Default value

Memory Cache

Valid Values

Memory Cache | External Loader File

actionOnOrphan

Description

This setting determines what to do with response events that do not have corresponding contact events posted yet. The setting applies to in-session response events. If set to `NoAction`, the response event is processed as if the corresponding contact event was posted. If set to `Warning`, the response event is processed as if the corresponding contact event was posted, but a warning message is written into `interact.log`. If set to `Skip`, the response even

is not processed, and an error message is written into `interact.log`. The setting that you choose here is effective regardless if response history logging is enabled.

Default value

NoAction

Valid Values

NoAction | Warning | Skip

suppressionActionOnResponse**Description**

This setting handles the suppression of an offer responded by a response event in a session. It has the following four options.

- NoSuppression. Do not suppress this offer.
- SuppressionTillAudienceChange. This offer is suppressed until the active audience ID in this session changes.
- SuppressionForAudience. This offer is suppressed as long as the active audience ID in this session is same as the one when this offer was returned.
- SuppressionInSession. This offer is suppressed throughout this session even if the audience ID changes.

The following is an example with an API sequence.

1. startSession (audience 1)
2. getOffers -> return offer A
3. postEvent (contact of offer A)
4. postEvent (accept or reject offer A)
5. getOffers
6. setAudience (audience 2)
7. getOffers

8. setAudience (audience 1)
9. getOffers

Default value

SuppressionTillAudienceChange

Valid Values

NoSuppression | SuppressionTillAudienceChange| SuppressionForAudience|
SuppressionInSession

The following table shows whether offer A is suppressed in Steps 5, 7, and 9.

Setting	Step 5	Step 7	Step 9
NoSuppression	N	N	N
SuppressionTillAudienceChange	Y	N	N
SuppressionForAudience	Y	N	Y
SuppressionInSession	Y	Y	Y

Interact | services | response Hist | responseTypeCodes

The configuration properties in this category define the settings for the response history service.

New category name**Description**

The name of your response type code.

code**Description**

The custom code for your response type.

Default value

The custom code added in the UA_UsrResponseType table.

action

Description

The action corresponding to the custom response type code.

The action defined for the event this is posted overrides the action defined here. Therefore, if a logAccept event is posted without responseTypeCode, this event is treated as an acceptance event. If a logAccept event is posted with a responseTypeCode that exists in this configuration, the configured action is used to determine if it is an acceptance event. If a logAccept event is posted with a responseTypeCode that does not exist in this configuration, this event is not treated as an acceptance event. When an event is treated as an acceptance event, the learning statistics are updated accordingly if learning is enabled. Offer expression rules are evaluated if there is one based on the acceptance of this offer.

Default value

None

Valid Values

LogAccept | LogReject | None

Interact | services | responseHist | cache

The configuration properties in this category define the cache settings for the service that collects the response history data. **Note:** When contactHist or responseHist is configured to use memoryCache, you can optionally create a data source systemTablesDataSource and configure the settings under Affinium|interact|general|systemTablesDataSource|loaderProperties. When this is done, the contact/response history staging records will be persisted into files in directory as set by Affinium|interact|services|

externalLoaderStagingDirectory if the persistence into database fails. Otherwise, an INFO entries will be logged at initialization saying failover is not enabled.

threshold

Description

The number of records accumulated before the flushCacheToDB service writes the collected response history data to the database.

Default value

100

insertPeriodInSecs

Description

The number of seconds between forced writes to the database.

Default value

3600

Interact | services | responseHist | fileCache

The configuration properties in this category define the cache settings for the service that collects the response history data if you are using a database loader utility.

threshold

Description

The number of records accumulated before Unica Interact writes them to the database.

`responseHist` - The table defined by the `responseHistoryTable` property for the audience level. The default is `UACI_RHStaging`.

Default value

100

insertPeriodInSecs

Description

The number of seconds between forced writes to the database.

Default value

3600

Interact | services | crossSessionResponse

The configuration properties in this category define general settings for the crossSessionResponse service and the xsession process. You only need to configure these settings if you are using Unica Interact cross-session response tracking.

enableLog

Description

If `true`, enables the crossSessionResponse service and Unica Interact writes data to the cross-session response tracking staging tables. If `false`, disables the crossSessionResponse service.

Default value

False

xsessionProcessIntervalInSecs

Description

The number of seconds between runs of the xsession process. This process moves data from the cross-session response tracking staging tables to the response history staging table and the built-in learning module.

Default value

180

Valid Values

An integer greater than zero

purgeOrphanResponseThresholdInMinutes

Description

The number of minutes the `crossSessionResponse` service waits before marking any responses that do not match contacts in the contact and response history tables.

If a response has no match in the contact and response history tables, after `purgeOrphanResponseThresholdInMinutes` minutes, Unica Interact marks the response with a value of -1 in the `Mark` column of the `xSessResponse` staging table. You can then manually match or delete these responses.

Default value

180

xsessionResponseBatchsize

Description

The number of cross-session response records to process at once. Rather than processing all new or retry records at once, system loops through the `xsessionResponseBatchSize` records at a time. This is a performance change, since processing a large number of records at once can lead to slowness

Default value

10000

Valid values

Any integer greater than zero.

generateOnlyOneResponseRecord

Description

When a cross session response is processed, Interact must link it to the available contact history records. Sometimes, multiple matching contact history records are found based on the given criteria (treatment code or

offer ID). In this case, Interact uses the "generateOnlyOneResponseRecord" configuration setting to decide the outcome.

Values

- True: Only one response history record is generated using the most recent contact history record.
- False: One response history record is generated for each matching contact history record.

Default Value

False

Interact | services | crossSessionResponse | cache

The configuration properties in this category define the cache settings for the service that collects cross-session response data.

threshold

Description

The number of records accumulated before the flushCacheToDB service writes the collected cross-session response data to the database.

Default value

100

insertPeriodInSecs

Description

The number of seconds between forced writes to the `XSessionResponse` table.

Default value

3600

Interact | services | crossSessionResponse | OverridePerAudience | [AudienceLevel] | TrackingCodes | byTreatmentCode

The properties in this section define how cross-session response tracking matches treatment codes to contact and response history.

SQL

Description

This property defines whether Unica Interact uses the System Generated SQL or custom SQL defined in the `OverrideSQL` property.

Default value

Use System Generated SQL

Valid Values

Use System Generated SQL | Override SQL

OverrideSQL

Description

If you do not use the default SQL command to match the treatment code to the contact and response history, enter the SQL or stored procedure here.

This value is ignored if `SQL` is set to `Use System Generated SQL`.

Default value

useStoredProcedure

Description

If set to true, the `OverrideSQL` must contain a reference to a stored procedure which matches the treatment code to the contact and response history.

If set to false, the `OverrideSQL`, if used, must be an SQL query.

Default value

false

Valid Values

true | false

Type**Description**

The associated TrackingCodeType defined in the `UACI_TrackingType` table in the runtime environment tables. Unless you revise the `UACI_TrackingType` table, the `Type` must be 1.

Default value

1

Valid Values

An integer defined in the `UACI_TrackingType` table.

Interact | services | crossSessionResponse | OverridePerAudience | [AudienceLevel] | TrackingCodes | byOfferCode

The properties in this section define how cross-session response tracking matches offer codes to contact and response history.

SQL**Description**

This property defines whether Unica Interact uses the System Generated SQL or custom SQL defined in the `OverrideSQL` property.

Default value

Use System Generated SQL

Valid Values

Use System Generated SQL | Override SQL

OverrideSQL**Description**

If you do not use the default SQL command to match the offer code to the contact and response history, enter the SQL or stored procedure here.

This value is ignored if `SQL` is set to `Use System Generated SQL`.

Default value

useStoredProcedure

Description

If set to true, the `OverrideSQL` must contain a reference to a stored procedure which matches the offer code to the contact and response history.

If set to false, the `OverrideSQL`, if used, must be an SQL query.

Default value

false

Valid Values

true | false

Type

Description

The associated `TrackingCodeType` defined in the `UACI_TrackingType` table in the runtime environment tables. Unless you revise the `UACI_TrackingType` table, the `Type` must be 2.

Default value

2

Valid Values

An integer defined in the `UACI_TrackingType` table.

Interact | services | crossSessionResponse | OverridePerAudience | [AudienceLevel] | TrackingCodes | byAlternateCode

The properties in this section define how cross-session response tracking matches a user-defined alternate code to contact and response history.

Name

Description

This property defines the name for the alternate code. This must match the Name value in the `UACI_TrackingType` table in the runtime environment tables.

Default value

OverrideSQL

Description

The SQL command or stored procedure to match the alternate code to the contact and response history by offer code or treatment code.

Default value

useStoredProcedure

Description

If set to true, the `OverrideSQL` must contain a reference to a stored procedure which matches the alternate code to the contact and response history.

If set to false, the `OverrideSQL`, if used, must be an SQL query.

Default value

false

Valid Values

true | false

Type

Description

The associated TrackingCodeType defined in the `UACI_TrackingType` table in the runtime environment tables.

Default value

3

Valid Values

An integer defined in the `UACI_TrackingType` table.

Interact | services | threadManagement | contactAndResponseHist

The configuration properties in this category define thread management settings for the services which collect data for the contact and response history staging tables.

corePoolSize

Description

The number of threads to keep in the pool, even if they are idle, for collecting the contact and response history data.

Default value

5

maxPoolSize

Description

The maximum number of threads to keep in the pool for collecting the contact and response history data.

Default value

5

keepAliveTimeSecs

Description

When the number of threads is greater than the core, this is the maximum time that excess idle threads will wait for new tasks before terminating for collecting the contact and response history data.

Default value

5

queueCapacity**Description**

The size of the queue used by the thread pool for collecting the contact and response history data.

Default value

1000

termWaitSecs**Description**

At the shutdown of the runtime server, this is the number of seconds to wait for service threads to complete collecting the contact and response history data.

Default value

5

Interact | services | threadManagement | allOtherServices

The configuration properties in this category define the thread management settings for the services which collect the offer eligibility statistics, event activity statistics, default string usage statistics, and the custom log to table data.

corePoolSize**Description**

The number of threads to keep in the pool, even if they are idle, for the services which collect the offer eligibility statistics, event activity statistics, default string usage statistics, and the custom log to table data.

Default value

5

maxPoolSize

Description

The maximum number of threads to keep in the pool for the services which collect the offer eligibility statistics, event activity statistics, default string usage statistics, and the custom log to table data.

Default value

5

keepAliveTimeSecs

Description

When the number of threads is greater than the core, this is the maximum time that excess idle threads wait for new tasks before terminating for the services which collect the offer eligibility statistics, event activity statistics, default string usage statistics, and the custom log to table data.

Default value

5

queueCapacity

Description

The size of the queue used by the thread pool for the services which collect the offer eligibility statistics, event activity statistics, default string usage statistics, and the custom log to table data.

Default value

1000

termWaitSecs

Description

At the shutdown of the runtime server, this is the number of seconds to wait for service threads to complete for the services which collect the offer eligibility statistics, event activity statistics, default string usage statistics, and the custom log to table data.

Default value

5

Interact | services | threadManagement | flushCacheToDB

The configuration properties in this category define the thread management settings for the threads that write collected data in cache to the runtime environment database tables.

corePoolSize

Description

The number of threads to keep in the pool for scheduled threads that write cached data to the data store.

Default value

5

maxPoolSize

Description

The maximum number of threads to keep in the pool for scheduled threads that that write cached data to the data store.

Default value

5

keepAliveTimeSecs

Description

When the number of threads is greater than the core, this is the maximum time that excess idle threads wait for new tasks before terminating for scheduled threads that that write cached data to the data store.

Default value

5

queueCapacity

Description

The size of the queue used by the thread pool for scheduled threads that that write cached data to the data store.

Default value

1000

termWaitSecs

Description

At the shutdown of the runtime server, this is the number of seconds to wait for service threads to complete for scheduled threads that that write cached data to the data store.

Default value

5

Interact | services | threadManagement | eventHandling

The configuration properties in this category define the thread management settings for the services which collect data for event handling.

corePoolSize

Description

The number of threads to keep in the pool, even if they are idle, for collecting event handling data.

Default value

1

maxPoolSize**Description**

The maximum number of threads to keep in the pool for the services which collect the event handling data.

Default value

5

keepAliveTimeSecs**Description**

When the number of threads is greater than the core, this is the maximum time that excess idle threads wait for new tasks before terminating for collecting the event handling data.

Default value

5

queueCapacity**Description**

The size of the queue used by the thread pool for collecting event handling data.

Default value

1000

termWaitSecs**Description**

At the shutdown of the runtime server, this is the number of seconds to wait for service threads to complete for the services which collect the event handling data.

Default value

5

Interact | services | configurationMonitor

The configuration properties in this category allow you to enable or disable integration with Unica Interact Advanced Patterns without having to restart Unica Interact real time, and they define the interval for polling the property value that enables the integration.

enable**Description**

If `true`, enables the service that refreshes the value of the **Interact | services | eventPattern | advancedPatterns enableAdvancedPatterns** property.

If `false`, you must restart Unica Interact real time when you change the value of the **Interact | services | eventPattern | advancedPatterns enableAdvancedPatterns** property.

Default value

False

Valid Values

True | False

refreshIntervalInMinutes**Description**

Defines the time interval for polling the value of the **Interact | services | eventPattern | advancedPatterns enableAdvancedPatterns** property.

Default value

5

Interact | cacheManagement

This set of configuration properties defines settings for selecting and configuring each of the supported cache managers that you can use to improve the performance of Unica Interact, such as EHCACHE or Ignite, which is built-in to your Unica Interact installation.

Use the **Unica Interact | cacheManagement | Cache Managers** configuration properties to configure the cache manager you want to use. Use the **Unica Interact | cacheManagement | caches** configuration properties to specify which cache manager Unica Interact should use to improve performance.

Interact | cacheManagement | Cache Managers

The Cache Managers category specifies the parameters for the cache management solutions you plan to use with Unica Interact.

Interact | cacheManagement | Cache Managers | EHCACHE

The EHCACHE category specifies the parameters for the EHCACHE cache management solution, so that you can customize it to improve the performance of Unica Interact.

Interact | caches

Use this set of configuration properties to specify which supported cache manager you want to use to improve the performance of Unica Interact, such as Ehcache or Ignite caching, and to configure specific cache properties for the runtime server you are configuring.

This includes the caches for storing session data, event pattern states, and segmentation results. By adjusting those settings, you can specify which cache solution to use for each type of caching, and you can specify individual settings to control how the cache works.

Interact | cacheManagement | caches | InteractCache

The InteractCache category configures the caching for all session objects, including the profile data, segmentation results, most recently delivered treatments, parameters passed through API methods, and other objects used by the Unica Interact run time.

The InteractCache category is required for Interact to work properly.

The InteractCache category can also be configured through an external EHCACHE configuration for settings that are not supported in **Interact | cacheManagement | Caches**. If you use EHCACHE, you must ensure that InteractCache is configured properly.

CacheManagerName

Description

The name of the cache manager that handles the Unica Interact cache. The value you enter here must be one of the cache managers defined in the **Interact | cacheManagement | Cache Managers** configuration properties, such as EHCACHE OR Ignite.

Default value

EHCACHE

Valid Values

Any cache manager defined in the **Interact | cacheManagement | Cache Managers** configuration property.

maxEntriesInCache

Description

The maximum number of session data objects to store in this cache. When the maximum number of session data objects has been reached, and data for an additional session need to be stored, the least-recently used object is deleted.

Default value

100000

Valid Values

Integer greater than 0.

timeoutInSecs

Description

The time in seconds that have elapsed since a session data object has been used or updated that are used to determine when the object is removed from the cache.



Note: If you upgraded from a version prior to 9.1, then you will need to reconfigure `timeoutInSecs` property because the property moved.

Default value

300

Valid Values

Integer greater than 0.

Interact | Caches | Interact Cache | Ignite

A cache manager "Ignite" is added under Cache Manager node. The cache Unica Interact Cache and PatternStateCache can use either EHCACHE or Ignite independently of each other. The following parameters are available for configuration:

cacheType

Description

When "Local" is selected, each node runs independently of each other. When "Distributed" is selected, all the nodes form a grid and the data are distributed across the grid, which is the default.

Default value

When "Distributed" is selected, all the nodes form a grid and the data are distributed across the grid, which is the default.

discoveryIPAddresses

Description

The comma separated list of nodes' addresses in the format of <IP>:<port> for the nodes to communicate with each other. If one of these addresses is a multicast address, multicast discovery is used. Otherwise, the static IP discovery is used, and in this case, at least one of them has to be active at any moment. This is required when "Distributed" is selected as the cache type. The default value 230.0.0.1:6363 is a multicast.

Default value

230.0.0.1:6363

localPort

The port each node will use for communicating with other nodes. If not specified, an open port in the range between 47500 and 47509 will be used. It is suggested to configure this setting if static IP discovery is used. This value can be overridden by using JVM property `-Dinteract.ignitePort=<valid port>`.

numberOfBackups

This is the backup copies of data are saved in the grid. Higher value will have better failover support and better read performance with the cost of lower write performance. When cache type is Distributed set numberOfBackups value to 1.

overflowToDisk

Whether persist data into a temporary file on disk.

Note: Requests for the same session on different instances may fail if an instance stops and no backup is configured. This implies, API call fails on two different RTs when cache type is Ignite, in a case.

Interact | Caches | Interact Cache | Parameter Data

The configuration properties in this category control the Interact Cache that is automatically used by your Unica Interact installation. These settings must be configured individually for each Unica Interact run time server.

asyncIntervalMillis

Description

The time in millisecond that the cache manager EHCACHE should wait before it replicates any changes to other Unica Interact run time instances. If the value is not positive, those changes will be replicated synchronously.

This configuration property is not created by default. If you create this property, it is used only when EHCACHE is the cache manager, and when the ehCache **cacheType** property is set to `distributed`.

Default value

None.

(Parameter)

Description

A template that you can use to create a custom parameter to be used with the Interact Cache. You can set up any parameter name, and the value it must have.

To create a custom parameter, click **(Parameter)** and complete the name and the value you want to assign to that parameter. When you click **Save Changes**, the parameter you have created is added to the list in the Parameter Data category.

Default value

None

Interact | cacheManagement | caches | PatternStateCache

The PatternStateCache category is used to host the states of event patterns and real time offer suppression rules. By default, this cache is configured as a read-through and write-through cache, so that Unica Interact attempts to use the cache first event pattern and offer suppression data. If the requested entry does not exist in the cache, the cache implementation loads it from the data source, through either the JNDI configuration or directly using a JDBC connection.

To use a JNDI connection, Unica Interact connects to an existing data source provider that has been defined through the specified server using the JNDI name, URL, and so on. For a JDBC connection, you must provide a set of JDBC settings that include the JDBC driver class name, database URL, and authentication information.

Note that if you define multiple JNDI and JDBC sources, the first enabled JNDI source is used, and if there is no enabled JNDI sources, the first enabled JDBC source is used.

The PatternStateCache category is required for Interact to work properly.

The PatternStateCache category can also be configured through an external EHCache configuration for settings that are not supported in **Interact | cacheManagement | Caches**. If you use EHCache, you must ensure that PatternStateCache is configured properly.

CacheManagerName

Description

The name of the cache manager that handles the Unica Interact pattern state cache. The value you enter here must be one of the cache managers defined in the **Interact | cacheManagement | Cache Managers** configuration properties, such as `EHCache` or `Ignite`.

Default value

EHCache

Valid Values

Any cache manager defined in the **Interact | cacheManagement | Cache Managers** configuration property.

maxEntriesInCache

Description

The maximum number of event pattern states to store in this cache. When the maximum number of event pattern states has been reached, and data for an additional event pattern state need to be stored, the least-recently used object is deleted.

Default value

100000

Valid Values

Integer greater than 0.

timeoutInSecs**Description**

Specifies the amount of time, in seconds, for an event pattern state object to time out in the event pattern state cache. When such a state object has been idling in the cache for `timeoutInSecs` number of seconds, it may be ejected from the cache based on the least-recently-used rule. Note that the value of this property should be larger than that defined in the `sessionTimeoutInSecs` property.



Note: If you upgraded from a version prior to 9.1, then you will need to reconfigure `timeoutInSecs` property because the property moved.

Default value

300

Valid Values

Integer greater than 0.

Interact | Caches | PatternStateCache | Parameter Data

The configuration properties in this category control the Pattern State Cache used to host the states of event patterns and real time offer suppression rules.

(Parameter)**Description**

A template that you can use to create a custom parameter to be used with the Pattern State Cache. You can set up any parameter name, and the value it must have.

To create a custom parameter, click **(Parameter)** and complete the name and the value you want to assign to that parameter. When you click **Save Changes**, the parameter you have created is added to the list in the Parameter Data category.

Default value

None

Interact | cacheManagement | caches | PatternStateCache | loaderWriter

The **loaderWriter** category contains the configuration of the loader that interacts with external repositories for the retrieval and persistence of event patterns.

className**Description**

The fully-qualified class name for this loader. This class must comply with the chosen cache manager's requirement.

Default value

```
com.unicacorp.interact.cache.ehcache.loaderwriter.  
PatternStateEHCacheLoaderWriter
```

Valid Values

A fully-qualified class name.

classPath**Description**

The path to the loader's class file. If you leave this value blank or the entry is invalid, the class path used for running Unica Interact is used.

Default value

None

Valid Values

A valid class path.

writeMode**Description**

Specifies the mode for the writer to persist the new or updated event pattern states in the cache. Valid options are:

- `WRITE_THROUGH`. Every time there is a new entry or an existing entry is updated, that entry is written into the repositories immediately.
- `WRITE_BEHIND`. The cache manager waits for some time to collect a number of changes, and then persists them into the repositories in a batch.

Default value

`WRITE_THROUGH`

Valid Values

`WRITE_THROUGH` or `WRITE_BEHIND`.

batchSize**Description**

The maximum number of event pattern state objects the writer will persist in a batch. This property is used only when **writeMode** is set to `WRITE_BEHIND`.

Default value

100

Valid Values

Integer value.

maxDelayInSecs

Description

The maximum time in seconds that the cache manager waits before an event pattern state object is persisted. This property is used only when **writeMode** is set to `WRITE_BEHIND`.

Default value

5

Valid Values

Integer value.

Interact | Caches | PatternStateCache | loaderWriter | Parameter Data

The configuration properties in this category control the Pattern State Cache loader.

(Parameter)

Description

A template that you can use to create a custom parameter to be used with the Pattern State Cache loader. You can set up any parameter name, and the value it must have.

To create a custom parameter, click **(Parameter)** and complete the name and the value you want to assign to that parameter. When you click **Save Changes**, the parameter you have created is added to the list in the Parameter Data category.

Default value

None

Interact | cacheManagement | caches | PatternStateCache | loaderWriter | jndiSettings

The **jndiSettings** category contains the configuration for the JNDI data source the loader will use to communicate with the backing database. To create a new set of JNDI settings, expand the **jndiSettings** category and click the **(jndiSetting)** property.

(jndiSettings)



Note: When the WebSphere Application Server is used, the loaderWriter is not get connected with the **jndiSettings**.

Description

When you click this category, a form appears. To define a JNDI data source, complete the following values:

- **New category name** is the name you want to use to identify this JNDI connection.
- **enabled** lets you indicate whether you want this JNDI connection to be available for use or not. Set this to `True` for new connections.
- **jndiName** is the JNDI name that has already been defined in the data source when it was set up.
- **providerUrl** is the URL to find this JNDI data source. If you leave this field blank, the URL of the web application that hosts the Unica Interact run time is used.
- **Initial context factory** is the fully qualified class name of the initial context factory class for connecting to the JNDI provider. If the web application hosting the Unica Interact run time is used for the **providerUrl**, leave this field blank.

Default value

None.

Interact | cacheManagement | caches | PatternStateCache | loaderWriter | jdbcSettings

The **jdbcSettings** category contains the configuration for the JDBC connections the loader will use to communicate with the backing database. To create a new set of JDBC settings, expand the **jdbcSettings** category and click the **(jdbcSetting)** property.

(jdbcSettings)

Description

When you click this category, a form appears. To define a JDBC data source, complete the following values:

- **New category name** is the name you want to use to identify this JDBC connection.
- **enabled** lets you indicate whether you want this JDBC connection to be available for use or not. Set this to `True` for new connections.
- **driverClassName** is the fully-qualified class name of the JDBC driver. This class must exist in the class path configured for starting the hosting cache server.
- **databaseUrl** is the URL to find this JDBC data source.
- **asmUser** is the name of the Unica user that has been configured with the credentials for connecting to the database in this JDBC connection.
- **asmDataSource** the name of Unica data source that has been configured with the credentials for connecting to the database in this JDBC connection.
- **maxConnection** is the maximum number of concurrent connections that are allowed to be made the database in this JDBC connection.

Default value

None.

Interact | triggeredMessage

The configuration properties in this category define settings for all triggered messages and offer channel delivery.

backendProcessIntervalMin

Description

This property defines the time period in minutes that the backend thread loads and processes delayed offer deliveries. This value must be an integer. If the value is zero or negative, the backend process is disabled.

Valid Values

A positive integer

autoLogContactAfterDelivery

Description

If this property is set to true, a contact event is automatically posted as soon as this offer is dispatched or this offer is queued for delayed delivery. If this property is set to false, no contact event is automatically posted for the outbound offers. This is the default behavior.

Valid Values

True | False

waitForFlowchart

Description

This property determines if the flowchart should wait for the currently running segmentation to finish, and the behavior if that wait times out.

DoNotWait: The processing of a triggered message starts regardless if segmentation is currently running or not. However, if segments are used in the eligibility rule and/or NextBestOffer is selected as the offer selection method, the TM execution still waits.

OptionalWait : The processing of a triggered message waits until the currently running segmentation finishes or times out. If the wait times out, a warning is logged, and the processing of this triggered message continues. This is the default.

MandatoryWait: The processing of a triggered message waits until the currently running segmentation finishes or times out. If the wait times out, an error is logged, and the processing of this triggered message aborts.

Valid Values

DoNotWait | OptionalWait | MandatoryWait

Interact | triggeredMessage | offerSelection

The configuration properties in this category define settings for offer selection in triggered messages.

maxCandidateOffers

Description

This property defines the maximum number of eligible offers that the engine returns to get the best offer for delivery. There is a chance that none of those returned eligible offers can be sent based on the selected channel. The more candidate offers there are, the less this case happens. However, more candidate offers can increase processing time.

Valid Values

A positive integer

defaultCellCode

Description

If the delivered offer is the result of evaluating a strategic rule or a table driven record, there is a target cell associated to it, and the information of this cell is used in all the related logging. However, if a list of specific offers are used as the input to the offer selection, no target cell is available. In this case, the value

of this configuration setting is used. You must make sure this target cell and its campaign are included in the deployment. The easiest method to achieve this is to add the cell into a deployed strategy.

Interact | triggeredMessage | dispatchers

The configuration properties in this category define settings for all dispatchers in triggered messages.

dispatchingThreads

Description

This property defines the number of threads the engine uses to asynchronously call the dispatchers. If the value is 0 or a negative number, the invocation of dispatchers is synchronous. The default value is 0.

Valid Values

An integer

Interact | triggeredMessage | dispatchers | <dispatcherName>

The configuration properties in this category define settings for a specific dispatcher in triggered messages.

category name

Description

This property defines the name of this dispatcher. The name must be unique among all dispatchers.

type

Description

This property defines the dispatcher type.

Valid Values

InMemoryQueue | JMSQueue | Custom | Kafka



Note: For WebSphere and WebLogic, it is recommended to use the latest supplied JVM fix pack version. If you have used Kafka in the previous version, then you can set the type as Kafka in the upgraded version.

JMSQueue only supports WebLogic. You cannot use JMSQueue if you use WebSphere Application Server.

className

Description

This property defines the fully qualified class name of this dispatcher implementation. If the type is InMemoryQueue the value should be empty. If the type is custom, this setting must have the following value

`"com.unicacorp.interact.eventhandler.triggeredmessage.dispatchers.KafkaDispatcher"`. If the type is Kafka, then the value must be empty.

classPath

Description

This property defines the URL to the JAR file that includes the implementation of this dispatcher. If the type is Kafka, then the value must be empty.

Interact | triggeredMessage | dispatchers | <dispatcherName> | Parameter Data

The configuration properties in this category define parameters for a specific dispatcher in triggered messages.

You can choose between three types of dispatchers. InMemoryQueue is the internal dispatcher for Unica Interact. Custom is used for Kafka. JMSQueue is used to connect to a JMS provider via JNDI. Kafka is distributed as a streaming platform, which is used to publish and subscribe the streams of records.

category name

Description

This property defines the name of this parameter. The name must be unique among all parameters for that dispatcher.

value

Description

This property defines the parameters, in the format of name value pairs, needed by this dispatcher.



Note: All parameters for trigger messages are case sensitive and should be entered as shown here.

If the type is InMemoryQueue, the following parameter is supported.

- **queueCapacity:** Optional. The maximum offers that can be waiting in the queue to be dispatched. When specified, this property must be a positive integer. If not specified or invalid, the default value (1000) is used.

If the type is Custom, the following parameters are supported.

- **providerUrl:** <hostname>:port (case sensitive)
- **queueManager:** The name of the queue manager that was created on the Kafka server.
- **messageQueueName:** The name of the message queue that was created on the Kafka server.
- **enableConsumer:** This property must be set to true.

- `asmUserforMQAuth`: The user name for logging into the server. It is required when the server enforces authentication. Otherwise, it should not be specified.
- `authDS`: The password associated with the user name for logging into the server. It is required when the server enforces authentication. Otherwise, it should not be specified.

If the type is `JMSQueue`, the following parameter is supported.

- `providerUrl`: The URL to the JNDI provider (case sensitive).
- `connectionFactoryJNDI`: The JNDI name of the JMS connection factory.
- `messageQueueJNDI`: The JNDI name of the JMS queue where the triggered messages are sent to and retrieved from.
- `enableConsumer`: This property specifies whether a consumer of those triggered messages must be started in Unica Interact. This property must be set to true. If not specified, the default value (false) is used.
- `initialContextFactory`: The fully qualified name of the JNDI initial context factory class. If you use WebLogic, the value of this parameter must be `weblogic.jndi.WLInitialContextFactory`.

If the type is `Kafka`, the following parameters are supported.

- `providerUrl`: A list of host/port pairs to be used for establishing the initial connection to the Kafka cluster. This list must be in the form of `host1:port1,host2:port2,...`.
- `topic`: A topic is a category or feed name to which messages are stored and published. All Kafka messages are organized into topics. If you require to send a message, you can send it to a specific topic and if you require to read a message you can read it from a specific topic. Producer applications write data to topics and consumer applications read from topics. Topic name must contain a ASCII alphanumeric, `'`, `_` and `-` characters. Due to the limitations in topic names, you can either

use topics with a period ('.') or underscore ('_'). The maximum length of a topic name can be 255 characters. For example, if you create or provide a topic name 'InteractTM_1' and you create a topic like 'InteractTM.1', then the following error is generated. "Topic InteractTM.1 collides with existing topics: InteractTM_1."

- **group.id:** Specifies the name of the consumer group to which a Kafka consumer belongs.
- **zookeeper.connect:** Specifies the zookeeper connection string in the form of `hostname:port`, where hostname and port are the host and port of a ZooKeeper server.
- **authentication:** Users can use Kafka by enabling different authentication mechanisms.

Mandatory parameters for publishing and subscribing messages

By default, the Kafka server does not support any authentication mechanism. Users can start the Kafka server considering that authentication mechanism is disabled. In this case, users can set the "authentication" parameter with value "None".

Table 79. Mandatory parameters for publishing messages

Parameters	Allowed/Sample Parameter Values
providerUrl	<host>:<port> (example: local-host:9092)
topic	Any string (example: InteractTM)
authentication	none Plain SSL SASL_SSL
zookeeper.connect	<host>:<port> (example: local-host:2181)

Table 80. Mandatory parameters for subscribing messages

Parameters	Allowed/Sample Parameter Value
providerUrl	<host>:<port> (example: local-host:9092)
group.id	Any string (example: InteractTM-Gateway)
topic	Any string (example: InteractTM)
authentication	none Plain SSL SASL_SSL
zookeeper.connect	<host>:<port> (example: local-host:2181)

Authentication mechanism

You can use Kafka by enabling different authentication mechanisms.

Authentication by SASL_PLAIN mechanism

If you require to use the SASL_PLAIN authentication mechanism, you must set the parameter "authentication" with value "Plain" along with its supported parameters.

The following parameters are required if SASL_PLAIN mechanism is supported.

- `asmUserforMQAuth`: The user name for logging into the server. It is required when the server enforces authentication.
- `authDS`: The password associated with the user name for logging into the server.
- `username/password`: The username or password of Kafka server configured in the JASS configuration file.

The following table provides the parameters required for SASL_PLAIN mechanism.

Parameters	Allowed/Sample parameter values
authentication	Plain
asmUserforMQAuth	Any string (example: test_user)
authDS	Any string (example: authDS)
username	Any string (example: test_user)
password	Any string (example: test-secret)

If the "authentication" parameter is "Plain", you must either use asmUserforMQAuth/authDS or username/password parameters for authentication .

Create the data sources (authDS) in the User section in platform configuration. See the following example for data sources details.

Datasource	Username	Password
authDS	test_user	test-secret

Authentication by SSL mechanism

To use the SSL authentication mechanism, you must set the parameter "authentication" with value "SSL" along with its supported parameters.

The following parameters are required to support SSL mechanism.

- ssl.keystore.location: The location of the key store file. You can use it for a two-way authentication for client.
- ssl.truststore.location: The location of the trust store file.
- SSLKeystoreDS: The keystore datasource name, which stores the password of ssl keystore.
- SSLKeyDS: The key datasource name, which stores the password of ssl key.
- SSLTruststoreDS: The truststore datasource name, which stores the password of ssl truststore.

The following table includes the supported parameters for SSL mechanism.

Parameters	Allowed/Sample Parameter Values
authentication	SSL
ssl.keystore.location	SSL Keystore location (example: <code>C:/SSL/kafka.client.keystore.jks</code>)
ssl.truststore.location	SSL Keystore location (example: <code>C:/SSL/kafka.client.truststore.jks</code>)
asmUserforMQAuth	Any string (example: <code>test_user</code>)
SSLKeystoreDS	Any string (example: <code>SSLKeystoreDS</code>)
SSLKeyDS	Any string (example: <code>SSLKeyDS</code>)
SSLTruststoreDS	Any string (example: <code>SSLTruststoreDS</code>)

Create the data sources (SSLKeystoreDS, SSLKeyDS, and SSLTruststoreDS) in the User section in platform configuration. See the following example for data sources details.

Datasource	Username	Password
SSLKeystoreDS	keystore	keystore-secret
SSLKeyDS	key	key-secret
SSLTruststoreDS	truststore	truststore -secret



Note: Client keystore or truststore is required at Producer or Consumer side in Unica Interact application (where the Interact



application is installed). `C:/SSL/kafka.client.keystore.jks` and `C:/SSL/kafka.client.truststore.jks` are the local locations, where the Interact application is installed.

Authentication by SASL_SSL mechanism

If you require to use the SASL_SSL authentication mechanism, then you must set the parameter "authentication" with value "SASL_SSL" along with its supported parameters. SASL_SSL mechanism is the combination of SASL_PLAIN and SSL mechanisms. The following table includes the supported parameters for SASL_SSL mechanism.

Parameters	Allowed/Sample Parameter Values
authentication	SASL_SSL
asmUserforMQAuth	Any string (example: test_user)
authDS	Any string (example: authDS)
username	Any string (example: test_user)
password	Any string (example: test-secret)
ssl.keystore.location	SSL Keystore location (example: <code>C:/SSL/kafka.client.keystore.jks</code>)
ssl.truststore.location	SSL Keystore location (example: <code>C:/SSL/kafka.client.truststore.jks</code>)
SSLKeystoreDS	Any string (example: SSLKeystoreDS)
SSLKeyDS	Any string (example: SSLKeyDS)

Parameters	Allowed/Sample Parameter Values
SSLTruststoreDS	Any string (example: SSLTruststoreDS)

If the "authentication" parameter is "SASL_SSL", you must either use `asmUserforMQAuth/authDS` or `username/password`.

Create the data sources (`authDS`, `SSLKeystoreDS`, `SSLKeyDS` and `SSLTruststoreDS`) in the User section in platform configuration. For data sources details, see the following example.

Datasource	Username	Password
<code>authDS</code>	<code>admin</code>	<code>admin-secret</code>
<code>SSLKeystoreDS</code>	<code>keystore</code>	<code>test1234</code>
<code>SSLKeyDS</code>	<code>key</code>	<code>test1234</code>
<code>SSLTruststoreDS</code>	<code>truststore</code>	<code>test1234</code>



Note: If you provide any data sources like `authDS`, `SSLKeystoreDS`, `SSLKeyDS`, or `SSLTruststoreDS` in the platform configuration parameter, then you must also provide `asmUserforMQAuth` parameter.

Client keystore/truststore is required at Producer/Consumer side in the Interact application (where Unica Interact application is installed). `C:/SSL/kafka.client.keystore.jks` and `C:/SSL/kafka.client.truststore.jks` are the local locations, where Interact application is installed.

Optional parameter for publishing messages

The following optional parameters can be used for publishing messages.

- **acks:** The acks config controls the criteria under which requests are considered complete. The "all" setting results in blocking the full commit of the record.
- **retries:** If the request fails, the producer can retry. Since, the specified retries are set as 0, retry is not possible. Enabling retries can lead to duplicates.
- **batch.size:** The default batch size is in bytes, when multiple records are batched and sent to a partition.
- **linger.ms:** The producer waits till the given delay time to allow other records to be sent so that the sent records can be batched together.
- **buffer.memory:** The total bytes of memory that the producer can use to buffer records, which are waiting to be sent to the server.

The following table includes the optional parameters required for publishing messages.

Parameters	Default value	Allowed/Sample Parameter values
acks	1	0, 1, all
retries	3	Non-negative integer
batch.size	16384	Positive integer
linger.ms	0	Non-negative integer
buffer.memory	33554432	Positive integer

Optional parameters for subscribing messages

`enable.auto.commit` means that offsets are committed automatically with a frequency controlled by the config "`auto.commit.interval.ms`". The value of `auto.commit.interval.ms` must not exceed 1000 as the poll interval is set to 1000. The value of `auto.commit.interval.ms` must not exceed the value of poll interval.

The following table includes the optional parameters for subscribing messages.

Parameters	Default value	Allowed/Sample parameter values
enable.auto.commit	true	True, False
auto.commit.interval- .ms	200	Positive integer

Optional thread management parameters

The following optional parameters can be used for thread management.

- **corePoolSize**: The number of threads to keep in the pool for monitoring Kafka service.
- **maxPoolSize**: The maximum number of threads to keep in the pool for monitoring Kafka service.
- **keepAliveTimeSecs**: The maximum time that the excess idle threads waits for new tasks before terminating to monitor Kafka service, when the number of threads is greater than the core.
- **queueCapacity**: The size of the queue used by the thread pool to monitor Kafka service.

The following table includes the optional parameters for thread management.

Parameters	Default value	Allowed/Sample Parameter Values
corePoolSize	1	Positive integer
maxPoolSize	5	Positive integer
keepAliveTimeSecs	5	Positive integer
queueCapacity	100	Positive integer

Optional zookeeper parameters

The following optional parameters can be used for zookeeper activities.

`zookeeper.connection.timeout.ms`: The maximum time that the client waits to establish a connection with zookeeper. If not set, the value in `zookeeper.session.timeout.ms` is used.

The following table includes the optional parameters for Zookeeper activities.

Parameters	Default Value	Allowed/Sample Parameter Value
<code>zookeeper.connection.timeout.ms</code>	6000	Positive integer

Optional parameters for creating topic

The following optional parameters can be used for creating topic.

- `num.partitions`: The number of partitions for the offset commit topic.
- `replication.factor`: The replication factor to change log topics and repartition topics created by the stream processing application.

The following table includes the optional parameters for creating topic.

Parameters	Default value	Allowed/Sample Parameter Values
<code>num.partitions</code>	1	Positive integer
<code>replication.factor</code>	1	Positive integer

Interact | triggeredMessage | gateways | <gatewayName>

The configuration properties in this category define settings for a specific gateway in triggered messages.

Unica Interact does not support multiple instances of the same gateway. All of the gateway configuration files should be accessible from every Unica Interact Runtime node. In the case of a distributed setup, ensure that the gateway files are kept at a shared location.



Note: The out of the box gateways with names "EMail", "MobilePush", "UBX" are available under this node along with all required parameters and their respective values . You do not require to update any of the values in Platform configuration . Only change is required in the properties files which are referred in those configurations. In case you have upgraded from a previous version of Interact , then any existing configuration using those gateways will continue to work as is.

category name

Description

This property defines the name of this gateway. It must be unique among all gateways.

className

Description

This property defines the fully qualified class name of this gateway implementation.

classPath

Description

This property defines the URI of the JAR file that includes the implementation of this gateway. If left empty, the class path of the hosting Interact application is used.

For example in a Windows system, if the gateway JAR file is available in the directory, `C:\HCL\Unica\EmailGateway\IBM_Interact_OMO_OutboundGateway_Silverpop_1.0\lib\OMO_OutboundGateway_Silverpop.jar`, the classPath should be `file:///C:/HCL/Unica/EmailGateway/IBM_Interact_OMO_OutboundGateway_Silverpop_1.0/lib/OMO_OutboundGateway_Silverpop.jar`. In a Unix system, if the gateway jar file is available in the directory, `/opt/HCL/Unica/EmailGateway/IBM_Interact_OMO_OutboundGateway_Silverpop_1.0/lib/OMO_OutboundGateway_Silverpop.jar`, the classpath should be `file:///opt/HCL/Unica/EmailGateway/IBM_Interact_OMO_OutboundGateway_Silverpop_1.0/lib/OMO_OutboundGateway_Silverpop.jar`.

Interact | triggeredMessage | gateways | <gatewayName> | Parameter Data

The configuration properties in this category define parameters for a specific gateway in triggered messages.

category name

Description

This property defines the name of this parameter. The name must be unique among all parameters for that gateway.

value

Description

This property defines the parameters, in the format of name value pairs, needed by this gateway. For all gateways, the following parameters are supported.



Note:



- All parameters for trigger messages are case sensitive and should be entered as shown here.
 - `validationTimeoutMillis`: The duration in milliseconds that the validation of an offer through this gateway timeouts. The default value is 500.
 - `deliveryTimeoutMillis`: The duration in milliseconds that the delivery of an offer using this gateway timeouts. The default value is 1000.
- In order to get gateway related logs in the `Interact.log` file, place the old `'interact_log4j2.xml'` from versions prior to 11.1 in `'InteractRT.war/WEB-INF/classes'` and also put it at any location outside the war file . You need to specify the following JVM parameter in the application server: `-Dlog4j.configuration=file:/opt/any_location/interact_log4j.properties`

Interact | triggeredMessage | channels

The configuration properties in this category define settings for all channels in triggered messages.

type

Description

This property defines the root node for settings related to a specific gateway. Default uses the built in channel selector, which is based on the list of channels defined on in the triggered messages UI. If default is selected, `className` and `classPath` values should be left blank. Custom uses the customer implementation of `IChannelSelector`.

Valid Values

Default | Custom

className**Description**

This property defines the fully qualified class name of the customer implementation of channel selector. This setting is required if the type is Custom.

classPath**Description**

This property defines the URL to the JAR file that includes the implementation of the customer implementation of channel selector. If left empty, the class path of the hosting Interact application is used.

Interact | triggeredMessage | channels | <channelName>

The configuration properties in this category define settings for a specific channel in triggered messages.

category name**Description**

This property defines the name of the channel through which offers are sent. It should match those defined in the design time under **Campaign | partitions | <partition[N]> | Interact | outboundChannels**.

Interact | triggeredMessage | channels | <channelName> | <handlerName>

The configuration properties in this category define settings for a specific handler in triggered messages that is used to sent offers.

category name**Description**

This property defines the name of the handler which the channel will use to send offers.

dispatcher

Description

This property defines the name of the dispatcher through which this handler uses send offers to the gateway. It must be one of those defined under **interact | triggeredMessage | dispatchers**.

gateway

Description

This property defines the name of the gateway to which this handler send offers ultimately. It must be one of those defined under **interact | triggeredMessage | gateways**.

mode

Description

This property defines the usage mode of this handler. If Failover is selected, this handler is used only when all the handlers with higher priorities defined within this channel failed to send offers. If Addon is selected, this handler is used no matter if other handlers have successfully sent offers.

priority

Description

This property defines the priority of this handler. The engine first tries to use the handler with the highest priority for sending offers.

Valid Values

Any integer

Default

100

Interact | triggeredMessage | channels | Parameter Data

The configuration properties in this category define parameters for a specific channel in triggered messages.

category name

Description

This property defines the name of this parameter. The name must be unique among all parameters for that channel.

value

Description

This property defines the parameters, in the format of name value pairs, needed by the channel selector.

If you use **Customer Preferred Channels** for your channel, you must create

Interact | activityOrchestrator

The activity orchestrator category specifies the receivers and gateways for your Unica Interact inbound gateway activity.

Use the **Interact | activityOrchestrator | receivers** configuration properties to configure your Unica Interact receivers. Use the **Interact | activityOrchestrator | gateways** configuration properties to configure your gateways to use in Unica Interact.

Interact | activityOrchestrator | gateways

The activity orchestrator gateway category specifies the gateways for your Unica Interact inbound gateway activity.



Note: The out of the box inbound gateway with name "UBX" is available under this node along with all required parameters and their respective values . You are not required to update any of the values in Platform configuration . Only change is required in the properties files which are referred in those configurations. In



case you have upgraded from a previous version of Interact, then any existing configuration using those gateways continue to work as is.

Category name

Description

The name of your gateway.

className

Description

This property defines the fully qualified class name of this gateway implementation.

classPath

Description

This property defines the URI to the JAR file that includes the implementation of this gateway. If left empty, the class path of the hosting Unica Interact application is used. It is used only when the type is `Custom`.

Interact | activityOrchestrator | gateways | Parameter Data

You can add gateway parameters for your gateway configuration files, such as `OMO-conf_inbound_UBX_interactEventNameMapping` and `OMO-conf_inbound_UBX_interactEventPayloadMapping`.

Configuration tree paths

```
Interact | activityOrchestrator | gateways | <gatewayName> | Parameter
Data | <partitionName> | processTimeoutMillis | value=XXX
```

```
Interact | activityOrchestrator | gateways | <gatewayName> | Parameter
Data | <partitionName> | OMO-processTimeoutMillis | value=XXX
```

Interact | activityOrchestrator | receivers

The activity orchestrator receivers category specifies the event receivers for your Unica Interact inbound gateway activity.

Category name

Description

The name of your receiver.

Type

Description

The type of receiver. You can choose between Kafka, and Custom. Custom requires you to use an implementation of the `iReceiver`.



Note: If you have used Kafka in the previous version, then you can set the value of type as Kafka in the upgraded version.

Enabled

Description

Select `True` to enable the receiver or `false` to disable the receiver.

className

Description

This property defines the fully qualified class name of this receiver implementation. It is used only when the type is `Custom`. If the type is `Kafka`, then the value must be empty.

classPath

Description

This property defines the URI to the JAR file that includes the implementation of this receiver. If left empty, the class path of the hosting Unica Interact

application is used. It is used only when the type is `Custom`. If the type is Kafka, then the value must be empty.

Interact | activityOrchestrator | receivers | Parameter Data

You can add receiver parameters, such as `queueManager` and `messageQueueName` to define your receiver queue.

If the type is Kafka, the following parameters are supported.

- `providerUrl`: A list of host/port pairs to be used for establishing the initial connection with the Kafka cluster. This list must be in the form of `host1:port1,host2:port2,...`.
- `topic`: A topic is a category or feed name to which messages are stored and published. All Kafka messages are organized into topics. If you require to send a message, you can send it to a specific topic and if you require to read a message you can read it from a specific topic. Producer applications write data to topics and consumer applications read from topics. Topic name must contain a ASCII alphanumeric, '.', '_' and '-' characters. Due to the limitations in topic names, you can either use topics with a period ('.') or underscore ('_'). The maximum length of a topic name can be 255 characters. For example, if you create or provide a topic name 'InteractTM_1', and you try to create a topic like 'InteractTM.1', then the following error is generated. "Topic InteractTM.1 collides with existing topics: InteractTM _1."
- `group.id`: Specifies the name of the consumer group to which a Kafka consumer belongs.
- `zookeeper.connect`: Specifies the zookeeper connection string in the form of `hostname:port`, where `hostname` and `port` are the host and port of a zookeeper server.
- `authentication`: Users can use Kafka by enabling different authentication mechanisms.

Mandatory parameters for subscribing messages

By default, the Kafka server does not support any authentication mechanism. You can start the Kafka server considering that authentication mechanism is disabled. In this case, you can set the "authentication" parameter with value "None". The following table includes the mandatory parameters required to subscribe messages.

Parameters	Allowed/Sample Parameter Value
providerUrl	<host>:<port> (example: local-host:9092)
group.id	Any string (example: InteractTM-Gateway)
topic	Any string (example: InteractTM)
authentication	Any string
zookeeper.connect	<host>:<port> (example: local-host:2181)

Authentication mechanism

You can use Kafka by enabling different authentication mechanisms.

Authentication by SASL_PLAIN mechanism

If you want to use the SASL_PLAIN authentication mechanism, you must set the parameter "authentication" with value "Plain" along with its supported parameters.

The following parameters are required, if SASL_PLAIN mechanism is supported.

- **asmUserforMQAuth:** The user name for logging into the server. It is required when the server enforces authentication.
- **authDS:** The password associated with the user name for logging into the server.
- **username/password:** The username or password of Kafka server configured in the JASS configuration file.

The following table provides the parameters required for the SASL_PLAIN mechanism.

Parameters	Allowed/Sample parameter values
authentication	Plain
asmUserforMQAuth	Any string (example: test_user)
authDS	Any string (example: authDS)
username	Any string (example: test_user)
password	Any string (example: test-secret)

If the "authentication" parameter is "Plain", you must either use asmUserforMQAuth/authDS or username/password parameters for authentication .

Create the data sources (authDS) in the User section in platform configuration. See the following example for data sources details.

Datasource	Username	Password
authDS	test_user	test-secret

Authentication by SSL mechanism

To use the SSL authentication mechanism, you must set the parameter 'authentication' with value 'SSL' along with its supported parameters.

The following parameters are required to support SSL mechanism.

- `ssl.keystore.location`: The location of the key store file. You can use it for a two-way authentication for client.
- `ssl.truststore.location`: The location of the trust store file.
- `SSLKeystoreDS`: The keystore datasource name, which stores the password of ssl keystore.
- `SSLKeyDS`: The key datasource name, which stores the password of ssl key.
- `SSLTruststoreDS`: The truststore datasource name, which stores the password of ssl truststore.

The following table includes the supported parameters for SSL mechanism.

Parameters	Allowed/Sample Parameter Values
authentication	SSL
<code>ssl.keystore.location</code>	SSL Keystore location (example: <code>C:/SSL/kafka.client.keystore.jks</code>)
<code>ssl.truststore.location</code>	SSL Keystore location (example: <code>C:/SSL/kafka.client.truststore.jks</code>)
<code>asmUserforMQAuth</code>	Any string (example: <code>test_user</code>)
<code>SSLKeystoreDS</code>	Any string (example: <code>SSLKeystoreDS</code>)
<code>SSLKeyDS</code>	Any string (example: <code>SSLKeyDS</code>)
<code>SSLTruststoreDS</code>	Any string (example: <code>SSLTruststoreDS</code>)

Create the data sources (SSLKeystoreDS, SSLKeyDS, and SSLTruststoreDS) in the User section in platform configuration. See the following example for data sources details.

Datasource	Username	Password
SSLKeystoreDS	keystore	keystore-secret
SSLKeyDS	key	key-secret
SSLTruststoreDS	truststore	truststore -secret



Note: Client keystore or truststore is required at Producer or Consumer side in Interact application (where the Interact application is installed). `C:/SSL/kafka.client.keystore.jks` and `C:/SSL/kafka.client.truststore.jks` are the local locations, where the Interact application is installed.

Authentication by SASL_SSL mechanism

If you require to use the SASL_SSL authentication mechanism, then you must set the parameter "authentication" with value "SASL_SSL" along with its supported parameters. SASL_SSL mechanism is the combination of SASL_PLAIN and SSL mechanisms. The following table includes the supported parameters for SASL_SSL mechanism.

Parameters	Allowed/Sample Parameter Values
authentication	SASL_SSL
asmUserforMQAuth	Any string (example: test_user)
authDS	Any string (example: authDS)
username	Any string (example: test_user)
password	Any string (example: test-secret)

Parameters	Allowed/Sample Parameter Values
ssl.keystore.location	SSL Keystore location (example: <code>C:/SSL/kafka.client.keystore.jks</code>)
ssl.truststore.location	SSL Keystore location (example: <code>C:/SSL/kafka.client.truststore.jks</code>)
SSLKeystoreDS	Any string (example: SSLKeystoreDS)
SSLKeyDS	Any string (example: SSLKeyDS)
SSLTruststoreDS	Any string (example: SSLTruststoreDS)

If the "authentication" parameter is "SASL_SSL", you must either use `asmUserforMQAuth/authDS` or `username/password`.

Create the data sources (`authDS`, `SSLKeystoreDS`, `SSLKeyDS`, and `SSLTruststoreDS`) in the User section in platform configuration. For data sources details, see the following example.

Datasource	Username	Password
<code>authDS</code>	<code>admin</code>	<code>admin-secret</code>
<code>SSLKeystoreDS</code>	<code>keystore</code>	<code>test1234</code>
<code>SSLKeyDS</code>	<code>key</code>	<code>test1234</code>
<code>SSLTruststoreDS</code>	<code>truststore</code>	<code>test1234</code>



Note: If you provide any data sources like `authDS`, `SSLKeystoreDS`, `SSLKeyDS`, or `SSLTruststoreDS` in the platform configuration parameter, then you must also provide `asmUserforMQAuth` parameter.



Client keystore/truststore is required at Producer/Consumer side in Interact application (where Interact application is installed).

`C:/SSL/kafka.client.keystore.jks` and `C:/SSL/kafka.client.truststore.jks` are the local locations, where Interact application is installed.

Optional parameters for subscribing messages

`enable.auto.commit` means that offsets are committed automatically with a frequency controlled by the config "`auto.commit.interval.ms`". The value of `auto.commit.interval.ms` must not exceed 1000 as the poll interval is set to 1000. The value of `auto.commit.interval.ms` must not exceed the value of poll interval.

The following table includes the optional parameters for subscribing messages.

Parameters	Default value	Allowed/Sample parameter values
<code>enable.auto.commit</code>	true	True, False
<code>auto.commit.interval.ms</code>	200	Positive integer

Optional thread management parameters

The following optional parameters can be used for thread management.

- `corePoolSize`: The number of threads to keep in the pool for monitoring Kafka service.
- `maxPoolSize`: The maximum number of threads to keep in the pool for monitoring Kafka service.

- `keepAliveTimeSecs`: The maximum time taken by the excess idle threads to wait for new tasks before terminating to monitor Kafka service, when the number of threads is greater than the core.
- `queueCapacity`: The size of the queue used by the thread pool for monitoring Kafka service.

The following table includes the optional parameters for thread management.

Parameters	Default value	Allowed/Sample Parameter Values
<code>corePoolSize</code>	1	Positive integer
<code>maxPoolSize</code>	5	Positive integer
<code>keepAliveTimeSecs</code>	5	Positive integer
<code>pqueueCapacity</code>	100	Positive integer

Optional zookeeper parameters

The following optional parameter can be used for Zookeeper activities.

`zookeeper.connection.timeout.ms`: The maximum time that the client waits to establish a connection with zookeeper. If not set, the value in "`zookeeper.session.timeout.ms`" is used.

The following table includes the optional parameters for zookeeper activities.

Parameter	Default Value	Allowed/Sample Parameter Value
<code>zookeeper.connection.timeout.ms</code>	6000	Positive integer

Optional parameters for creating topic

The following optional parameters can be used for creating topic.

- `num.partitions`: The number of partitions for the offset commit topic.
- `replication.factor`: The replication factor to change log topics and repartition topics created by the stream processing application.

The following table includes the optional parameters for creating topic.

Parameters	Default value	Allowed/Sample Parameter Values
<code>num.partitions</code>	1	Positive integer
<code>replication.factor</code>	1	Positive integer

Unica Interact design environment configuration properties

This section describes all the configuration properties for Unica Interact design environment.

Campaign | partitions | partition[n] | reports

The **Campaign | partitions | partition[n] | reports** property defines the different types of folders for reports.

offerAnalysisTabCachedFolder

Description

The `offerAnalysisTabCachedFolder` property specifies the location of the folder that contains the specification for bursted (expanded) offer reports listed on the Analysis tab when you reach it by clicking the Analysis link on the navigation pane. The path is specified by using the XPath notation.

Default value

```
/content/folder[@name='Affinium Campaign - Object Specific Reports']/folder[@name='offer']/folder[@name='cached']
```

segmentAnalysisTabOnDemandFolder

Description

The `segmentAnalysisTabOnDemandFolder` property specifies the location of the folder that contains the segment reports listed on the Analysis tab of a segment. The path is specified by using the XPath notation.

Default value

```
/content/folder[@name='Affinium Campaign - Object Specific Reports']/folder[@name='segment']/folder[@name='cached']
```

offerAnalysisTabOnDemandFolder

Description

The `offerAnalysisTabOnDemandFolder` property specifies the location of the folder that contains the offer reports listed on the Analysis tab of an offer. The path is specified by using the XPath notation.

Default value

```
/content/folder[@name='Affinium Campaign - Object Specific Reports']/folder[@name='offer']
```

segmentAnalysisTabCachedFolder

Description

The `segmentAnalysisTabCachedFolder` property specifies the location of the folder that contains the specification for bursted (expanded) segment reports listed on the Analysis tab when you reach it by clicking the Analysis link on the navigation pane. The path is specified by using the XPath notation.

Default value

```
/content/folder[@name='Affinium Campaign - Object Specific Reports']/folder[@name='segment']
```

analysisSectionFolder

Description

The `analysisSectionFolder` property specifies the location of the root folder where report specifications are stored. The path is specified by using the XPath notation.

Default value

```
/content/folder[@name='Affinium Campaign']
```

campaignAnalysisTabOnDemandFolder

Description

The `campaignAnalysisTabOnDemandFolder` property specifies the location of the folder that contains the campaign reports listed on the Analysis tab of a campaign. The path is specified by using the XPath notation.

Default value

```
/content/folder[@name='Affinium Campaign - Object Specific  
Reports']/folder[@name='campaign']
```

campaignAnalysisTabCachedFolder

Description

The `campaignAnalysisTabCachedFolder` property specifies the location of the folder that contains the specification for bursted (expanded) campaign reports listed on the Analysis tab when you reach it by clicking the Analysis link on the navigation pane. The path is specified by using the XPath notation.

Default value

```
/content/folder[@name='Affinium Campaign - Object Specific  
Reports']/folder[@name='campaign']/folder[@name='cached']
```

campaignAnalysisTabEmessageOnDemandFolder

Description

The `campaignAnalysisTabEmessageOnDemandFolder` property specifies the location of the folder that contains the IBM eMessage reports listed on the Analysis tab of a campaign. The path is specified by using the XPath notation.

Default value

```
/content/folder[@name='Affinium Campaign']/folder[@name='eMessage
Reports']
```

campaignAnalysisTabInteractOnDemandFolder**Description**

Report server folder string for Unica Interact reports.

Default value

```
/content/folder[@name='Affinium Campaign']/folder[@name='Interact
Reports']
```

Availability

This property is applicable only if you install Unica Interact.

interactiveChannelAnalysisTabOnDemandFolder**Description**

Report server folder string for Interactive Channel analysis tab reports.

Default value

```
/content/folder[@name='Affinium Campaign - Object Specific Reports']/
folder[@name='interactive channel']
```

Availability

This property is applicable only if you install Unica Interact.

Campaign | partitions | partition[n] | Interact |
contactAndResponseHistTracking

These configuration properties define settings for the Unica Interact contact and response history module.

isEnabled**Description**

If set to `yes`, enables the Unica Interact contact and response history module which copies the Unica Interact contact and response history from staging tables in the Unica Interact runtime to the Unica Campaign contact and response history tables. The property `interactInstalled` must also be set to `yes`.

Default value

no

Valid Values

yes | no

Availability

This property is applicable only if you have installed Unica Interact.

runOnceADay**Description**

Specifies whether to run the Contact and Response History ETL once a day. If you set this property to `yes`, the ETL runs during the scheduled interval specified by `preferredStartTime` and `preferredEndTime`.

If ETL takes more than 24 hours to execute, and thus misses the start time for the next day, it will skip that day and run at the scheduled time the following day. For example, if ETL is configured to run between 1AM to 3AM, and the process starts at 1AM on Monday and completes at 2AM on Tuesday, the next run, originally scheduled for 1AM on Tuesday, will be skipped, and the next ETL will start at 1AM on Wednesday.

ETL scheduling does not account for Daylight Savings Time changes. For example, if ETL scheduled to run between 1AM and 3AM, it could run at 12AM or 2AM when the DST change occurs.

Default value

No

Availability

This property is applicable only if you have installed Unica Interact.

processSleepIntervalInMinutes

Description

The number of minutes the Unica Interact contact and response history module waits between copying data from the Unica Interact runtime staging tables to the Unica Campaign contact and response history tables.

Default value

60

Valid Values

Any integer greater than zero.

Availability

This property is applicable only if you have installed Unica Interact.

preferredStartTime

Description

The preferred time to start the daily ETL process. This property, when used in conjunction with the preferredEndTime property, sets up the preferred time interval during which you want the ETL to run. The ETL will start during the specified time interval and will process at most the number of records specified using `maxJDBCFetchBatchSize`. The format is HH:mm:ss AM or PM, using a 12-hour clock.

Default value

12:00:00 AM

Availability

This property is applicable only if you have installed Unica Interact.

preferredEndTime

Description

The preferred time to complete the daily ETL process. This property, when used in conjunction with the preferredStartTime property, sets up the preferred time interval during which you want the ETL to run. The ETL will start during the specified time interval and will process at most the number of records specified using maxJDBCFetchBatchSize. The format is HH:mm:ss AM or PM, using a 12-hour clock.

Default value

2:00:00 AM

Availability

This property is applicable only if you have installed Unica Interact.

purgeOrphanResponseThresholdInMinutes

Description

The number of minutes the Unica Interact contact and response history module waits before purging responses with no corresponding contact. This prevents logging responses without logging contacts.

Default value

180

Valid Values

Any integer greater than zero.

Availability

This property is applicable only if you have installed Unica Interact.

maxJDBCInsertBatchSize

Description

The maximum number of records of a JDBC batch before committing the query. This is not the max number of records that the Unica Interact contact and response history module processes in one iteration. During each iteration, the Unica Interact contact and response history module processes

all available records from the staging tables. However, all those records are broken into `maxJDBCInsertSize` chunks.

Default value

1000

Valid Values

Any integer greater than zero.

Availability

This property is applicable only if you have installed Unica Interact.

maxJDBCFetchBatchSize**Description**

The maximum number of records of a JDBC batch to fetch from the staging database. You may need to increase this value to tune the performance of the contact and response history module.

For example, to process 2.5 million contact history records a day, you should set `maxJDBCFetchBatchSize` to a number greater than 2.5M so that all records for one day will be processed.

You could then set `maxJDBCFetchChunkSize` and `maxJDBCInsertBatchSize` to smaller values (in this example, perhaps to 50,000 and 10,000, respectively).

Some records from the next day may be processed as well, but would then be retained until the next day.

Default value

1000

Valid Values

Any integer greater than zero

maxJDBCFetchChunkSize**Description**

The maximum number of a JDBC chunk size of data read during ETL (extract, transform, load). In some cases, a chunk size greater than insert size can improve the speed of the ETL process.

Default value

1000

Valid Values

Any integer greater than zero

deleteProcessedRecords

Description

Specifies whether to retain contact history and response history records after they have been processed.

Default value

Yes

completionNotificationScript

Description

Specifies the absolute path to a script to run when the ETL is completed. If you specify a script, five arguments are passed to the completion notification script: start time, end time, total number of CH records processed, total number of RH records processed and status. The start time and end time are numeric values representing number of milliseconds elapsed since 1970. The status argument indicates whether the ETL job was a success or failure. 0 indicates a successful ETL job. 1 indicates a failure and that there are some errors in the ETL job.

Default value

None

fetchSize

Description

Allow you to set the JDBC fetchSize when retrieving records from staging tables.

On Oracle databases especially, adjust the setting to the number of records that the JDBC should retrieve with each network round trip. For large batches of 100K or more, try 10000. Be careful not to use too large a value here, because that will have an impact on memory usage and the gains will become negligible, if not detrimental.

Default value

None

daysBackInHistoryToLookupContact

Description

Limits the records that are searched during response history queries to those within the past specified number of days. For databases with a large number of response history records, this can reduce processing time on queries by limiting the search period to the number of days specified.

When the value for daysBackInHistoryToLookupContact is greater than zero, a date constraint is added to the RH join query. This is useful when the UA_DtlContactHist table is date partitioned. The date constraint limits the records searched within the date constraint."

The default value of 0 indicates that all records are searched.

Default value

0 (zero)

Campaign | partitions | partition[n] | Interact | contactAndResponseHistTracking | runtimeDataSources | [runtimeDataSource]

These configuration properties define the data source for the Unica Interact contact and response history module.

jndiName

Description

Use the `systemTablesDataSource` property to identify the Java™ Naming and Directory Interface (JNDI) data source that is defined in the application server (Websphere or WebLogic) for the Unica Interact runtime tables.

The Unica Interact runtime database is the database populated with the `aci_runtime` and `aci_populate_runtime` dll scripts and, for example, contains the following tables (among others): `UACI_CHOfferAttrib` and `UACI_DefaultedStat`.

Default value

No default value defined.

Availability

This property is applicable only if you have installed Unica Interact.

databaseType

Description

Database type for the Unica Interact runtime data source.

Default value

SQLServer

Valid Values

SQLServer | Oracle | DB2® | MariaDB | IIFORMIX

Availability

This property is applicable only if you have installed Unica Interact.

schemaName

Description

The name of the schema containing the contact and response history module staging tables. This should be the same as the runtime environment tables.

You do not have to define a schema.

Default value

No default value defined.

Campaign | partitions | partition[n] | Interact |
contactAndResponseHistTracking | contactTypeMappings

These configuration properties define the contact type from campaign that maps to a 'contact' for reporting or learning purposes.

contacted

Description

The value assigned to the `ContactStatusID` column of the `UA_DtlContactHist` table in the Unica Campaign system tables for an offer contact. The value must be a valid entry in the `UA_ContactStatus` table. See the Unica Campaign Administrator's Guide for details on adding contact types.

Default value

2

Valid Values

An integer greater than zero.

Availability

This property is applicable only if you have installed Unica Interact.

Campaign | partitions | partition[n] | Interact |
contactAndResponseHistTracking | responseTypeMappings

These configuration properties define the responses for accept or reject for reporting and learning.

accept

Description

The value assigned to the `ResponseTypeID` column of the `UA_ResponseHistory` table in the Unica Campaign system tables for an accepted offer. The value must be a valid entry in the `UA_UsrResponseType` table. You should assign the `CountsAsResponse` column the value 1, a response.

See the Unica Campaign Administrator's Guide for details on adding response types.

Default value

3

Valid Values

An integer greater than zero.

Availability

This property is applicable only if you have installed Unica Interact.

reject**Description**

The value assigned to the `ResponseTypeID` column of the `UA_ResponseHistory` table in the Unica Campaign system tables for a rejected offer. The value must be a valid entry in the `UA_UsrResponseType` table. You should assign the `CountsAsResponse` column the value 2, a reject. See the Unica Campaign Administrator's Guide for details on adding response types.

Default value

8

Valid Values

Any integer greater than zero.

Availability

This property is applicable only if you have installed Unica Interact.

Campaign | partitions | partition[n] | Interact | report

These configuration properties define the report names when integrating with Cognos®.

interactiveCellPerformanceByOfferReportName

Description

Name for Interactive Cell Performance by Offer report. This name must match the name of this report on the Cognos® server.

Default value

Interactive Cell Performance by Offer

treatmentRuleInventoryReportName

Description

Name for Treatment Rule Inventory report. This name must match the name of this report on the Cognos® server.

Default value

Channel Treatment Rule Inventory

deploymentHistoryReportName

Description

Name for Deployment History Report report. This name must match the name of this report on the Cognos® server

Default value

Channel Deployment History

Campaign | partitions | partition[n] | Interact | learning

These configuration properties enable you to tune the built-in learning module.

confidenceLevel

Description

A percentage indicating how confident you want the learning utility to be before switching from exploration to exploitation. A value of 0 effectively shuts off exploration.

This property is applicable if the `Interact > offerserving > optimizationType` property for Unica Interact runtime is set to `BuiltInLearning` only.

Default value

95

Valid Values

An integer between 0 and 95 divisible by 5 or 99.

validateonDeployment**Description**

If set to `No`, Unica Interact does not validate the learning module when you deploy. If set to `Yes`, Unica Interact validates the learning module when you deploy.

Default value

No

Valid Values

Yes | No

maxAttributeNames**Description**

The maximum number of learning attributes the Unica Interact learning utility monitors.

This property is applicable if the `Interact > offerserving > optimizationType` property for Unica Interact runtime is set to `BuiltInLearning` only.

Default value

10

Valid Values

Any integer.

maxAttributeValues

Description

The maximum number of values the Unica Interact learning module tracks for each learning attribute.

This property is applicable if the `Interact > offerserving > optimizationType` property for Unica Interact runtime is set to `BuiltInLearning` only.

Default value

5

otherAttributeValue

Description

The default name for the attribute value used to represent all attribute values beyond the `maxAttributeValues`.

This property is applicable if the `Interact > offerserving > optimizationType` property for Unica Interact runtime is set to `BuiltInLearning` only.

Default value

Other

Valid Values

A string or number.

Example

If `maxAttributeValues` is set to 3 and `otherAttributeValue` is set to `other`, the learning module tracks the first three values. All of the other values are

assigned to the other category. For example, if you are tracking the visitor attribute hair color, and the first five visitors have the hair colors black, brown, blond, red, and gray, the learning utility tracks the hair colors black, brown, and blond. The colors red and gray are grouped under the `otherAttributeValue`, other.

percentRandomSelection

Description

The percent of the time the learning module presents a random offer. For example, setting `percentRandomSelection` to 5 means that 5% of the time (5 out of every 100 recommendations), the learning module presents a random offer, independent of the score. Enabling `percentRandomSelection` overrides the `offerTieBreakMethod` configuration property. When `percentRandomSelection` is enabled, this property is set regardless if learning is on or off or if built-in or external learning is used.

Default value

5

Valid Values

Any integer from 0 (which disables the `percentRandomSelection` feature) up to 100.

recencyWeightingFactor

Description

The decimal representation of a percentage of the set of data defined by the `recencyWeightingPeriod`. For example, the default value of .15 means that 15% of the data used by the learning utility comes from the `recencyWeightingPeriod`.

This property is applicable if the `Interact > offerserving > optimizationType` property for Unica Interact runtime is set to `BuiltInLearning` only.

Default value

0.15

Valid Values

A decimal value less than 1.

recencyWeightingPeriod**Description**

The size in hours of data granted the `recencyWeightingFactor` percentage of weight by the learning module. For example, the default value of 120 means that the `recencyWeightingFactor` of the data used by the learning module comes from the last 120 hours.

This property is applicable only if `optimizationType` is set to `builtInLearning`.

Default value

120

minPresentCountThreshold**Description**

The minimum number of times an offer must be presented before its data is used in calculations and the learning module enters the exploration mode.

Default value

0

Valid Values

An integer greater than or equal to zero.

enablePruning**Description**

If set to `yes`, the Unica Interact learning module algorithmically determines when a learning attribute (standard or dynamic) is not predictive. If a learning

attribute is not predictive, the learning module will not consider that attribute when determining the weight for an offer. This continues until the learning module aggregates learning data.

If set to `NO`, the learning module always uses all learning attributes. By not pruning non-predictive attributes, the learning module may not be as accurate as it could be.

Default value

Yes

Valid Values

Yes | No

Campaign | partitions | partition[n] | Interact | learning | learningAttributes | [learningAttribute]

These configuration properties define the learning attributes.

attributeName

Description

Each `attributeName` is the name of a visitor attribute you want the learning module to monitor. This must match the name of a name-value pair in your session data.

This property is applicable if the `Interact > offerserving > optimizationType` property for Unica Interact runtime is set to `BuiltInLearning` only.

Default value

No default value defined.

Campaign | partitions | partition[n] | Interact | deployment

These configuration properties define deployment settings.

chunkSize

Description

The maximum size of fragmentation in KB for each Unica Interact deployment package.

Default value

500

Availability

This property is applicable only if you have installed Unica Interact.

Campaign | partitions | partition[n] | Interact | serverGroups | [serverGroup]

These configuration properties define server group settings.

serverGroupName

Description

The name of the Unica Interact runtime server group. This is the name that appears on the interactive channel summary tab.

Default value

No default value defined.

Availability

This property is applicable only if you have installed Unica Interact.

Campaign | partitions | partition[n] | Interact | serverGroups | [serverGroup] | instanceURLs | [instanceURL]

These configuration properties define the Unica Interact runtime servers.

instanceURL

Description

The URL of the Unica Interact runtime server. A server group can contain several Unica Interact runtime servers; however, each server must be created under a new category.

Default value

No default value defined.

Example

```
http://server:port/interact
```

Availability

This property is applicable only if you have installed Unica Interact.

Campaign | partitions | partition[n] | Interact | flowchart

These configuration properties define the Unica Interact runtime environment used for test runs of interactive flowcharts.

serverGroup

Description

The name of the Unica Interact server group Unica Campaign uses to execute a test run. This name must match the category name you create under `serverGroups`.

Default value

No default value defined.

Availability

This property is applicable only if you have installed Unica Interact.

dataSource

Description

Use the `dataSource` property to identify the physical data source for Unica Campaign to use when performing test runs of interactive flowcharts.

This property should match the data source defined by the `Campaign` >

`partitions > partitionN > dataSources` property for the test run data source defined for Unica Interact design time.

Default value

No default value defined.

Availability

This property is applicable only if you have installed Unica Interact.

eventPatternPrefix

Description

The `eventPatternPrefix` property is a string value that is prepended to event pattern names to allow them to be used in expressions in Select or Decision processes within interactive flowcharts.

Note that if you change this value, you must deploy global changes in the interactive channel for this updated configuration to take effect.

Default value

`EventPattern`

Availability

This property is applicable only if you have installed Unica Interact.

Campaign | partitions | partition[n] | Interact | whiteList | [AudienceLevel]

These configuration properties define the default cell code under various special circumstances.

DefaultCellCode

Configuration category

`Campaign|partitions|partition[n]|Interact | whiteList | [AudienceLevel] | defaultOffers`

Description

The default cell code Unica Interact uses if you do not define a cell code in the default offers table.

You need to configure these properties only if you are defining global offer assignments.

Default value

No default value defined.

Valid Values

A string that matches the cell code format defined in Unica Campaign

Availability

This property is applicable only if you have installed Unica Interact.

DefaultCellCode

Configuration category

```
Campaign|partitions|partition[n]|Interact | whiteList |  
[AudienceLevel] | offersBySQL
```

Description

The default cell code Unica Interact uses for any offer in the OffersBySQL table(s) that has a null value in the cell code column (or if the cell code column is missing altogether. This value must be a valid cell code.

You need to configure these properties only if you are using SQL queries to get a desired set of candidate offers.

Default value

No default value defined.

Valid Values

A string that matches the cell code format defined in Unica Campaign

Availability

This property is applicable only if you have installed Unica Interact.

DefaultCellCode

Configuration category

```
Campaign|partitions|partition[n]|Interact | whiteList |
[AudienceLevel] | scoreOverride
```

Description

The default cell code Unica Interact uses if you do not define a cell code in the score override table.

You need to configure these properties only if you are defining individual offer assignments.

Default value

No default value defined.

Valid Values

A string that matches the cell code format defined in Unica Campaign

Availability

This property is applicable only if you have installed Unica Interact.

Campaign | partitions | partition[n] | Interact | eventPatterns

This configuration property is used when Unica Interact is integrated with Unica Interact Advanced Patterns.

enableAdvancedPatterns

Configuration category

```
Campaign|partitions|partition[n]|Interact|eventPatterns
```

Description

Set this value to **True** when Unica Interact is integrated with Unica Interact Advanced Patterns.

Default value

False

Availability

This property is applicable only if Unica Interact is integrated with Unica Interact Advanced Patterns.

Campaign | partitions | partition[n] | Interact | Simulator

These configuration properties define the server group you want to use to run API simulations.

serverGroup

Description

Specify the runtime server group that is used to run API simulations.

Default value

defaultServerGroup

Campaign | partitions | partition[n] | server | internal

Properties in this category specify integration settings and the internalID limits for the selected Unica Campaign partition. If your Unica Campaign installation has multiple partitions, set these properties for each partition that you want to affect.

internalIdLowerLimit

Configuration category

`Campaign|partitions|partition[n]|server|internal`

Description

The `internalIdUpperLimit` and `internalIdLowerLimit` properties constrain the Unica Campaign internal IDs to be within the specified range. Note that the values are inclusive: that is, Unica Campaign may use both the lower and upper limit.

Default value

0 (zero)

internalIdUpperLimit

Configuration category

`Campaign|partitions|partition[n]|server|internal`

Description

The `internalIdUpperLimit` and `internalIdLowerLimit` properties constrain the Unica Campaign internal IDs to be within the specified range. The values are inclusive: that is, Unica Campaign may use both the lower and upper limit. If Unica Collaborate is installed, set the value to 2147483647.

Default value

4294967295

eMessageInstalled

Configuration category

`Campaign|partitions|partition[n]|server|internal`

Description

Indicates that IBM eMessage is installed. When you select `Yes`, IBM eMessage features are available in the Unica Campaign interface.

The installer sets this property to `Yes` for the default partition in your IBM eMessage installation. For additional partitions where you installed IBM eMessage, you must configure this property manually.

Default value

No

Valid Values

Yes | No

interactInstalled

Configuration category

`Campaign|partitions|partition[n]|server|internal`

Description

After installing the Unica Interact design environment, this configuration property should be set to `Yes` to enable the Unica Interact design environment in Unica Campaign.

If Unica Interact is not installed, set to `No`. Setting this property to `No` does not remove Unica Interact menus and options from the user interface. To remove menus and options, you must manually unregister Unica Interact using the `configTool` utility.

Default value

No

Valid Values

Yes | No

Availability

This property is applicable only if you installed Unica Interact.

MO_UC_integration

Configuration category

`Campaign|partitions|partition[n]|server|internal`

Description

Enables integration with Unica Plan for this partition, if the integration is enabled in the **Platform** configuration settings. For more information, see the Unica Plan and Unica Campaign Integration Guide.

Default value

No

Valid Values

Yes | No

MO_UC_BottomUpTargetCells

Configuration category

`Campaign|partitions|partition[n]|server|internal`

Description

For this partition, allows bottom-up cells for Target Cell Spreadsheets, if **MO_UC_integration** is enabled. When set to `Yes`, both top-down and bottom-up target cells are visible, but bottom-up target cells are read-only. For more information, see the Unica Plan and Unica Campaign Integration Guide.

Default value

No

Valid Values

Yes | No

Legacy_campaigns

Configuration category

`Campaign|partitions|partition[n]|server|internal`

Description

For this partition, enables access to campaigns created before Unica Plan and Unica Campaign were integrated. Applies only if **MO_UC_integration** is set to `Yes`. Legacy campaigns also include campaigns created in Unica Campaign 7.x and linked to Plan 7.x projects. For more information, see the Unica Plan and Unica Campaign Integration Guide.

Default value

No

Valid Values

Yes | No

Unica Plan - Offer integration

Configuration category

`Campaign|partitions|partition[n]|server|internal`

Description

Enables the ability to use Unica Plan to perform offer lifecycle management tasks on this partition, if **MO_UC_integration** is enabled for this partition. Offer integration must be enabled in your **Platform** configuration settings. For more information, see the Unica Plan and Unica Campaign Integration Guide.

Default value

No

Valid Values

Yes | No

UC_CM_integration

Configuration category

`Campaign|partitions|partition[n]|server|internal`

Description

Enables Digital Analytics online segment integration for a Unica Campaign partition. If you set this value to `Yes`, the Select process box in a flowchart provides the option to select **Digital Analytics Segments** as input. To configure the Digital Analytics integration for each partition, choose **Settings > Configuration > Unica Campaign | partitions | partition[n] | Coremetrics**.

Default value

No

Valid Values

Yes | No

numRowsReadToParseDelimitedFile

Configuration category

Campaign|partitions|partition[n]|server|internal

Description

This property is used when mapping a delimited file as a user table. It is also used by the Score process box when importing a score output file from IBM SPSS Modeler Advantage Enterprise Marketing Management Edition. To import or map a delimited file, Unica Campaign needs to parse the file to identify the columns, data types (field types), and column widths (field lengths).

The default value of 100 means Unica Campaign examines the first 50 and the last 50 line entries in the delimited file. Unica Campaign then allocates the field length based on the largest value it finds within those entries. In most cases, the default value is sufficient to determine field lengths. However, in very large delimited files, a later field might exceed the estimated length that Unica Campaign computes, which can cause an error during flowchart runtime. Therefore, if you are mapping a very large file, you can increase this value to make Unica Campaign examine more line entries. For example, a value of 200 makes Unica Campaign examine the first 100 line entries and the last 100 line entries of the file.

A value of 0 examines the entire file. Typically, this is necessary only if you are importing or mapping files that have variable data widths of fields which cannot be identified by reading the first and last few lines. Reading the entire file for extremely large files can increase the required processing time for table mapping and Score process box runs.

Default value

100

Valid Values

0 (all lines) or any positive integer

Campaign | monitoring

Properties in the this category specify whether the Operational Monitoring feature is enabled, the URL of the Operational Monitoring server, and caching behavior. Operational Monitoring displays and allows you to control active flowcharts.

cacheCleanupInterval

Description

The `cacheCleanupInterval` property specifies the interval, in seconds, between automatic cleanups of the flowchart status cache.

This property is not available in versions of Unica Campaign earlier than 7.0.

Default value

600 (10 minutes)

cacheRunCompleteTime

Description

The `cacheRunCompleteTime` property specifies the amount of time, in minutes, that completed runs are cached and display on the Monitoring page.

This property is not available in versions of Unica Campaign earlier than 7.0.

Default value

4320

monitorEnabled

Description

The `monitorEnabled` property specifies whether the monitor is turned on.

This property is not available in versions of Unica Campaign earlier than 7.0.

Default value

FALSE

Valid values

TRUE | FALSE

serverURL

Description

The `Campaign > monitoring > serverURL` property specifies the URL of the Operational Monitoring server. This is a mandatory setting; modify the value if the Operational Monitoring server URL is not the default.

If Unica Campaign is configured to use Secure Sockets Layer (SSL) communications, set the value of this property to use HTTPS. For example:
`serverURL=https://host:SSL_port/Campaign/OperationMonitor` where:

- `host` is the name or IP address of the machine on which the web application is installed
- `SSL_Port` is the SSL port of the web application.

Note the `https` in the URL.

Default value

`http://localhost:7001/Campaign/OperationMonitor`

monitorEnabledForInteract

Description

If set to `TRUE`, enables Unica Campaign JMX connector server for Unica Interact. Unica Campaign has no JMX security.

If set to `FALSE`, you cannot connect to the Unica Campaign JMX connector server.

This JMX monitoring is for the Unica Interact contact and response history module only.

Default value

`FALSE`

Valid Values

TRUE | FALSE

Availability

This property is applicable only if you have installed Unica Interact.

protocol

Description

Listening protocol for the Unica Campaign JMX connector server, if `monitorEnabledForInteract` is set to yes.

This JMX monitoring is for the Unica Interact contact and response history module only.

Default value

JMXMP

Valid Values

JMXMP | RMI

Availability

This property is applicable only if you have installed Unica Interact.

port

Description

Listening port for the Unica Campaign JMX connector server, if `monitorEnabledForInteract` is set to yes.

This JMX monitoring is for the Unica Interact contact and response history module only.

Default value

2004

Valid Values

An integer between 1025 and 65535.

Availability

This property is applicable only if you have installed Unica Interact.

Unica Optimize configuration properties

This section describes the Unica Optimize configuration properties that are found on the **Configuration** page.

Starting Campaign 12.0, there is no separate listener for Optimize, since it is integrated into Campaign listener.

Non-clustered setup: If Optimize is installed on a different server, the configuration properties mentioned under Campaign|unicaACOListener are applicable for the listener.

Clustered or single host configuration : Properties under Campaign|unicaACLlistener are applicable for the listener.

Campaign | unicaACOListener

These configuration properties are for Unica Optimize listener settings.

serverHost

Description

Set to the host server name for the Unica Optimize installation.

Default value

localhost

serverPort

Description

Set to the host server port for the Unica Optimize installation.

Default value

none

useSSL

Description

Set to `True` to connect to the Unica Platform server by using SSL. Otherwise, set to `False`.

Default value

`False`

Valid Values

`True` | `False`

keepalive

Description

The number of seconds the Unica Campaign web application waits between sending messages to the Unica Optimize Listener to keep the connection active. Using `keepalive` keeps connections open if your network is configured to close inactive connections.

If set to `0`, the web application does not send any messages.

This `keepalive` property is separate from the Java™ socket `keepAlive`.

Default value

`0`

Valid Values

Positive integer

logProcessId

Description

Set to `yes` to log the ID of the Campaign listener process in the Campaign Listener log (`unica_aclsnr.log`, in the `logs` directory of your Campaign installation). Otherwise, set to `no`.

Default value

yes

Valid Values

yes | no

loggingLevels

Description

You can set the details for the Campaign listener data you log.

This setting affects the Campaign Listener log (`unica_aclsnr.log`, in the `logs` directory of your Campaign installation).

Default value

MEDIUM

Valid Values

LOW | MEDIUM | HIGH | ALL

logMaxFileSize

Description

Set this integer to the maximum size for a log file, in bytes. Unica Optimize creates a file after the log file reaches this size. This setting affects the Campaign Listener log (`unica_aclsnr.log`, in the `logs` directory of your Campaign installation).

Default value

20485760

enableLogging

Description

Set to `True` to enable logging. Otherwise, set to `False`. This setting affects the Unica Optimize Listener log (`unica_aclsnr.log`, in the `logs` directory of your Campaign installation).

Default value

True

Valid Values

True | False

logMaxBackupIndex

Description

Set this integer to the number of backup files to store. This setting affects the Campaign Listener log (`unica_aclsnr.log`, in the `logs` directory of your Campaign installation).

Default value

5

loggingCategories

Description

You can specify the categories of data you want to log in a comma-separated list. This setting affects the Campaign Listener log (`unica_aclsnr.log`, in the `logs` directory of your Campaign installation).

Default value

all

Valid Values

all | bad_order | cell_access | commands | config | data_errors | dbload | file_access | general | memory | procrun | query | sort | sysquery | table_access | table_io | table_mapping | webproc

defaultFilePermissions (UNIX™ only)

Description

The permission level for the generated log files in the numeric format. For example, `777` for read, write, and execute permissions.

Default value

660 (Owner and Group have read and write access only)

Campaign | unicaACOOptAdmin

These configuration properties define settings for the unicaACOOptAdmin tool.

getProgressCmd

Description

Specifies a value that is used internally. Do not change this value.

Default value

optimize/ext_optimizeSessionProgress.do

Valid Values

optimize/ext_optimizeSessionProgress.do

runSessionCmd

Description

Specifies a value that is used internally. Do not change this value.

Default value

optimize/ext_runOptimizeSession.do

Valid Values

optimize/ext_runOptimizeSession.do

loggingLevels

Description

The `loggingLevels` property controls the amount of detail that is written to the log file for the Unica Optimize command-line tool, which is based on severity. Available levels are LOW, MEDIUM, HIGH, and ALL, with LOW providing the least detail (that is, only the most severe messages are written). The ALL level includes trace messages and is intended primarily for diagnostic purposes.

Default value

HIGH

Valid Values

LOW | MEDIUM | HIGH | ALL

cancelSessionCmd**Description**

Specifies a value that is used internally. Do not change this value.

Default value

optimize/ext_stopOptimizeSessionRun.do

Valid Values

optimize/ext_stopOptimizeSessionRun.do

logoutCmd**Description**

Specifies a value that is used internally. Do not change this value.

Default value

optimize/ext_doLogout.do

Valid Values

optimize/ext_doLogout.do

getProgressWaitMS**Description**

Set this value to the number (integer) of milliseconds between two successive polls to the web application to get progress information. This value is not used if you do not set `getProgressCmd`.

Default value

1000

Valid Values

An integer greater than zero

Campaign | partitions | partition[n] | Optimize | sessionRunMonitor

These configuration properties are for sessionRunMonitor settings.

progressFetchDelay**Description**

Set this integer to the number of milliseconds that the web application waits before it obtains progress information from the listener.

Default value

250

Campaign | partitions | partition[n] | Optimize | MemoryTuning

These configuration properties are for the MemoryTuning settings.

MaxRamUsage**Description**

Defines the maximum memory in MB used to cache the contact history. This value must be at least as large as one contact history record.

Default value

128

Campaign | partitions | partition[n] | Optimize |
AgentTemplateTables

These configuration properties define template tables for Agent Capacity Optimization.

AgentInfoTemplateTables**Description**

Enter a comma-separated list of table names for the Agent Information Template Table. Each table contains the unique identification values (IDs) of agents and their capacity. These tables should be present in the Unica Campaign system database.

Default value

There is no default value defined.

AgentCustomerRelTemplateTables

Description

Enter a comma-separated list of table names for the Agent Customer Relationship Template Table. The Agent Customer Relationship table contains the unique identification values (IDs) of agents and the audience ID of associated customers. This table should be present in the Unica Campaign system database. The audience level of the audience ID must be the same as the audience level of your Unica Optimize session.

Default value

There is no default value defined.

Campaign | partitions | partition[n] | Optimize | userTemplateTables

This property defines the template tables that are used by the PCT and OCT.

tablenames

Description

Enter a comma-separated list of table names for the Unica Optimize template tables. These template tables can be used to add user-specific fields to the proposed contacts table (PCT) or the optimized contacts table (OCT).

Default value

UACO_UserTable

Campaign | partitions | partition[n] | Optimize | TestRun

This property defines the options to use for performing a test run of your Unica Optimize session.

TestRunSamplePercent

Description

The test run sample percentage is the percentage of customers to use from the PCT to perform a test run of your Unica Optimize session.

Default value

10

Valid values

1 - 100

Campaign | partitions | partition[n] | Optimize | AlgorithmTuning

These configuration properties define settings that you can use to tune your optimizations.

MaxAlternativesPerCustomerEvaluated

Description

The maximum number of times Unica Optimize tests combinations of proposed transactions, or alternatives, to find the optimal alternative for a customer.

For example, if the following are true:

- The offers that are associated with a customer in the proposed contacts table (PCT) are A,B,C,D, where the scores for these offers are A=8, B=4, C=2, D=1
- The MaxAlternativesPerCustomerEvaluated property is 5
- A rule of MAX # Offers=3 exists

Then, the alternatives that are tried might be as follows:

- ABC score = 14
- ABD score = 13
- AB score = 12
- ACD score = 11
- AC score = 10

Because the number of alternatives to test might be large, this value limits the effort the core algorithm spends on a customer before Unica Optimize moves to the next customer in the PCT.

Default value

1000

CustomerSampleSize**Description**

If your number of customers that are optimized is greater than `CustomerSampleSize`, Unica Optimize divides the customers into groups of no greater than `CustomerSampleSize`. Unica Optimize then optimizes each sample group separately. Rules that span across groups, such as a Custom Capacity rule, are still met. Increasing this number might increase optimality but hinder performance.

The most optimal `CustomerSampleSize` is equal to your number of customers. However, processing a large set of data might take a prohibitive amount of time. By dividing customers into smaller groups for Unica Optimize to process at a time, you can increase performance with minimal loss to optimality.

Default value

1000

Valid Values

Positive integer

MaxIterationsPerCustomerSample

Description

The maximum number of iterations Unica Optimize processes a group of customers. Unica Optimize processes a group of customers until optimality is reached or the number of iterations equals

`MaxIterationsPerCustomerSample`.

Search for the following information in the session log to observe the effect of setting changes for `MaxIterationsPerCustomerSample`.

- Maximum, minimum, and mean number of iterations per customer chunk
- Maximum, minimum, and mean number of alternatives that are created per customer
- Maximum, minimum, and mean number of alternatives that are tried per customer
- Standard deviation of iterations

Default value

1000

Valid Values

Positive integer

CustomerRandomSeed

Description

The random seed represents the starting point that Unica Optimize uses to select records randomly before Unica Optimize populates sample groups that are defined by the `CustomerSampleSize`. If you have fewer customers than `CustomerSampleSize`, this property has no effect on the optimization.

You might want to change the random seed if you think your current random sample produces highly skewed results.

Default value

1928374656

Valid Values

Positive integer

MaxCustomerSampleProcessingThreads

Description

The maximum number of threads Unica Optimize uses to process the optimization algorithms. In general, the higher you set `MaxCustomerSampleProcessingThreads`, the more you might improve performance. However, the performance increase is limited by several factors, including the type and number of optimization rules you use and your hardware. For detailed instructions on tuning your Unica Optimize implementation, contact your representative.

Default value

1

Valid Values

Positive integer

ProcessingThreadQueueSize

Description

The number of threads available to Unica Optimize to use to read a customer sample from the PCT. Increasing the number of threads might improve the performance of a Unica Optimize session. For detailed instructions on tuning your Unica Optimize implementation, contact your representative.

Default value

1

Valid Values

Positive integer

PostProcessingThreadQueueSize

Description

The number of threads available to Unica Optimize to write a customer sample to a staging table for the OCT. Increasing the number of threads might improve the performance of a Unica Optimize session. For detailed instructions on tuning your Unica Optimize implementation, contact your representative.

Default value

1

Valid Values

Positive integer

EnableMultithreading

Description

If true, Unica Optimize attempts to use multiple threads when processing the optimization algorithms. You can configure the number of threads with the `MaxCustomerSampleProcessingThreads`, `ProcessingThreadQueueSize`, and `PostProcessingThreadQueueSize` configuration properties. If false, Unica Optimize uses a single thread when processing the optimization algorithms.

Default value

True

Valid Values

True | False

EnableMaxCapacityConsumption

Description

If you get Unica Optimize results that underuse the channel capacities, enable `EnableMaxCapacityConsumption` to reduce the loss of channel capacity. Then, rerun the Unica Optimize session. If the parameter is set to true, Unica

Optimize uses an enhanced algorithm for trying to meet maximum constraints that are set in Cross Customer rules (Min/Max # Offers Capacity rule and Custom capacity rule). However, if this is used, the session run time might increase depending on the data that is provided to the session.

Default value

False

Valid Values

True | False

EnableBufferingHistoryTransactions**Description**

If true, Unica Optimize writes contact history transactions to a file to read during a Unica Optimize session run. If false, Unica Optimize reads from the `UA_ContactHistory` table in the Unica Campaign system tables.

If false, Unica Optimize creates a read lock on the `UA_ContactHistory` table for the length of the Unica Optimize session. This lock might cause attempts to write to the table to fail if you are using a database load utility. If true, Unica Optimize creates a read lock on the table only for the time it takes to write the query to a file.

Default value

False

Valid Values

True | False

MinImprovementPercent**Description**

Use this configuration property to stop processing a group of customers when the rate of optimization reaches a specified level. The `MinImprovementPercent` property sets a rate of score improvement, which is measured as a

percentage, to continue iterating. The default is zero, which means that there is no limit to the number of iterations possible.

Default value

0.0

UseFutureContacts**Description**

If you are not using time periods in any of your optimization rules, you can prevent Unica Optimize from querying the Contact History tables to improve performance. You can control this behavior with the `UseFutureContacts` configuration property.

If you set `UseFutureContacts` to false, and the optimization rules for your Unica Optimize session do not use time periods, Unica Optimize does not query the Contact History tables. This setting improves the time that is needed to run the Unica Optimize session. However, if the Unica Optimize session uses time periods, Contact History tables are queried.

If you record potential future contacts in Contact History, you must set `UseFutureContacts` to true. For example, if you know that you are sending an email communication next week about a special promotion to certain customers, those contacts might already be in the Contact History tables as placeholders. In this case, set `UseFutureContacts` to true and Unica Optimize always queries the Contact History tables.

Default value

False

Valid Values

True | False

ContinueOnGenerationLoopError**Description**

If `False`, Unica Optimize stops the Unica Optimize session if it is not possible to process a set of customers for the following reasons:

- The outer algorithm cannot satisfy the capacity rules with any of its alternate solutions.
- The core algorithm is not creating alternative solutions.

Unica Optimize logs this condition with the following error:

```
The generation loop was unable to eliminate all slack  
and surplus variables
```

If `True`, Unica Optimize skips all the customers in the set that triggered the generation loop error. Unica Optimize then continues processing the next customer set in the Unica Optimize session. It is possible that Unica Optimize might have violated some rules and generated this result without honoring all rules and data. If `Optimize|logging|enableBailoutLogging` property is also set to `TRUE`, the skipped customers are logged to `unprocessables_10-digit-session-ID.csv` in the `partition/partition[n]/logs` directory in the Unica Optimize installation directory. Customers skipped because of the generation loop error have the reason `SkippedOnGenerationLoopError`.

See the Unica Optimize Troubleshooting and Tuning Guide for details about how to avoid the generation loop error.

Default value

`False`

Valid Values

`True` | `False`

Campaign | partitions | partition[n] | Optimize | Debug

This property defines debug level for processing the PCT.

ExtraVerbose

Description

Set this value to `yes` to provide detailed logs on the rows that are processed in the proposed contacts table (PCT). By default, all rows are logged if you set this value to `yes`.

If you do not want processed rows of the PCT to be logged, set this value to `no`.

Default value

`no`

Valid Values

`yes` | `no`

Campaign | partitions | partition[n] | Optimize | DatabaseTuning

These configuration properties are for tuning the database.

UpdateSessionTableStatistics

Description

The `UpdateSessionTableStatistics` parameter adds a query for updating statistics of the PCT, RC, and POA tables during a Unica Optimize session run. You can tune this parameter at the session level without affecting other sessions. Keeping up-to-date index statistics can help improve the performance of the query on these tables. This parameter is also present in the global configuration settings of Unica Optimize.

Depending on your database, the method to write a query to update statistics varies.

Use following value to update statistics of DB2® tables:

```
CALL SYSPROC.ADMIN_CMD('RUNSTATS ON TABLE <TABLENAME>')
```



Note: If you use DB2® 8 or below, you must write your own custom stored procedure for implementing the functionality that is similar to `SYSPROC.ADMIN_CMD`. Also, you can write your own stored procedure to update statistics and start it through the `UpdateSessionTableStatistics` parameter at run time to update statistics.

Use the following value to update statistics of Oracle tables:

```
analyze table <TABLE> compute statistics
```

Use the following value to update statistics of SQL Server tables:

```
UPDATE STATISTICS <TABLE>
```



Important: If you run this query, the database user in `UA_SYSTEM_TABLES` must have privileges to run query, which is mentioned in this `UpdateSessionTableStatistics` parameter. For the session to run successfully, the correct value must be passed or left blank. If the value passed is incorrect, then the session run fails.

Default value

No default value defined.

AllowTempTables

Description

The `AllowTempTables` parameter creates temporary tables instead of database views, and populates them during the Unica Optimize session run. Enabling this parameter helps in improving run time performance of the Unica Optimize session run. For more information about this parameter, see [Optimize a transaction query for performance improvements in the Unica Optimize Troubleshooting and Tuning Guide](#).

Default value

True

Valid values

True | False

Campaign | partitions | partition[n] | Optimize | logging

This property defines logging settings for Unica Optimize.

logMaxBackupIndex**Description**

Set this integer to the number of backup files to store. This effects the Unica Optimize Server log (`unica_acosvr_SESSIONID.log` in the `partitions/partition[n]/logs` directory of your Campaign installation.).

Default value

5

logProcessId**Description**

Set to `True` to log the ID of the Unica Optimize server process in the Unica Optimize Server log (`unica_acosvr_SESSIONID.log` in the `partitions/partition[n]/logs` directory of your Campaign installation). Otherwise, set to `False`.

Default value

False

Valid Values

True | False

loggingCategories**Description**

You can specify the categories of data you want to log in a comma-separated list. This setting affects the Unica Optimize Server log (`unica_acosvr_SESSIONID.log` in the `partitions/partition[n]/logs` directory of your Campaign installation.).

Default value

all

Valid Values

all | bad_order | cell_access | commands | config | data_errors | dbload | file_access | general | memory | procrun | query | sort | sysquery | table_access | table_io | table_mapping | webproc

loggingLevels

Description

You can set the details for the server data you log.

This setting affects the Unica Optimize Server log

`unica_acosvr_SESSIONID.log` in the `partitions/partition[n]/logs` directory of your Campaign installation).

Default value

MEDIUM

Valid Values

LOW | MEDIUM | HIGH | ALL

enableBailoutLogging

Description

If set to `True`, Unica Optimize generates a separate file in comma-separated value (CSV) format. The CSV file contains details of customers Unica Optimize cannot process. Unica Optimize cannot process a customer if either of the following are true:

- Unica Optimize exceeds the limit that is set by `MaxAlternativesPerCustomerEvaluated`, and no legal alternatives are found for a customer.
- `ContinueOnGenerationLoopError` is set to `True` and Unica Optimize encounters a generation loop error.

Each row corresponds to one customer. The first column is the customer ID and the second column is the reason why Unica Optimize was not able to process the customer. The file is named `unprocessables_sessionID.csv` and is in the `partitions/partition[n]/logs` directory of your Campaign installation.

If set to `False`, Unica Optimize does not generate a list of customers that cannot be processed.

Default value

`False`

Valid Values

`True` | `False`

logMaxFileSize**Description**

Set this integer in bytes to the maximum size for a log file. Unica Optimize creates a file after the log file reaches this size. This setting affects the Unica Optimize Server log (`unica_acosvr_SESSIONID.log` in the `partitions/partition[n]/logs` directory of your Campaign installation.).

Default value

`10485760`

enableLogging**Description**

Set to `True` to enable logging. Otherwise, set to `False`. This setting affects the Unica Optimize Server log (`Optimize_installation_directory/partitions/partition[n]/logs/unica_acosvr_SESSIONID.log`).

Default value

`True`

Valid Values

`True` | `False`

defaultFilePermissions (UNIX™ only)

Description

The permission level for the generated log files in the numeric format. For example, `777` for read, write, and run permissions.

Default value

`660` (Owner and Group have read and write access only.)

Unica Collaborate configuration properties

This section describes the Unica Collaborate configuration properties on the configuration page.

Additional configuration properties exist in XML files that are located under the Unica Collaborate installation directory.

Collaborate | navigation

These configuration properties are for navigation settings.

welcomePageURI

Description

The Uniform Resource Identifier of the Unica Collaborate index page. You should not change this value.

Default Value

```
affiniumcollaborate.jsp?cat=home
```

projectDetailpageURI

Description

The Uniform Resource Identifier of the Unica Collaborate detail page. You should not change this value.

Default Value

```
uaprojectervlet?cat=projectabs&projecttype=CORPORATE&projectid=
```

seedName

Description

Used internally by the Unica Plan applications. You should not change this value.

Default Value

```
Collaborate
```

type

Description

Used internally by the Unica Plan applications. Do not change this value.

Default Value

```
Collaborate
```

httpPort

Description

The port number that is used by the application server for connections to the Unica Collaborate application.

Default Value

```
7001
```

httpsPort

Description

The port number that is used by the application server for secure connections to the Unica Collaborate application.

Default Value

7001

serverURL

Description

The URL of the Unica Collaborate installation.

If users access Unica Collaborate with the Chrome browser, use the fully qualified domain name (FQDN) in the URL. If the FQDN is not used, the Chrome browser cannot access the product URLs.

Default Value

`http://localhost:7001/collaborate`

displayName

Description

Used internally.

Default Value

Distributed Marketing

timeout_redirection

Description

Timeout URL displays. The Unica Collaborate logout page is displayed if empty.

Default Value

No default value is defined.

Collaborate | UDM Configuration Settings

These configuration properties are for Configuration settings.

serverType

Description

The type of web application server you are using. The valid values are `WEBLOGIC` or `WEBSPHERE`.

Default value

userManagerSyncTime

Description

Time in Milliseconds to sync with Unica Platform. The default value is equivalent to 3 hours.

Default value

`10800000`

showServerLiveClock

Description

This configuration parameter shows the server's clock and time zone information. If the value for this parameter is set to `True`, a message that contains the server time zone and a live clock that shows the server time is displayed on the Summary and Workflow tabs (in both view and edit modes), the Scheduler pop-up, and post-task pop-up pages of Lists, On-demand Campaigns, and Corporate Campaigns.

Default value

`False`

Valid value

`TRUE` | `FALSE`

firstMonthInFiscalYear

Description

The first month in the fiscal year. The default is 0 for January.

Default value

0

systemUserLoginName

Description

The login name of a Unica Platform user to be used for system tasks (for example, the system task monitor or the scheduler). It is recommended that the system user is not a normal Unica Collaborate user.

Default value

[CHANGE-ME]

searchModifiedTasksForSummaryFrequencyInSeconds

Description

How often, in seconds, to search for changes in task runs to refresh the Summary tab.

Default value

10

collaborateFlowchartStatusPeriod

Description

The period in milliseconds between two flowchart status checks.

Default value

100000

collaborateFlowchartStatusPeriodRunning

Description

The period in milliseconds between two flowchart status checks when the flowchart is running.

Default value

2000

enableEditProjectCode**Description**

If set to `true`, you can edit the List Code when on the **Summary** page of the New List wizard. If set to `false`, you cannot edit the List Code.

Default value

TRUE

Valid value

TRUE | FALSE

minimumDelayForExecutionMonitoring**Description**

Optional. Defines the minimum delay, in seconds, for an execution before it appears on the **Flowchart Runs Monitoring** page.

Default value

10800

validateAllWizardSteps**Description**

Determines whether Unica Collaborate checks required fields on non-visited wizard steps. Use this parameter to change behavior that occurs after you click Finish in the project wizard:

- `true`: Unica Collaborate checks all required fields on all non-visited wizard steps (except workflow, tracking, attachments) when creating a project by using the wizard. If there are any required fields blank, the wizard jumps to that page and displays an error message.
- `false`: Unica Collaborate does not check required fields on non-visited wizard steps.



Note: Unica Collaborate automatically checks the current page for blank requirement fields. This parameter controls whether Unica Collaborate checks all pages for blank required fields after you click Finish.

Default value

True

Valid value

TRUE | FALSE

Collaborate | UDM Configuration Settings | Attachment

These configuration properties are for Attachment settings.

collaborateModeForAttachments

Description

Unica Collaborate can get the attachments generated by flowchart execution from the Unica Campaign server through the following modes:

- Directory (the default)
- HTTP
- FTP
- TFTP
- SFTP

Default value

True

Valid value

True | False

collaborateAttachmentsDIRECTORY_directory**Description**

Indicates the address in the Unica Campaign server where Unica Collaborate takes the attachments if the mode is set to `Directory`, the default.

Default value

`\Affinium\Campaign\partitions\partition1`

collaborateAttachmentsDIRECTORY_deletefile**Description**

The value `True` indicates that the original files will be deleted after copy. The default is `false` if the mode is set to `Directory`.

Default value

False

Valid value

True | False

collaborateAttachmentsFTP_server**Description**

Indicates the server where Unica Collaborate takes the attachments if the mode is set to `FTP`.

Default value

No default value defined.

collaborateAttachmentsFTP_username

Description

Optional. Indicates the user name to log in on FTP server where Unica Collaborate takes the attachments if the parameter `collaborateModeForAttachments` is `FTP`.

Default value

No default value defined.

collaborateAttachmentsFTP_password

Description

Optional. Indicates the password to log in on FTP server where Unica Collaborate takes the attachments if the parameter `collaborateModeForAttachments` is `FTP`.

Default value

No default value defined.

collaborateAttachmentsFTP_account

Description

Optional. Indicates the account to log in on FTP server where Unica Collaborate takes the attachments if the parameter `collaborateModeForAttachments` is `FTP`.

Default value

No default value defined.

collaborateAttachmentsFTP_directory

Description

Optional. Indicates the directory on the FTP server from where Unica Collaborate takes the attachments if the parameter `collaborateModeForAttachments` is `FTP`. Accepts the relative path of the

directory regarding the FTP default directory from where Unica Collaborate can get the attachments for the Windows™ operating system.

Default value

No default value defined.

collaborateAttachmentsFTP_transfertype**Description**

Optional. Indicates the file transfer type on the FTP server that is used by Unica Collaborate to get the attachments if the parameter `collaborateModeForAttachments` is `FTP`. The value can be `ASCII` or `BINARY`. The default is `ASCII`.

Default value

No default value defined.

collaborateAttachmentsFTP_deletefile**Description**

Optional. The value `True` indicates that the original files will be deleted after copy. The default is `false` if the parameter `collaborateModeForAttachments` is `HTTP`.

Default value

No default value defined.

collaborateAttachmentsHTTP_url**Description**

Indicates the HTTP URL where Unica Collaborate takes the attachments if the parameter `collaborateModeForAttachments` is `HTTP`.

Default value

No default value defined.

collaborateAttachmentsHTTP_deletefile

Description

Optional. The value `True` indicates that the original files will be deleted after copy. The default is `false` if the parameter `collaborateModeForAttachments` is `HTTP`.

Default value

No default value defined.

collaborateAttachmentsTFTP_server

Description

Indicates the server where Unica Collaborate takes the attachments if the parameter `collaborateModeForAttachments` is `TFTP`.

Default value

No default value defined.

collaborateAttachmentsTFTP_port

Description

Optional. Indicates the port where Unica Collaborate takes the attachments if the parameter `collaborateModeForAttachments` is `TFTP`.

Default value

69

collaborateAttachmentsTFTP_transfertype

Description

Optional. Indicates the file transfer type on the server that is used by Unica Collaborate to get the attachments if the parameter `collaborateModeForAttachments` is `TFTP`. The valid values are `ASCII` or `BINARY`. The default is `ASCII`.

Default value

No default value defined.

collaborateAttachmentsSFTP_server

Description

SFTP server name (or IP).

Default value

No default value defined.

collaborateAttachmentsSFTP_port

Description

Optional. FTP server port.

Default value

22

collaborateAttachmentsSFTP_username

Description

User name to log in to the SFTP server.

Default value

No default value defined.

collaborateAttachmentsSFTP_password

Description

Optional. The SFTP password to log in to the SFTP server. It is used if it is needed by the server, and if `usepassword=true`.

Default value

No default value defined.

collaborateAttachmentsSFTP_usekey

Description

Optional. Use private key file for authenticate user.

Default value

False

Valid values

True | False

collaborateAttachmentsSFTP_keyfile

Description

Optional. SFTP key file name (used if it is needed by the server, and if usekey=true) to log in on SFTP server.

Default value

No default value defined.

collaborateAttachmentsSFTP_keypassphrase

Description

SFTP passphrase to log in on SFTP server. It is used if it is needed by the server, and if usekey=true.

Default value

No default value defined.

collaborateAttachmentsSFTP_knownhosts

Description

Optional. File name for known hosts (used if it is needed by server).

Default value

No default value defined.

collaborateAttachmentsSFTP_directory

Description

Optional. Accepts the relative path of the directory regarding the FTP default directory from where Unica Collaborate can get the attachments for the Windows™ operating system.

Default value

No default value defined.

collaborateAttachmentsSFTP_deletefile**Description**

Optional. Deletes original file after copy, if possible.

Default value

False

Valid values

True | False

mergeEnabled**Description**

Determines whether the merge of documents will be enabled:

- true: the merge is enabled (default).
- false: the merge is disabled.

Default value

True

Valid values

True | False

mergeFullWritePath**Description**

When the merge feature is enabled, this parameter specifies the full path to the merged data file on the local machine.

Default value

`c:/temp`

mergeDataLimitSize

Description

Indicates the upper limit for the size of the data to merge in Microsoft™ Word. The size is specified in rows (for example, a value of 100 indicates that the merged file cannot contain more than 100 rows). That is, if the number of rows in the file is greater than the value of this parameter, merge is not enabled for this file.

Default value

`1000`

validateFileUpload

Description

The `validateFileUpload` property is used to check whether your system validates the file types that are to be uploaded.

Default value

`False`

Valid values

`True | False`

upload_allowedFileTypes

Description

Indicates the types of files that can be uploaded in Unica Collaborate.

Default value

`doc ppt xls pdf gif jpeg png mpp`

upload_fileMaxSize

Description

Indicates the limit on the maximum size of the file that can be uploaded.

Default value

5000000

Collaborate | UDM Configuration Settings | Attachment Folders

These configuration properties are for Attachment Folders settings.

uploadDir

Description

The full path to the Unica Collaborate upload directories. Edit this path to include the full path to the Unica Collaborate upload directories. For example, `c:\DistributedMarketing\projectattachments`. If you are using UNIX™, confirm that Unica Collaborate users have permission to read, write, and run files in this directory.

Default value

`projectattachments`

taskUploadDir

Description

The full path to the Unica Collaborate task upload directories. Edit this path to include the full path to the Unica Collaborate upload directories. For example, `c:\DistributedMarketing\taskattachments`. If you are using UNIX™, confirm that Unica Collaborate users have permission to read, write, and run files in this directory.

Default value

`taskattachments`

Collaborate | UDM Configuration Settings | Campaign Integration

These configuration properties are for Unica Campaign Integration settings.

defaultCampaignPartition

Description

The default Unica Campaign partition. Unica Collaborate uses this parameter if you do not define the <campaign-partition-id> tag in a project template file.

Default value

`partition1`

defaultCampaignFolderId

Description

The default Unica Campaign folder ID. Unica Collaborate uses this parameter if you do not define the <campaign-partition-id> tag in a project template file.

Default value

`2`

Collaborate | UDM Configuration Settings | Datasource

These configuration properties are for data source settings.

jndiName

Description

Data source name for Unica Collaborate database.

Default value

`collaborateds`

asmJndiName

Description

Data source name for Unica Platform database, and is used only to synchronize users.

Default value

UnicaPlatformDS

Collaborate | UDM Configuration Settings | Flowchart

These configuration properties are for flowchart settings.

enableFlowchartPublishEvent**Description**

Specifies whether Unica Collaborate receives events that are sent by Unica Campaign when a flowchart is published.

Default value

True

flowchartRepublishOverwriteUserVarPrompt**Description**

Specifies whether the User Variable prompt is overwritten when a flowchart is republished.

Default value

False

flowchartRepublishOverwriteProcParamPrompt**Description**

Specifies whether the Process Parameter prompt is overwritten when a flowchart is republished.

Default value

False

flowchartServiceCampaignServicesURL

Description

The URL to the CampaignServices web service that should be used to run flowcharts, get flowchart data, and so on.

Default value

```
http://[server-name]:[server-port]/Campaign/services/  
CampaignServices30Service
```

flowchartServiceCampaignServicesTimeout

Description

The number of milliseconds Unica Collaborate waits for communications with the Unica Campaign services before it issues a timeout error.

Default value

```
600000
```

flowchartServiceNotificationServiceURL

Description

The URL to Unica Collaborate's notification service that receives notifications from Unica Campaign. You must set this parameter for Unica Collaborate to work.



Note: If you use a nonstandard context root, you must specify this parameter.

Default value

```
http://[server-name]:[server-port]/collaborate/  
flowchartRunNotifyServlet
```

flowchartServiceCampaignServicesAuthorizationLoginName

Description

A Unica Campaign user with administrative permissions, including access to all data sources, for example, asm_admin.

Default value

[CHANGE-ME]

flowchartServiceScheduleServices10Timeout**Description**

The number of milliseconds Unica Collaborate waits for communications with the Unica Platform scheduler before it issues a timeout error.

Default value

600000

flowchartServiceScheduleServices10MaxRetries**Description**

The number of times Unica Collaborate attempts to connect with the Unica Platform scheduler before it issues an error.

Default value

3

flowchartServiceScheduleServices10RetryPollPeriod**Description**

The number of seconds Unica Collaborate waits before it attempts to communicate with the Unica Platform scheduler again.

Default value

60

flowchartServiceScheduleServices10ThrottleType**Description**

The types of throttling for scheduled flowchart runs. The valid values are:

- 0: no throttling (throttle value is ignored)
- 1: throttle per flowchart instance
- 2: throttle all flowcharts (default)

Default value

2

flowchartServiceScheduleServices10ThrottleValue

Description

The maximum number of scheduled flowcharts or flowchart instances that can be run at one time.

Default value

10

flowchartServiceSchedulerMonitorPollPeriod

Description

Optional. Defines the approximate time, in seconds, for the scheduler monitor to sleep between polls.

Default value

10

flowchartServiceSchedulerMonitorRemoveSize

Description

Optional. Sets the number of jobs to try to remove from the queue in one shot. The scheduler monitor continues removing events from the event queue in increments that are specified by this value until none are left.

Default value

10

flowchartServiceIsAliveMonitorTimeout

Description

The duration, in seconds, to wait between the start of the flowchart execution and the periodic queries to Unica Campaign of the isAlive monitor.

Default value

900

flowchartServiceIsAliveMonitorMaxRetries

Description

The maximum number of queries that are sent to Unica Campaign by the isAlive monitor before it throws a flowchart run error.

Default value

10

flowchartServiceIsAliveMonitorPollPeriod

Description

The time, in seconds, to wait between queries that are made by the isAlive monitor to Unica Campaign.

Default value

600

Collaborate | UDM Configuration Settings | History

These configuration properties are for history settings.

enableRevisionHistoryPrompt

Description

Ensures that users are prompted to add change comments when they save a project or request or approval.

Default value

False

Valid values

TRUE | FALSE

runHistoryKeep_LIST

Description

Number of run history records to keep for a LIST project. If the value is ≤ 0 , Unica Collaborate keeps all run history records.

Default value

-1

runHistoryKeep_LOCAL

Description

Number of run history records (for a List or Unica Campaign flowchart) to keep a local project. If the value is ≤ 0 , Unica Collaborate keeps all run history records.

Default value

-1

runHistoryKeep_CORPORATE

Description

Number of run history records (for each run flowchart task) to keep for a corporate project. If the value is ≤ 0 , Unica Collaborate keeps all run history records.

Default value

-1

Collaborate | UDM Configuration Settings | Integration Services

These configuration properties are for the integrated services settings.

enableIntegrationServices

Description

This configuration property either enables or disables custom form validation.

Default value

integrationProcedureDefintionPath

Description

This configuration property specifies the location of the `procedure-plugins.xml`.

Default value

```
[udm-home]/devkits/integration/examples/src/procedure/procedure-plugins.xml
```

integrationProcedureClasspathURL

Description

This configuration property specifies the location of the compiled binary files of the custom validation classes that are defined in the `procedure-plugins.xml` file.

Default value

```
file://[udm-home]/devkits/integration/examples/classes/
```

Collaborate | UDM Configuration Settings | Listing Pages

These configuration properties are for list pages settings.

listItemsPerPage

Description

Specifies how many items (rows) to be displayed in one list page. This value should be greater than 0.

Default value

10

listPageGroupSize

Description

Specifies the size of visible page numbers in the list navigator in the list page. For example, pages 1-5 is a page group. This value should be greater than 0.

Default value

5

maximumItemsToBeDisplayedInCalendar

Description

The maximum number of objects the system displays on calendars. Use this parameter to restrict users' view of calendars to a specific number of objects. The setting of 0, the default, indicates that there is no restriction.

Default value

0

Collaborate | UDM Configuration Settings | List Manager

These configuration properties are for list manager settings.

listManagerEnabled

Description

Optional. Determines whether marketers can view the List Manager section on the Summary tab:

- true: the List Manager section displays (default)
- false: hides the List Manager section

If you disable the List Manager, you do not need to configure the List Manager configuration files.



Note: The data source to the List Manager table must be active to update the list size after generation.

Default value

True

Valid values

TRUE | FALSE

listManagerSearchscreenMaxrow**Description**

Indicates the maximum number of rows that are returned on the search screen.

Default value

1000

listManagerListPageSize**Description**

The number of rows that are displayed on a page in the List Manager.

Default value

20

listManagerListsMaxrow**Description**

The maximum number of rows that are displayed in a list.

Default value

No default value defined.

listManagerResetToValidatelsAllowed_list

Description

By default, when this property is set to `false`, you have the following actions when validating proposed contacts from a List:

- To Validate > Approved
- To Validate > Removed
- Added > Removed
- Approved > Removed
- Removed > Approved

If you set this property to `true`, you can also reset a selection if you made an error with the addition of the following actions:

- Removed > To Validate
- Approved > To Validate

Default value

`False`

Valid values

`TRUE` | `FALSE`

listManagerResetToValidatelsAllowed_local

Description

By default, when this property is set to `false`, you have the following actions when validating proposed contacts from an On-demand Campaign.

- To Validate > Approved
- To Validate > Removed
- Added > Removed
- Approved > Removed
- Removed > Approved

If you set this property to `true`, you can also reset a selection if you made an error with the addition of the following actions:

- Removed > To Validate
- Approved > To Validate

Default value

`False`

Valid values

`TRUE` | `FALSE`

listManagerResetToValidatelsAllowed_corporate

Description

By default, when this property is set to `false`, you have the following actions when validating proposed contacts from a Corporate Campaign list:

- To Validate > Approved
- To Validate > Removed
- Added > Removed
- Approved > Removed
- Removed > Approved

If you set this property to `true`, you can also reset a selection if you made an error with the addition of the following actions:

- Removed > To Validate
- Approved > To Validate

Default value

`False`

Valid values

`TRUE` | `FALSE`

Collaborate | UDM Configuration Settings | Lookup Cleanup

These configuration properties are for the lookup cleanup settings.

lookupCleanupMonitorStartDay

Description

Indicates the day when the unused lookup tables or views are automatically cleaned up. The parameter takes weekdays in terms of counts, such as Sunday = 1, Monday = 2. The frequency is weekly.

Default value

2

lookupCleanupMonitorStartTime

Description

Indicates the time when the unused lookup tables or views are automatically cleaned up. The frequency is weekly.

Default value

09:30 am

enableLookupCleanup

Description

When enabled, the lookup monitor runs according to the schedule specified in configuration.

Default value

Disabled

Collaborate | UDM Configuration Settings | Notifications

These configuration properties are for notification settings.

notifyCollaborateBaseURL

Description

The URL for Unica Collaborate. Edit this URL by entering the computer name where you installed Unica Collaborate and the port number you want to use.

Default value

```
http://[server-name]:[server-port]/collaborate/  
affiniumcollaborate.jsp
```

notifyDelegateClassName

Description

Optional. Specifies the fully qualified Java™ class name of the delegate implementation to be installed by the service.

Default value

No default value defined.

notifyIsDelegateComplete

Description

Indicates that the delegate implementation is complete.

Default value

```
true
```

Valid values

```
TRUE | FALSE
```

notifyEventMonitorStartTime

Description

Optional. Time to start the event monitor formatted according to the `java.text.DateFormat` class for the current locale, SHORT version. For example, in US English, the valid string is HH:MM A/PM. The default is set to start immediately after the monitor is created.

Default value

No default value defined.

notifyEventMonitorPollPeriod**Description**

Optional. Defines the approximate time, in seconds, for the event monitor to sleep between polls.

Default value

33

notifyEventMonitorRemoveSize**Description**

Optional. Defines the number of events to try to remove from queue in one shot.

Default value

10

Collaborate | UDM Configuration Settings | Notifications | Email

These configuration properties are for email settings.

notifyEmailMonitorJavaMailSession**Description**

Optional. Specifies the JNDI name of an existing initialized JavaMail™ Session to use for email notifications.

Default value

No default value defined.

notifyEmailMonitorJavaMailHost**Description**

The machine name or IP address of your organization's SMTP server.

Default value

[none]

notifyEmailMonitorJavaMailProtocol**Description**

Optional. Mail server transport protocol to use for email notifications.

Default value

smtp

notifyDefaultSenderEmailAddress**Description**

A valid email address for Unica Collaborate to use to send emails when there is otherwise no valid email address available to send notification emails.

Default value

[CHANGE-ME]

notifySenderAddressOverride**Description**

Optional. Email address to use for the REPLY-TO and FROM email addresses for notifications. By default, the event number owner's email address is used. If this parameter is not declared or an empty email address is provided, the default addresses are used.

notifyEmailMonitorStartTime**Description**

Optional. The time to start the email monitor formatted according to the `java.text.DateFormat` class for the current locale, SHORT version. For example, in US English, the valid string is HH:MM A/PM. The default is set to start immediately after monitor is created.

Default value

No default value defined.

notifyEmailMonitorPollPeriod

Description

Optional. Defines the approximate time, in seconds, for the email monitor to sleep between polls.

Default value

60

notifyEmailMonitorRemoveSize

Description

Optional. Defines the number of events to try to remove from queue in one shot.

Default value

10

notifyEmailMonitorMaximumResends

Description

Optional. Maximum number of times to try to resend an email after send problems are detected.

Default value

1440

emailMaximumSize

Description

Maximum size, in bytes, of an email.

Default value

2000000

Collaborate | UDM Configuration Settings | Notifications | Project

These configuration properties are for project settings.

notifyProjectAlarmMonitorStartTime

Description

Optional. Time to start the project alarm monitor. If not set, it will start immediately after the monitor is created.

Default value

10:00 pm

notifyProjectAlarmMonitorPollPeriod

Description

Optional. Defines approximate time, in seconds, for the project alarm monitor to sleep between polls.

Default value

86400

notifyProjectAlarmMonitorScheduleStartCondition

Description

Optional. The number of days before a project's start date when Unica Collaborate should start sending start notifications to users. If a project is pending and its start date is within the condition number of days in the future, a PROJECT_SCHEDULED_START notification will be sent out to the appropriate users. If the value is -1, then this condition is not checked for.

Default value

1

notifyProjectAlarmMonitorScheduleEndCondition

Description

Optional. The number of days before a project's end date when Unica Collaborate should start sending notifications to users. If a project is active and its end date is within the condition number of days in the future, a PROJECT_SCHEDULED_END notification will be sent out to the appropriate users. If the value is -1, then this condition is not checked for.

Default value

3

notifyProjectAlarmMonitorScheduleCutoffCondition**Description**

Optional. The number of days to start notifying users that a project is scheduled to be closed. If a project is active and its cutoff date is within the condition number of days in the future, a CORPORATE_CAMPAGN_TO_REVIEW notification will be sent out to the appropriate users. If the value is -1, then this condition is not checked for.

Default value

3

notifyProjectAlarmMonitorTaskScheduledStartCondition**Description**

Optional. The number of days before a task's start date when Unica Collaborate should start sending notifications to users. If a task is pending and its start date is within the condition number of days in the future, a TASK_SCHEDULED_START notification will be sent out to the appropriate users. If the value is -1, then this condition is not checked for.

Default value

1

notifyProjectAlarmMonitorTaskScheduledEndCondition**Description**

Optional. The number of days before a task's start date when Unica Collaborate should start sending notifications to users that a task did not start. If a task is active and its end date is within the condition number of days in the future, a TASK_SCHEDULED_END notification will be sent out to the appropriate users. If the value is -1, then this condition is not checked for.

Default value

3

notifyProjectAlarmMonitorTaskLateCondition**Description**

Optional. The number of days after a task's start date when Unica Collaborate should start sending notifications to users that a task did not start. If a task is pending and its scheduled start date is within the condition number of days in the past, a TASK_LATE notification is sent out to the appropriate users. If the value is -1, then this condition is not checked for.

Default value

3

notifyProjectAlarmMonitorTaskOverdueCondition**Description**

Optional. The number of days after a task's end date when Unica Collaborate should be notifying users that a task did not finish. If a task is active and its scheduled end date is within the condition number of days in the past, a TASK_OVERDUE notification is sent out to the appropriate users. If the value is -1, then this condition is not checked for.

Default value

3

notifyProjectAlarmMonitorTaskScheduledMilestoneCondition**Description**

Optional. The number of days before a task milestone's start date when Unica Collaborate should start sending notifications to users. If a milestone task is active and its scheduled end date is within the condition number of days in the future, a TASK_SCHEDULED_MILESTONE notification will be sent out to the appropriate users. If the value is `-1`, then this condition is not checked for.

Default value

1

Collaborate | UDM Configuration Settings | Notifications | System Task

These configuration properties are for system task settings.

systemTaskMonitorStartTime

Description

Optional. The time to start the system task monitor.

- If this parameter contains a value (for example, `11:00 pm`), this is the start time for the task monitor to start.
- If this parameter is undefined, the monitor starts immediately after it is created.

Default value

3

systemTaskMonitorPollPeriod

Description

Optional. The duration, in seconds, for the system task monitor to sleep between polls.

Default value

3600

Collaborate | UDM Configuration Settings | Performance

These configuration properties are for performance settings.

commonDataAccessLayerFetchSize

Description

This parameter is a performance optimization that sets the batch size of some performance-sensitive queries. The fetch size is used to determine how many records in the result set are returned to the application at one time.

Default value

500

commonDataAccessLayerMaxResultSetSize

Description

This parameter crops all list page results that are longer than the specified value.

Default value

1000

ssdorSearchResultLimit

Description

The maximum number of rows that are returned by the SSDOR search screen. Increasing this number to a high value may degrade performance.

Default value

500

Collaborate | UDM Configuration Settings | Read Only Lookup Tables

These configuration properties are for lookup table settings.

lookupTableName

Description

Optional. A read-only lookup table name. The lookup table name can include a wildcard, an asterisk (*), at the end of the name. The lookup table is not updated in the Form Editor when a flowchart is republished.

Default value

No default value defined.

New category name

Description

Optional. A template for adding a list of lookup tables to not update during a form merge. When you republish a flowchart, if any attributes in the form are associated with the lookup table, the lookup table and its contents are not updated.

Default value

No default value defined.

Collaborate | UDM Configuration Settings | Reports

These configuration properties are for reports settings.

reportsAnalysisSectionHome

Description

Indicates the home directory for the Analysis Section reports.

Default value

```
/content/folder[@name='Affinium Collaborate']
```

reportsAnalysisTabHome

Description

Indicates the home directory for the object (Corporate Unica Campaign, List, or On-demand Unica Campaign) Analysis Tab reports.

Default value

```
/content/folder[@name='Affinium Collaborate - Object Specific Reports']
```

reportsAnalysisCorporateSectionHome

Description

Indicates the home directory for the corporate marketer Analysis Section reports.

Default value

```
/content/folder[@name='Affinium Collaborate']
```

reportsAnalysisCorporateTabHome

Description

Indicates the home directory for corporate marketer object (Corporate Unica Campaign, List, or On-Demand Unica Campaign) Analysis Tab reports.

Default value

```
/content/folder[@name='Affinium Collaborate - Object Specific Reports']/folder[@name='Corporate Marketer']
```

reportsAnalysisFieldMarketerSectionHome

Description

Indicates the home directory for the field marketers Analysis Section reports.

Default value

```
/content/folder[@name='Affinium Collaborate']/folder[@name='Field Marketer']
```

reportsAnalysisFieldTabHome

Description

Indicates the home directory for the field marketer object (Corporate Unica Campaign, List, or On-Demand Unica Campaign) Analysis tab reports.

Default value

```
/content/folder[@name='Affinium Collaborate - Object Specific Reports']/folder[@name='Field Marketer']
```

Collaborate | UDM Configuration Settings | Siblings

These configuration properties are for sibling settings.

siblingService

Description

Optional. Used to build links to other Unica Collaborate instances to propagate events.

Default value

```
http://[server-name]:[server-port]/collaborate/services/  
CollaborateIntegrationServices/1.0
```

New category name

Description

Optional. A template for giving the URLs specification for the sibling URLs service for the current base instance of Unica Collaborate. Used to build links to other Unica Collaborate instances to propagate events. For example, <http://collaborateserver:7001/collaborate/services/CollaborateIntegrationServices/1.0>. Do not specify sibling URLs if this configuration file is not the file of the Unica Collaborate base instance.

Default value

No default value defined.

Collaborate | UDM Configuration Settings | Templates

These configuration properties are for template settings.

templatesDir

Description

The directory that contains all your templates. As a best practice, set this to the full path to `IBM-Home\DistributedMarketing\templates`.

Default value

`templates`

projectTemplatesFile

Description

The specified file describes the various projects: List, On-demand Campaign, and Corporate Campaign.

Default value

`project_templates.xml`

templateAutoGenerateNameEnabled

Description

Indicates whether the template name for a new template must be generated or not.

Default value

`True`

Valid values

`True | False`

defaultListTableDSName

Description

Used to assign the data source name for templates while importing template if the data source name is not defined.

Default value

ACC_DEMO

templateAdminGroup_Name

Description

Specifies multiple groups. Users belonging to these groups have access to template configuration links in Unica Collaborate. Groups with the same name must exist in the Unica Platform. Multiple groups should be separated by commas.

Default value

Template Administrators

Collaborate | UDM Configuration Settings | Workflow

These configuration properties are for workflow settings.

daysInPastRecentTask

Description

How many days in the past Unica Collaborate looks for recent tasks.

Default value

14

daysInFutureUpcomingTasks

Description

How many days in the future Unica Collaborate looks for recent tasks.

Default value

14

beginningOfDay

Description

Indicates the beginning hour of the working day with the valid values representing midnight to noon. This setting is used as the denominator when calculating a percentage of task completion in workflows.

Default value

9

Valid values

0 - 12

numberOfHoursPerDay

Description

Indicates the number of hours per day. The default indicates a standard, eight-hour work day. This setting is used as the denominator when calculating a percentage of task completion in workflows.

Default value

8

Valid values

0 - 24

automaticallyRestartFailedRecurrentTasks

Description

Decides whether to automatically restart the failed recurrent tasks. If the value of parameter is set to false, users must manually update the failed task status to Pending either from workflow or from post-task update pop. The schedule picks up only those tasks for runs that are in pending state.

If the value is set to `True`, no manual intervention is required to restart this task.

Default value

True

Valid values

True | False

projectWorkflowRefreshPeriodInSeconds

Description

System-wide workflow refresh period, in seconds.

Default value

180

IBM SPSS Modeler Advantage Enterprise Marketing Management Edition configuration properties

Properties in this category specify values that are used to configure Unica for single sign-on with IBM SPSS Modeler Advantage Enterprise Marketing Management Edition.

See the Unica Campaign and IBM SPSS Modeler Advantage Enterprise Marketing Management Edition Integration Guide for complete instructions on setting up single sign-on with IBM SPSS Modeler Advantage Enterprise Marketing Management Edition.

SPSS® | integration

Properties in this category are used to configure Unica Platform for single sign-on with IBM SPSS Modeler Advantage Enterprise Marketing Management Edition.

Platform user for IBM® SPSS® account

Description

Enter the login name for the IBM SPSS Modeler Advantage Enterprise Marketing Management Edition account that you created or identified for single sign-on with IBM SPSS Modeler Advantage Enterprise Marketing Management Edition.

Default value

asm_admin

Availability

This property is used only to configure Unica Platform for single sign-on with IBM SPSS Modeler Advantage Enterprise Marketing Management Edition.

Datasource for IBM® SPSS® account**Description**

Set this property to the name of the data source you created for the system user when you configured single sign-on with IBM SPSS Modeler Advantage Enterprise Marketing Management Edition. If you used **SPSS_MA_ADMIN_DS** as the data source name, you can retain the default value of this property.

Default value

SPSS_MA_ADMIN_DS

Availability

This property is used only to configure Unica Platform for single sign-on with IBM SPSS Modeler Advantage Enterprise Marketing Management Edition.

Is this score only integration**Description**

Not supported.

Default value

FALSE

Availability

This property is used only to configure Unica Platform for single sign-on with IBM SPSS Modeler Advantage Enterprise Marketing Management Edition.

SPSS® | integration | partitions | partition [n]

The property in this category is used to configure Unica Platform for single sign-on with IBM SPSS Modeler Advantage Enterprise Marketing Management Edition.

Enable IBM® SPSS®

Description

Set this property to `TRUE` to enable single sign-on with IBM SPSS Modeler Advantage Enterprise Marketing Management Edition.

For each partition where you have users who should have single sign-on, you must use the **SPSS MA EMM Edition | Integration | partitions | partitionTemplate** to create the **enableSPSS** configuration property for that partition. The name of the category you create with the template must exactly match the name of the corresponding Campaign partition. The default partition1 already has the **Enable IBM SPSS** configuration property, so you do not have to use the template to create it.

Default value

`FALSE`

Availability

This property is used only to configure Unica Platform for single sign-on with IBM SPSS Modeler Advantage Enterprise Marketing Management Edition.

SPSS® | navigation

Properties in this category affect IBM SPSS Modeler Advantage Enterprise Marketing Management Edition integration with Unica Campaign. These properties define the location of the Decision Management server and the IBM SPSS Collaboration and Deployment Services server.

IBM® SPSS® Decision Management Server URL

Description

The URL for the SPSS® decision management server. Configure this URL with server name or server IP address followed by the port on which IBM SPSS Modeler Advantage Enterprise Marketing Management Edition is hosted on the server.

Default value

One of the following formats:

- `http://<server name>:<port>/DM`
- `http://<server IP address>:<port>/DM`

Valid values

The URL for the SPSS® decision management server.

C&DS Server**Description**

The name of the IBM SPSS Collaboration and Deployment Services server.

Default value

None

Valid values

Valid server name or server IP address on which IBM SPSS Collaboration and Deployment Services is installed and configured.

C&DS Port**Description**

The port where the IBM SPSS Collaboration and Deployment Services server is located.

Default value

None

Valid values

Valid port number on which IBM SPSS Collaboration and Deployment Services is hosted.

Opportunity Detect and Unica Interact Advanced Patterns configuration properties

This section describes the Opportunity Detect and Unica Interact Advanced Patterns configuration properties on the Configuration page.

Opportunity Detect and Interact Advanced Patterns | Navigation

Properties in this category specify values that are used internally to navigate among Unica products.

welcomePageURI

Description

The Uniform Resource Identifier of the Opportunity Detect index page. This value is used internally by Unica applications. Changes to this value are not recommended.

Default value

`/index.jsp`

seedName

Description

Used internally by Unica applications. Changes to this value are not recommended.

Default value

`Detect`

type

Description

Used internally by Unica applications. Changes to this value are not recommended.

Default value

Detect

httpPort**Description**

The port number that is used by the application server for connections to the Opportunity Detect application.

Default value

7001

httpsPort**Description**

The port number that is used by the application server for secure connections to the Opportunity Detect application.

Default value

7001

serverURL**Description**

The URL of the Opportunity Detect installation. Accepts either the HTTP or HTTPS protocol. If you are on a clustered environment and choose to use ports that are different from the default ports 80 or 443 for your deployment, do not use a port number in the value of this property.

If users access Opportunity Detect with the Chrome browser, use the fully qualified domain name (FQDN) in the URL. If the FQDN is not used, the Chrome browser cannot access the product URLs.



Important: If Unica products are installed in a distributed environment, you must use the machine name rather than an IP address in the navigation URL for all of the applications in the suite.

Default value

[server-url]

logoutURL

Description

Used internally. Changes to this value are not recommended.

Unica Platform uses this value to call the logout handler of each registered application if the user clicks the logout link in Unica.

serverURLInternal

Description

Used internally. Changes to this value are not recommended.

displayName

Description

Used internally. Changes to this value are not recommended.

Default value

Opportunity Detect

Opportunity Detect and Interact Advanced Patterns | System | Streams Remote Control Web Service

The property in this category specifies the URL for the InfoSphere Streams remote control web service. Opportunity Detect Design Time communicates with Opportunity Detect Run Time over this service.

ServerURL

Description

The person who installs the product sets this property value during installation. The default port number is 8080.

Default value

```
http://[SRCSTHost]:[SRCSPort]/axis2/services/RemoteControl
```

Opportunity Detect and Interact Advanced Patterns | System | Real Time Connector

The property in this category specifies the URL for the web service used when Unica Interact is integrated with Unica Interact Advanced Patterns or when the Web Service connector is used for input data.

ServerURL

Description

The person who installs the product sets this property value during installation. The default port number is 8282.

Default value

```
http://[RealTimeConnectorHost]:[RealTimeConnectorPort]/servlets/StreamServlet
```

Opportunity Detect and Interact Advanced Patterns | System | Monitoring

Properties in this category specify values that affect the monitoring tool.

Poll Interval (In Seconds)

Description

The number of seconds that the monitoring service waits between two successive polls of the Streams server for the statistics. The default is 300 seconds, or 5 minutes.

Default value

300

Retaining Time (In Days)

Description

The number of days the monitoring service should keep the polled data in the database. The default is 10 days. Data that is older than the time specified here is purged.

Default value

10

Opportunity Detect and Interact Advanced Patterns | System | Processing Options

Properties in this category specify values that affect the monitoring tool.

Cache profile records

Description

Opportunity Detect can cache profile data, which provides optimal performance. To enable caching of profile data, set the value of this property to `True`.

If you have very large profile data sets, you might want to retain the default value of this property, which is `False`. This disables caching of profile data and eliminates the out of memory issues that caching large amounts of profile data can cause.

If you change this property value, you must restart your web application server, the Streams instance, and the StreamsRCS service, and redeploy all affected deployments.

Default value

`False`

Opportunity Detect and Interact Advanced Patterns | logging

The property in this category specifies the location of the Opportunity Detect log file.

log4jConfig

Description

The location of the configuration file that Opportunity Detect uses for logging. This value is set automatically during installation, but if you change this path, you must restart the web application server to apply the change.

Default value

```
[absolute-path]/conf/detect_log4j.properties
```

Unica Interact Advanced Patterns | System | Interact Design Service

The property in this category specifies the URL for the web service that allows Interact to automatically create and deploy advanced patterns when Unica Interact is integrated with Unica Interact Advanced Patterns.

ServerURL

Description

This web service is the integration point between Unica Interact and Unica Interact Advanced Patterns design time. The person who installs the product sets this property value during installation. The default port number is 8181.

Default value

```
http://[InteractServiceHost]:[InteractServicePort]/axis2/services/  
InteractDesignService
```

Here are the configuration properties laid down by the Installer.

Birt | navigation

The Unica suite integrates with BIRT to generate reports.

This page displays properties that specify URLs and other parameters that are used by the BIRT system.

Seed Name

Description

Used internally by HCL Unica applications. Changes to this value are not recommended.

Default value

Birt

httpPort

Description

This property specifies the port used by the BIRT web application server. If your installation of Birt uses a port which is different from the default, you must edit the value of this property.

Default value

7001

httpsPort

Description

If SSL is configured, this property specifies the port used by the Birt web application server for secure connections. If your installation of BIRT uses a secure port that is different from the default, you must edit the value of this property.

Default value

7001

serverURL

Description

Specifies the URL of the Birt web application. Use a fully qualified host name, including the domain name (and subdomain, if appropriate) specified in the Domain property. For example: `http://MyReportServer.MyCompanyDomain.com:7001/hcl-birt`

Default value

```
http://[CHANGE ME]/hcl-birt
```

Valid values

A well-formed URL

logoutURL

Description

The logoutURL property is used internally to call the logout handler of the registered application if the user clicks the logout link. Do not change this value.

Default value

```
/j_spring_security_logout
```

Enabled

Description

Setting the value to `TRUE` ensures that BIRT will be used as reporting engine.



Note: If you are upgrading to V 12.0 and you have Campaign/Plan/Interact Reports pack and Unica Platform installed, then you can either see Cognos Reports or BIRT reports.

Default value

False

Valid values

FALSE | TRUE

Currently, Birt reports are supported for Oracle, SQL Server, and DB2 databases.

Customization of stylesheets and images in the Unica user interface

You can customize the appearance of the user interface where most Unica product pages appear. By editing a cascading style sheet and providing your own graphics, you can change many of the images, fonts, and colors in the user interface.

This is sometimes called re-branding, because you can override the HCL logo and color scheme with your company's logo and color scheme.

Stylesheets

The HTML frameset is formatted by a number of cascading style sheets, located in the `css` directory within the `unica.war` file. Several of these stylesheets import a stylesheet named `corporatetheme.css` in the `css\theme` directory. By default, this `corporatetheme.css` file is blank. When you replace this blank file with one that uses your colors and images, you change the appearance of the frameset.

also provides an example `corporatetheme.css` file, in the `css\theme\DEFAULT` directory within the `unica.war` file. This example stylesheet contains all of the specifications that are customizable, along with comments that explain what areas of the frameset each specification affects. You can use this file as a template for making your own changes, as described in the instructions in this section.

Images

Your images can be PNG, GIF, or JPEG format.

uses sprites for some of its buttons and icons. Using sprites reduces the number of HTTP requests going to the server, and can reduce possible flickering. Where uses sprites, the name of the image includes `_sprites`. If you want to replace these images, you should use sprites with the same dimensions, as this requires the fewest modifications to the stylesheet. If you are not familiar with sprites, you can learn about them on the internet.

Preparing your corporate theme

Follow these guidelines to create your corporate theme for the Unica frameset.

1. When you installed Unica Platform, you may have created an EAR file containing the `unica.war` file, or you may have installed the `unica.war` file. In either case, extract your installed file as necessary to access the files and directories the `unica.war` file contains.
2. Locate the `corporatetheme.css` file, located under in the `css\theme\DEFAULT` directory.
3. See the comments in the `corporatetheme.css` file for details on which area of the framework each stylesheet specification affects.
4. See the images in the `css\theme\img` directory to guide you in creating your images.
5. Create your theme in your preferred graphics program and make a note of the image names, fonts, and hexadecimal specifications for the font and background colors.
6. Edit the `corporatetheme.css` file to use your fonts, colors, and images.

Applying your corporate theme

Follow this procedure to apply your corporate theme to the Unica user interface.

1. Place the images you want to use (for example, your logo, buttons, and icons) in a directory accessible from the machine where Unica Platform is installed. Refer to the modified `corporatetheme.css` file, created as described in a "Preparing your corporate theme," to determine where to place your images.
2. If Unica Platform is deployed, undeploy it.

3. When you installed Unica Platform, you may have created an EAR file containing the `unica.war` file, or you may have installed the `unica.war` file. In either case, do the following.
 - Make a backup of your WAR or EAR file, saving the backup with a different name (for example, `original_unica.war`). This enables you to roll back your changes if necessary.
 - Extract your installed file as necessary to access the files and directories the `unica.war` contains.
4. Place the modified `corporatetheme.css` file, created as described in "Preparing your corporate theme," in the `css\theme` directory.

This overwrites the blank `corporatetheme.css` file that is already there.
5. Re-create the `unica.war` file, and, if necessary, the EAR file that contained it.
6. Deploy the WAR or EAR file.
7. Clear your browser cache and log in to Unica.

Your new theme should be applied.

Adding internal user accounts

Use this procedure to add internal user accounts.

1. Click **Settings > Users**.
2. Click **New user**.
3. Complete the form and click **Save changes**.

Use caution if you employ special characters in login names. Allowed special characters are listed in the New user page reference.

4. Click **OK**.

The new user name appears in the list.

Deleting internal user accounts

Use this procedure to delete internal user accounts.



Important: If Unica Campaign permissions are set up in a way that restricts ownership or access to a Unica Campaign object to a single user, deleting the account of that user makes the object inaccessible. Instead, you should disable rather than delete such accounts.

1. Click **Settings > Users**.
2. Click the user name of the account you want to delete.
3. Click **OK**.

Changing internal user password expiration dates

Use this procedure to change password expiration dates for internal users.



Restriction: If the system-wide password expiration property **General | Password settings | Validity (in days)** is set to zero, you cannot change the password expiration date of any internal user.

1. Click **Settings > Users**.
2. Click the user name.
3. Click the **Edit properties** link at the bottom of the page.
4. Change the date in the **Password expiration** field.
5. Click **OK**.

Resetting internal user passwords

Use this procedure to reset internal user passwords.

1. Click **Settings > Users**.

The **Users** list is displayed in the left pane.

2. Click the user name you want to change.
3. Click the **Reset password** link at the bottom of the page.

4. Enter the new password in the **Password** field.
5. Enter the same password in the **Confirm** field.
6. Click **Save changes** to save your changes.
7. Click **OK**.



Note: When user passwords are reset, users are prompted to change their password the next time they log in to an Unica application.

Adding internal user data sources

Use this procedure to add data sources for internal users.

1. Click **Settings > Users**.
2. Click the name of the account you want to change.
3. Click the **Edit data sources** link at the bottom of the page.
4. Click **Add new**.
5. Complete the form and click **Save changes** to save your changes.
6. Click **OK**.

Changing internal user account properties

Use this procedure to change the properties of internal user account.

1. Click **Settings > Users**.
2. Click the name of the account you want to change.
3. Click the **Edit properties** link at the bottom of the page.
4. Edit the fields as needed.
5. Click **Save changes** to save your changes.
6. Click **OK**.

Changing internal user system status

Use this procedure to change the system status of internal users.

1. Click **Settings > Users**.
2. Click the name of the account you want to change.
3. Click the **Edit properties** link at the bottom of the page.
4. Select the status in the **Status** drop-down list. The options are **ACTIVE** and **DISABLED**.



Note: If you select **DISABLED**, the user will no longer be able to log in to any Unica applications. Users with Admin access to Unica Platform cannot disable themselves.

5. Click **Save changes** to save your changes.
6. Click **OK**.

Deleting internal user data sources

Use this procedure to delete internal user data sources.

1. Click **Settings > Users**.
2. Click the name of the account you want to change.
3. Click the **Edit Data Sources** link at the bottom of the page.
4. Click the name of the data source you want to delete.
5. Click **Delete**.
6. Click **OK**.

The user management pages

Refer to this table if you need help completing the fields on the Users page.

The New user page

Table 81. Fields on the New user page

Field	Description
First name	The user's first name.
Last name	The user's last name.
Login	<p>The user's login name. This is the only required field. Only the following special characters are allowed in login names.</p> <ul style="list-style-type: none"> • Upper and lower case alphabetic characters (A-Za-z) • Numbers (0-9) • The 'at' sign (@) • Hyphen (-) • Underscore (_) • Dot (.) • Double byte characters (such as Chinese characters) <p>Do not include other special characters (including spaces) in the login name.</p>
Password	<p>A password for the user. Follow these rules when creating a password.</p> <ul style="list-style-type: none"> • Passwords are case-sensitive. For example, <code>password</code> is not the same as <code>Password</code>. • You may use any character when you create or reset a password in Unica. <p>Additional password requirements are set on the Configuration page. To see what they are for your installation of Unica, click the Password Rules link next to the Password field.</p>
Confirm password	The same password you entered in the Password field.

Table 81. Fields on the New user page (continued)

Field	Description
Title	The user's title.
Department	The user's department.
Company	The user's company.
Country	The user's country.
Address	The user's address.
Work phone	The user's work phone number.
Mobile phone	The user's mobile phone number.
Home phone	The user's home phone number.
Email address	The user's email address. This field must conform to email addresses as defined in RFC 821. See RFC 821 for details.
Alternate login	The user's UNIX™ login name, if one exists. An alternate login is typically required when the Unica Campaignlistener runs as root on a UNIX™-type system.
Status	Select ACTIVE or DISABLED from the drop-down list. ACTIVE is selected by default. Disabled users are prevented from logging in to all Unica applications.

The Edit properties page

The fields are the same as the fields on the New user page, except for the ones shown in the following table.

Table 82. Fields on the Edit properties page

Field	Description
Password	This field is not available on the Edit properties page.

Table 82. Fields on the Edit properties page (continued)

Field	Description
Login	This field is not available on the Edit properties page.
Password expiration	The date in the format appropriate for your locale (for example, for en_US, the format is <code>MM, dd, YYYY</code>). You cannot change a user's expiration date when the system-wide expiration date is set to never expire.
IBM® Digital Analytics user name	When integration is enabled with IBM Digital Analytics, and you choose to create users manually, you enter the user's Digital Analytics user name here as part of the configuration process.

The Reset password page

Table 83. Fields on the Reset password page

Field	Description
Password	The new password.
Confirm	The same password you entered in Password field.

The New Data Source and Edit Data Source Properties pages

Table 84. Fields on the Data Source pages

Field	Description
Data source	The name of a data source you want the user to be able to access from an Unica application. Unica names preserve case for display purposes, but use case-insensitive rules for comparison and creation (for example, you cannot create both <code>customer</code> and <code>Customer</code> data source names).
Data source login	The login name for this data source.

Table 84. Fields on the Data Source pages (continued)

Field	Description
Data source password	The password for this data source. You can leave this field empty, if the data source account does not have a password.
Confirm password	The password again (leave empty if you left the Data Source Password field empty).

Resetting internal user passwords

Use this procedure to reset internal user passwords.

1. Click **Settings > Users**.

The **Users** list is displayed in the left pane.

2. Click the user name you want to change.
3. Click the **Reset password** link at the bottom of the page.
4. Enter the new password in the **Password** field.
5. Enter the same password in the **Confirm** field.
6. Click **Save changes** to save your changes.
7. Click **OK**.



Note: When user passwords are reset, users are prompted to change their password the next time they log in to an Unica application.

Changing internal user data sources

Use this procedure to change data source passwords or login names.

1. Click **Settings > Users**.
2. Click the name of the account you want to change.
3. Click the **Edit data sources** link at the bottom of the page.

4. Click the **Data source name** you want to change.
5. Edit the fields.

If you do not set a new password, the old one is retained.

6. Complete the form and click **Save changes** to save your changes.
7. Click **OK**.

Locale preference

You can set the locale for both internal and external users. This setting affects the display of language, time, numbers, and dates in Unica applications.

There are two ways to set locale in Unica Platform.

Globally

A configuration property, `Platform | Region setting`, on the **Settings > Configuration** page, sets the locale globally.

Per user

An attribute on the **Settings > Users** page sets the locale for individual users. This setting overrides the global setting.

Availability of locales that you can set either per user or globally may vary depending on the Unica application, and not all Unica applications support this locale setting in Unica Platform. See specific product documentation to determine availability and support for the `Region setting` property.



Note: Availability of locales that you can set either per user or globally may vary depending on the Unica application. Not all Unica applications support this locale setting. See specific product documentation to determine availability and support for the locale settings in Unica.

The default user locale preference

Unica Platform contains a default locale attribute that applies to all Unica applications that implement it.

You can set this default by setting the value of the **Region setting** property in the **Platform** category.

For details on this property, see its online help in the Configuration area or the Unica Platform Administrator's Guide. To learn whether an Unica application implements this attribute, see the documentation for that application.

In addition, you can override these default values on a per-user basis by changing the value of this property in the user's account.

restoreAccess

The `restoreAccess` utility allows you to restore access to Unica Platform if all users with `PlatformAdminRole` privileges have been inadvertently locked out or if all ability to log in to the Unica Platform has been lost.

When to use restoreAccess

You might want to use `restoreAccess` under the two circumstances described in this section.

PlatformAdminRole users disabled

It is possible that all users with `PlatformAdminRole` privileges in Unica Platform might become disabled in the system. Here is an example of how the `platform_admin` user account might become disabled. Suppose you have only one user with `PlatformAdminRole` privileges (the `platform_admin` user). Assume the `Maximum failed login attempts allowed property` property in the **General | Password settings** category on the Configuration page is set to 3. Then suppose someone who is attempting to log in as `platform_admin` enters an incorrect password three times in a row. These failed login attempts cause the `platform_admin` account to become disabled in the system.

In that case, you can use `restoreAccess` to add a user with PlatformAdminRole privileges to the Unica Platform system tables without accessing the web interface.

When you run `restoreAccess` in this way, the utility creates a user with the login name and password you specify, and with PlatformAdminRole privileges.

If the user login name you specify exists in Unica Platform as an internal user, that user's password is changed.

Only a user with the login name of PlatformAdmin and with PlatformAdminRole privileges can universally administer all dashboards. So if the `platform_admin` user is disabled and you create a user with `restoreAccess`, you should create a user with a login of `platform_admin`.

Improper configuration of NTLMv2 authentication

If you implement NTLMv2 authentication with improper configuration and can no longer log in, use `restoreAccess` to restore the ability to log in.

When you run `restoreAccess` in this way, the utility changes the value of the Platform | Security | Login method property to Unica Platform. This change allows you to log in with any user account that existed before you were locked out. You can optionally specify a new login name and password as well. You must restart the web application server on which Unica Platform is deployed if you use the `restoreAccess` utility in this way.

Password considerations

Note the following about passwords when you use `restoreAccess`.

- The `restoreAccess` utility does not support blank passwords, and does not enforce password rules.
- If you specify a user name that is in use, the utility resets the password for that user.

Syntax

```
restoreAccess -u loginName -p password
```

```
restoreAccess -r
```

Commands

-r

When used without the `-u loginName` option, reset the value of the Platform | Security | Login method property to Unica Platform. Requires restart of the web application server to take effect.

When used with the `-u loginName` option, create a PlatformAdminRole user.

Options

`-u loginName`

Create a user with PlatformAdminRole privileges with the specified login name. Must be used with the `-p` option.

`-p password`

Specify the password for the user being created. Required with `-u`.

Examples

- Create a user with PlatformAdminRole privileges. The login name is `tempUser` and the password is `tempPassword`.

```
restoreAccess -u tempUser -p tempPassword
```

- Change the value of the login method to Platform and create a user with PlatformAdminRole privileges. The login name is `tempUser` and the password is `tempPassword`.

```
restoreAccess -r -u tempUser -p tempPassword
```

Cross-partition administration privileges

In a multi-partition environment, at least one user account with the PlatformAdminRole role in Unica Platform is required, to enable you to administer security for Unica users across all partitions.

The `platform_admin` account is pre-configured with the PlatformAdminRole role. The `platform_admin` account is a superuser account that cannot be deleted or disabled through the Users functions in Unica. However, this account is subject to the password constraints of any other user. For example, someone attempting to log in as `platform_admin` might

enter an incorrect password N times in a row. Depending on the password rules in effect, the `platform_admin` account might be disabled in the system. To restore this account, you must take one of the following actions.

- If you have another user with the `PlatformAdminRole` role in Unica Platform, log in as that user and reset the `platform_admin` user's password or create another account with the `PlatformAdminRole` role in Unica Platform.
- If you have only one user with the `PlatformAdminRole` role in Unica Platform (for example, `platform_admin`), and this user is disabled, you can create a new `platform_admin` account using the `restoreAccess` utility provided with Unica Platform.

To avoid a situation where you must restore `PlatformAdminRole` access using the `restoreAccess` utility, it is a good practice to create more than one account with `PlatformAdminRole` privileges.

Types of groups: internal and external

When Unica is integrated with an external server (such as a supported LDAP server or a web access control system), it supports two types of groups: internal and external.

- **Internal** - Groups that are created within Unica using the security user interface. These users are authenticated through Unica.
- **External** - Unica groups that are mapped to groups in the external system. Examples of external servers are LDAP and web access control servers.



Attention: A group referred to as an external group in this guide is one that is actually created in Unica but is mapped to an external system.

Depending on your configuration, you may have only internal groups, only external groups, or a combination of both.

For more information about integrating Unica with an LDAP or Windows™ Active Directory server, see the relevant sections of this guide.

Management of external groups

The membership of external groups is managed in the external system.

You can assign roles to Unica external groups just as you do to internal groups.

Management of internal groups and subgroups

You can define an unlimited number of internal groups, and any internal or external user can be a member of multiple internal groups and subgroups.

A subgroup does not inherit the user members assigned to its parents, but it does inherit the roles assigned to its parents. A group and its subgroups always belong to one partition.

Only internal groups may be assigned to a partition, and only the platform_admin user, or another account with the PlatformAdminRole role, can create groups in all partitions in a multi-partition environment.

Partitions and security management

Partitions in Unica Campaign and related products provide a way to secure the data associated with different groups of users. With partitioning, a user's partition appears as if it were a separate running instance of Unica Campaign, with no indication that other partitions are running on the same system. This section describes special security management considerations in a multi-partition environment.

User membership in a partition

You assign users to a partition based on their group membership. You assign a group to a partition and then assign users to a group to give them access to a partition.

A group or subgroup may be assigned to just one partition, and parent groups do not acquire the partition assignments of their subgroups. Only the platform_admin user, or another account with the PlatformAdminRole role, can assign a group to a partition.

You should make a user a member of only one partition.

About roles and partitions

A role always exists in the context of a partition. In a single-partition environment, all roles are automatically created within the default partition, partition1. In a multi-partition environment, a role is created in the partition of the user who created it. The exception is the platform_admin user and any other accounts with the PlatformAdminRole role; these accounts can create roles in any partition.

More information about partitions

This section provides instructions on assigning a group to a partition, and assigning users to groups. For complete details on configuring partitions, see the Unica Campaign installation documentation.

Pre-configured users and roles

When Unica is first installed, three users are pre-configured and are assigned system-defined roles in Unica Platform and Unica Campaign, as described in this section.

These internal user accounts all have "password" as the default password.

The platform_admin user account

The platform_admin user account is designed to allow an Unica administrator to manage product configuration, users, and groups across all partitions in a multi-partition environment, and to use all Unica Platform features (except reporting, which has its own roles) without any filtering by partition. By default, this account has the following roles in Unica Platform.

- In Unica Platform, in the default partition, partition1
 - AdminRole
 - UserRole
 - PlatformAdminRole

These roles allow the platform_admin user to perform all administrative tasks within Unica Platform, except for the reporting functions. When additional partitions are

created, the platform_admin user can access and administer users, groups, roles, and configuration within the additional partitions.

The PlatformAdminRole role is unique in that no user can modify permissions for this role, and only a user with this role can assign the PlatformAdminRole role to another user.

- In Unica Campaign, in the default partition, partition1
 - The Global policy Admin role

This role allows the platform_admin user to perform all tasks within Unica Campaign.

By default, this user does not have access to any Unica products beyond Unica Platform and Unica Campaign.

The asm_admin user account

The asm_admin user account is designed to allow an Unica administrator to manage users and groups in a single-partition environment, and to use all Unica Platform features (except reporting, which has its own roles). This account has the following roles.

- In Unica Platform, in the default partition, partition1
 - AdminRole
 - UserRole

With the exceptions noted below, these roles allow the asm_admin user to perform all administrative tasks within Unica Platform within the partition to which asm_admin belongs, which is partition1 by default.

These roles allow this user to administer the Configuration page, which does not filter by partition for any user. For this reason, you should remove the Administer Configuration page permission from the AdminRole role in Unica Platform, and reserve configuration tasks for the platform_admin user.

The exceptions are as follows.

- To access reporting functions, you must grant the Reports System role.
- This user cannot assign the PlatformAdminRole role to any user or group.

The demo account

The demo account has the following roles.

- In Unica Platform, in the default partition, partition1
 - UserRole

This role allows the demo user to view and modify his or her own account attributes on the Users page, but not to change roles or partitions for his or her own account or access any of the other features contained within Unica Platform. By default, this user does not have access to any of the Unica products.

- In Unica Campaign, in the default partition, partition1
 - The Global policy Review role

This role allows the demo user to create bookmarks and to view campaigns, sessions, offers, segments, and reporting in Unica Campaign.

Overview of managing user application access in Unica Platform

Using Unica Platform security administration features to manage user application access is a multi-step process. The following procedure provides an overview of the basic process, which is described in detail in the remainder of this guide.

1. Plan the roles you want to use to control user access to Unica products. Configure roles and their permissions as needed.
2. Plan what groups you need to fulfill your security requirements. You may have only internal groups, only external groups, or a combination of both, depending on how your system is configured.
3. Create any necessary internal and external groups.
4. Assign your groups to roles.
5. If you have only internal user accounts, create any internal user accounts as needed.
6. Assign users to groups, or assign roles to individual users, based on the application access you want the users to have.

Adding an internal group

Use this procedure to add an internal group.

1. Click **Settings > User groups**.
2. Click **New group** above the **Group Hierarchy** list.
3. Complete the **Group name** and **Description** fields.



Important: Do not give the group a the same name as system-defined roles. For example, do not name a group "Admin," which is a role name used in Unica Campaign. Doing so can cause problems during upgrades.

4. Click **Save changes**.

The new group's name appears in the **Group hierarchy** list.

Adding a subgroup

Use this procedure to add an internal subgroup.

1. Click **Settings > User groups**.
2. Click the name of the group to which you want to add a subgroup.
3. Click **New subgroup**.
4. Complete the **Group name** and **Description** fields.



Important: Do not give the subgroup a the same name as system-defined roles. For example, do not name a subgroup "Admin," which is a role name used in Unica Campaign. Doing so can cause problems during upgrades.

5. Click **Save changes**.

The new subgroup is added under the appropriate group in the **Group Hierarchy** list.



Tip: If the parent group's folder icon is closed, click the plus sign (+) to expand the list.

Deleting a group or subgroup

Remember, when you delete a group or subgroup, members of the group lose the roles assigned to that group, and any parents of that group also lose those role assignments, unless the roles are also explicitly assigned to the parents.

1. Click **Settings > User groups**.
2. Click the name of the group or subgroup that you want to delete.



Note: To select a subgroup when the parent group's folder icon is closed, click the plus sign (+) to expand the list.

3. Click the **Delete group** button at the top of the right pane.
4. Click **OK**.

Assigning a group to a partition

This procedure is necessary only if multiple partitions are configured for Unica Campaign. Only an account with the PlatformAdminRole role, such as the platform_admin user, can perform this task.

1. Determine which groups you want to assign to each partition. Create the groups, if necessary.
2. Click **Settings > User groups**.
3. Click the name of the group or subgroup that you want to assign to a partition.
4. Click **Edit properties**.
5. Select the desired partition from the **Partition ID** drop-down list.

This field is available only when multiple partitions are configured.

6. Click **Save changes** to save your changes.
7. Click **OK**.

Adding a user to a group or subgroup

Use this procedure to add a user to a group or subgroup.

1. Click **Settings > Users**.



Note: You can perform the same task on the **User groups** page by clicking the group name and then clicking **Edit Users**.

2. Click the user name you want to change.
3. Click the **Edit groups** link at the bottom of the page.
4. Click a group name in the **Available groups** box to select it.
5. Click the **Add** button.

The group name moves to the **Groups** box.

6. Click **Save changes** to save your changes.
7. Click **OK**.

The user account details are displayed, with the group or subgroup you assigned listed.

Removing a user from a group or subgroup

Use this procedure to remove a user from a group or subgroup.



Important: Removing a user from a group or subgroup removes the roles assigned to that group or subgroup from the user.

1. Click **Settings > Users**.
2. Click the user name you want to change.
3. Click the **Edit groups** link at the bottom of the page.
4. Click a group name in the **Groups** box to select it.
5. Click the **Remove** button.

The group name moves to the **Available groups** box.

6. Click **Save changes** to save your changes.
7. Click **OK**.
8. Click the **Edit properties** link at the bottom of the page.
9. Change the name or description as desired.
10. Click **Save changes** to save your changes.
11. Click **OK**.

Changing a group or subgroup description

Use this procedure to change a group or subgroup description.

1. Click **Settings > User groups**.
2. Click the name of the group or subgroup whose description you want to change.



Note: To select a subgroup when the parent group's folder icon is closed, click the plus sign (+) to expand the list.

3. Click **Edit properties**.
4. Edit the description as desired.
5. Click **Save changes** to save your changes.
6. Click **OK**.

The user group management pages

These are the fields you use to configure user groups.

Fields on the New group, New subgroup, and Edit properties pages

Table 85. Fields on the New group, New subgroup, and Edit properties pages

Field	Description
Group name	The group name. The limit is 64 characters.

**Table 85. Fields on the New group, New subgroup, and Edit properties pages
(continued)**

Field	Description
	<p>You may use the following characters when you create a group name.</p> <ul style="list-style-type: none"> • Upper and lower case alphabetic characters (A-Z) • Numbers (0-9) • Single quote (') • Hyphen (-) • Underscore (_) • The 'at' sign (@) • Forward slash (/) • Parenthesis • Colon (:) • Semi-colon (;) • Space (except as the first character) • Double byte characters (such as alpha-numeric Chinese characters) <p>Do not give a group or subgroup a the same name as system-defined roles. For example, do not name a group "Admin," which is a role name used in Unica Campaign. Doing so can cause problems during upgrades.</p> <p>Unica names preserve case for display purposes, but use case-insensitive rules for comparison and creation (for example, you cannot create both Admin and admin as as separate group names).</p> <p>When you create a subgroup, it is a good idea to give your subgroup a name that relates it to its parent group.</p>
Description	The group description. The limit is 256 characters.

**Table 85. Fields on the New group, New subgroup, and Edit properties pages
(continued)**

Field	Description
	It is helpful to include the roles you plan to give the group or subgroup in the description. Then you can see at a glance on the group detail page both the roles and users.
Partition ID	Available only when multiple partitions are configured. If you assign a partition to a group, the members of that group are members of that partition. A user can be a member of only one partition.

Fields on the Edit users and Edit roles pages

Table 86. Fields on the Edit users and Edit roles pages

Field	Description
Available groups or Available roles	A list of groups and subgroups or roles to which the user is not assigned.
Groups or Roles	A list of groups and subgroups or roles to which the user is assigned

Creating a role

You should create new roles only for products that have detailed permissions. The reporting function and some Unica products have only basic permissions available, so there is no need to create additional roles for these products.

1. Click **Settings > User roles & permissions**.
2. Click the plus sign next to the product name in the list on the left, and then click the name of the partition where you want to create the role.
3. For Unica Campaign only, if you want to create a new role under the Global Policy, click Global Policy.

4. Click **Add roles and assign permissions**.
5. Click **Add a role**.
6. Enter a name and description for the role.
7. Click **Save changes** to save the role, or **Save and edit permissions** to go to the Permissions page to add or modify permissions for any of the roles in the list.

Modifying role permissions

Use this procedure to modify role permissions.

1. Click **Settings > User roles & permissions**.
2. Click the plus sign next to a product in the list on the left, and then click the name of the partition where you want to modify a role.
3. For Unica Campaign only, if you want to create a new role under the Global Policy or a user-created policy, click the policy name.
4. Click **Add roles and assign permissions**.
5. Click **Save and edit permissions**.
6. Click the plus sign next to a role group to display all available permissions and the state of those permissions within each role.
7. In the role column where you want to modify permissions, click the box in the permissions rows to set the state to Grant, Deny, or Not granted.
8. Click **Save changes** save your changes.

You can click **Revert to saved** to undo changes since your last save and remain on the Permissions page, or **Cancel** to discard your changes since your last save and go to the partition or policy page.

Removing a role from the system

Use this procedure to remove a role from Unica.



Important: If you remove a role, it is removed from all users and groups to which it was assigned.

1. Click **Settings > User roles & permissions**.
2. Click the plus sign next to a product in the list on the left, and then click the name of the partition where you want to create the role.
3. For Unica Campaign only, if you want to create a new role under the Global Policy, click Global Policy.
4. Click **Add roles and assign permissions**.
5. Click the **Remove** link for the role you want to delete.
6. Click **Save changes**.

Assigning a role to or removing a role from a group

If you add a role to a group or remove a role from a group, members of that group acquire or lose that role.

1. Click **Settings > User groups**.
2. Click the name of the group that you want to work with.
3. Click **Assign roles**.

Roles that are not assigned to the group are shown in the **Available roles** box on the left. Roles that are currently assigned to the group are shown in the **Roles** box on the right.

4. Click a role name in the Available roles box to select it.
5. Click **Add** or **Remove** to move the role name from one box to the other.
6. Click **Save changes** to save your changes.
7. Click **OK**.

Assigning a role to or removing a role from a user

Use the **Edit roles** window to assign a role to or to remove a role from a user.

Complete the following tasks to assign or remove a role from a user:

1. Click **Settings > Users**.
2. Click the name of the user account that you want to work with.
3. Click **Edit roles**.

Roles that are not assigned to the user are shown in the **Available Roles** box on the left. Roles that are currently assigned to the user are shown in the **Selected roles** box on the right.

4. Select a role in the **Available roles** box. Complete one of the following tasks:
 - To assign a role to a user, select a role in the **Available roles** box, and click **Add**.
 - To remove a role from a user, select a role in the **Selected roles** box, and click **Remove**.
5. Click **Save changes**, and then click **OK**.

Definitions of permission states

For each role, you can specify which permissions are granted, not granted, or denied. You set these permissions on the **Settings > User roles and permissions** page.

These states have the following meanings.

- **Granted** - indicated with a check mark . Explicitly grants permission to perform this particular function as long as none of the user's other roles explicitly denies permission.
- **Denied** - indicated with an "X" . Explicitly denies permission to perform this particular function, regardless of any other of the user's roles which might grant permission.
- **Not granted** - indicated with a circle . Does not explicitly grant nor deny permission to perform a particular function. If this permission is not explicitly granted by any of a user's roles, the user is not allowed to perform this function.

Permissions for products that use only basic roles

The following table describes the functional definitions of the roles available for the Unica products that use only the basic roles. See the product documentation for additional information.

Table 87. Permissions for products that use only basic roles

Application	Roles
Leads	Leads roles are reserved for future use.
Reports	<ul style="list-style-type: none"> • ReportsSystem - grants the <code>report_system</code> permission, which gives you access to the Report SQL Generator and Sync Report Folder Permissions options in the Settings menu. • ReportsUser - grants the <code>report_user</code> permission, which is used by the Authentication Provider installed on the IBM® Cognos® 11 BI system only. <p>For information about authentication options for the IBM® Cognos® 11 BI integration and how the Authentication Provider uses the reporting permissions, see the Unica Reports Installation and Configuration Guide.</p>
IBM eMessage	<ul style="list-style-type: none"> • Deliver_Admin - Has full access to all features. • Deliver_User - Reserved for future use. <p>Access is further defined through the security policies in Unica Campaign. See the IBM eMessage Startup and Administrator's Guide for details.</p>
Unica Interact	<ul style="list-style-type: none"> • InteractAdminRole - Has full access to all features.
Unica Collaborate	<ul style="list-style-type: none"> • collab_admin - Has full access to all features. • corporate - Can use Unica Campaign and Unica Collaborate to develop reusable Lists and On-demand Campaign templates. Can create and execute Corporate Campaigns. • field - Can participate in Corporate Campaigns and can create and execute Lists and On-demand Campaigns in Unica Collaborate.

Table 87. Permissions for products that use only basic roles (continued)

Application	Roles
Unica Plan	<ul style="list-style-type: none"> • PlanUserRole - By default, users with the PlanUserRole role have very few permissions enabled in Unica Plan. They cannot create plans, programs, or projects and have limited access to the Administrative settings. • PlanAdminRole - By default, users with the PlanAdminRole role have most permissions enabled in Unica Plan, including access to all administrative and configuration settings, allowing a broad range of access. <p>Access is further defined through the security policies in Unica Plan.</p>
IBM SPSS Modeler Advantage Enterprise Marketing Management Edition	<ul style="list-style-type: none"> • SPSSUser - Users with the SPSSUser role can do the following: <ul style="list-style-type: none"> ◦ Run reports ◦ View items in their Content Repository ◦ Perform scoring • SPSSAdmin - Users with the SPSSAdmin role have all permissions enabled in IBM SPSS Modeler Advantage Enterprise Marketing Management Edition, including access to all administrative and configuration settings.

Permissions for Unica Platform

The following table describes the permissions you can assign to roles in Unica Platform.

Table 88. Unica Platform permissions

Permission	Description
Administer users page	Allows a user to perform all user administration tasks on the Users page for user accounts in his or her own partition: add

Table 88. Unica Platform permissions (continued)

Permission	Description
	and delete internal user accounts, and modify attributes, data sources and role assignments
Access users page	Allows a user to view the User page.
Administer User groups page	Allows a user to perform all actions on the User groups page except assign a partition to a group, which can only be done by the platform_admin user. This permission allows a user to create, modify, and delete groups, manage group membership, and assign roles to groups.
Administer User roles page	Allows a user to perform all actions on the User roles & permissions page: create, modify, and delete roles in Unica Platform and Unica Campaign, and assign users to roles for all listed Unica products.
Administer Configuration page	Allows a user to perform all actions on the Configuration page: modify property values, create new categories from templates, and delete categories that have the Delete Category link.
Administer Data filters page	Allows a user to perform all actions on the Data filters page: assign and remove data filter assignments.
Administer Scheduled tasks page	Allows a user to perform all actions on the Schedule management page: view and modify schedule definitions and view runs.
Administer dashboards	Allows a user to perform all actions on the dashboards pages: create, view, modify, and delete dashboards, assign dashboard administrators, and administer dashboard access.

Permissions for Opportunity Detect

The following table describes permissions that you can assign to roles in Opportunity Detect.

All permissions that have the **Not Granted** status are treated as **Denied**.

Table 89. Permissions in Opportunity Detect

Permission	Description
View only	Can access all of the user interface, in view-only mode.
Design triggers	<ul style="list-style-type: none"> • Can create workspaces and design trigger systems. • Can create, modify, and delete all trigger related resources. • Can access Workspace, Component, Audience Level, Data Source, and Named Value List pages. • Can not access the Server Groups page or the Deployment tab of a workspace. • Can not set off a batch run. • Can not administer objects that the web service creates when Opportunity Detect is integrated with Unica Interact.
Run for testing	<ul style="list-style-type: none"> • Deploy deployment configurations and run batch deployment configurations on server groups not designated for production. • Can access Server Group page and the Deployment tab of a workspace, but can not designate a server group for production. • Can not deploy deployment configurations or run deployment configurations that use a production server group.
Run for production	<ul style="list-style-type: none"> • Deploy deployment configurations and run batch deployment configurations on any server group. • Perform all actions on the Server Group page and the Deployment and Batch Run tabs of a workspace, including designating a server group for production.
Administer real time	<p>Manage objects that the web service creates when Opportunity Detect is integrated with Unica Interact to enable real time mode.</p> <p>Allows the following.</p>

Table 89. Permissions in Opportunity Detect (continued)

Permission	Description
	<ul style="list-style-type: none"> • Delete workspaces and components created by the web service. • Start and stop real time deployment configurations and update their log level. <p>The user with this permission alone can not start runs for real time deployment configurations.</p> <p>No one, even with this permission, can do any of the following.</p> <ul style="list-style-type: none"> • Delete and update audience levels, data sources, named value lists, server groups, or deployment configurations created by the web service. • Create and deploy deployment configurations created by the web service.

Unica configuration properties

This section describes the configuration properties found on the **Settings & Configuration** page.

Configuration management

When Unica is first installed, the Configuration page shows only the properties used to configure Unica Platform and some global configuration properties. When you install additional Unica applications, the properties used to configure these applications are registered with Unica Platform. These properties are then shown on the Configuration page, where you can set or modify their values.

Some applications might have additional configuration properties that are not stored in the central repository. See application documentation for complete information about all configuration options for the application.

Templates for duplicating categories

The properties for an Unica application are registered with Unica Platform when the application is installed. When an application requires users to create duplicate categories for configuration purposes, a category template is provided.


To create a category, you duplicate the template. For example, you can create a new Unica Campaign partition or data source by duplicating the appropriate template.

You can also delete any category that was created from a template.

Category naming restrictions

The following restrictions apply when you name a category that you create from a template.

- The name must be unique among categories that are siblings in the tree (that is, among categories that share the same parent category).
- The following characters are not allowed in category names.



! " ' # \$ % & () * + : ; ,
 ^ < > + ? @ [] { } / \ ` ~

Also, the name cannot start with a period.

Creating a category from a template

Use this procedure to create a category from a template on the Configuration page.

1. On the Configuration page, navigate to the template category you want to duplicate.
 Unlike other categories, template category labels are in italics and enclosed in parentheses.
2. Click the template category.

3. Enter a name in the **New category name** field (required).
4. You can edit properties within the new category now, or later.
5. Click **Save changes** to save the new configuration.

The new category appears in the navigation tree.

Navigating to a category

Use this procedure to navigate to a category on the Configuration page.

1. Log in to Unica.
2. Click **Settings > Configuration** in the toolbar.

The Configuration page shows the Configuration Categories tree.

3. Click the plus sign beside a category.

The category opens, showing sub categories. If the category contains properties, they are listed along with their current values.

The internal names for the categories are displayed under the page title. You use these internal names when you manually import or export categories and their properties using the `configTool` utility.

4. Continue to expand the categories and sub categories until the property you want to edit appears.

Editing property values

Use this procedure to modify a property value on the Configuration page.

1. Navigate to the category that contains the property you want to set.

The Settings page for the category shows a list of all the properties in the category and their current values.

2. Click **Edit settings**.

The Edit settings page for the category shows the property values in editable fields.

3. Enter or edit values as needed.

In UNIX™, all file and directory names are case-sensitive. The case of any file and folder name you enter must match the case of the file or folder name on the UNIX™ machine.

4. Click **Save changes** to save your changes or **Cancel** to exit the page without saving.

Templates for duplicating categories

The properties for an Unica application are registered with Unica Platform when the application is installed. When an application requires users to create duplicate categories for configuration purposes, a category template is provided.

To create a category, you duplicate the template. For example, you can create a new Unica Campaign partition or data source by duplicating the appropriate template.

You can also delete any category that was created from a template.

Category naming restrictions

The following restrictions apply when you name a category that you create from a template.

- The name must be unique among categories that are siblings in the tree (that is, among categories that share the same parent category).
- The following characters are not allowed in category names.

! " ' # \$ % & () * + : ; ,

^ < > + ? @ [] { } / \ ` ~

Also, the name cannot start with a period.

Assigning or changing a dashboard administrator

Use this procedure to assign or change a dashboard administrator.

1. In Unica, select **Dashboard**

A Dashboard Administration page opens. All dashboards associated with your partition are shown, with their portlets listed.

2. Click the **Manage Permissions** icon at the bottom of the dashboard you want to work with.

A Manage Permissions tab opens.

3. Click the **Manage Dashboard Administrators** icon.

A Manage Dashboard Administrators page opens. All dashboards associated with your partition are shown, with their portlets listed.

4. Select or deselect names.

Users whose names are selected have administration permissions for the dashboard.

You can do the following to find users.

- Filter the list by entering all or part of a user name in the **Search** field.
- Display all users, or only unassigned users, or only assigned users.
- Sort the list by clicking column headings.
- Display all users at once (based on your filtering criteria) or page through the list.

5. Click **Update**.

The dashboard administrator

If you have been designated a dashboard administrator, you are responsible for managing the membership, layout, and content of that dashboard. This section describes how to manage dashboard membership.

Pre-defined portlets

Unica provides two types of pre-defined dashboard portlets, which you can enable and then add to any dashboard you create.

Unica pre-defined portlets use Unica Platform single-sign-on mechanism to access Unica content. Users are not prompted for credentials when they view a dashboard containing these portlets.

- List: A list of Unica items specific to the user. Examples of list portlets are My Recent Campaigns (Unica Campaign), My Alerts (Unica Plan, and the Continent Summary report (Digital Analytics for On Premises).
- IBM® Cognos® report: A specially formatted version of an Unica report.

You can also create your own custom dashboard portlets.

Custom portlet types and availability

You can create portlets from the following types of Unica pages.

- Any Unica IBM® Cognos® report, including Unica Interact Interaction Point Performance reports that you have customized to point to additional interactive channels. You can customize any existing dashboard reports as described in this guide, or you can customize a non-dashboard report. For details on how to customize a non-dashboard report, see the *Unica Reports Installation and Configuration Guide*.
- Quick links portlets, which you can build using pre-defined links to Unica products.
- Any Digital Analytics for On Premises or Digital Analytics for On Premises On Demand report or dashboard that auto-updates.
- Any IBM Digital Analytics report.

In addition, you can create a portlet from a page on the internet or your company intranet.

Portlets that you create yourself are available for use in any dashboard. Your custom portlets are listed in the Manage Portlets window, where you can choose to add them to a dashboard.

Adding a pre-defined portlet to a dashboard

Use this procedure to add a pre-defined portlet to a dashboard.

1. In Unica, select **Dashboard** and then select the tab for the dashboard you want to work with.
2. Click **Manage portlets** to view a list of enabled portlets.

You can also access the Manage portlets page from the Administration tab, by clicking the Manage Portlets icon on the dashboard.

3. Select the check box next to one or more portlets to select it for addition to the dashboard.

Use the following features to assist you in selecting portlets.

- Filter the list of portlets by name or by the product that is the source of the portlet.
 - Display all portlets at once or page through the list.
 - Click column headings to sort the list alphabetically by source or portlet name, in ascending or descending order.
4. Click **Update**.

The selected portlets are added to the dashboard.

Adding a custom portlet to a dashboard

Perform this procedure to add a custom portlet to a dashboard.

Before performing this procedure, you should have done the following.

- Prepared a URL as described elsewhere in this section
- Added the URL to the `Platform_Admin_URL.properties` file, which is located in the `conf` directory under your Unica Platform installation
- Stopped and restarted the Unica Platform web application

1. In Unica, select **Dashboard** and then select the tab for the dashboard you want to work with.
2. Click **Manage Portlets**.
A **Manage Portlets** window opens.
3. Click **Create Custom Portlet**.

A **Create Custom Portlet** window opens.

4. Do one of the following sets of steps, depending on the type of portlet you are adding.

If you are creating a portlet that is not a Digital Analytics report portlet, do the following.

- For the **Type**, select **Custom**.
- Complete the **Name** and **Description** fields.
- Paste the contents of your clipboard (which contains the URL you obtained earlier) into the **URL** field.

If you are creating a Digital Analytics report portlet, do the following.

- For the **Type**, select **IBM Digital Analytics**.
- Complete the **Name** and **Description** fields.
- Paste the contents of your clipboard (which contains the URL you obtained earlier) into the **IBM Digital Analytics URL** field.

5. Click **Save**.

The window closes and you return to the Administration tab. The new portlet is located in the upper left corner, where it may overlay a previously added portlet. Click and drag the portlet heading to place the portlet in an appropriate position in the dashboard.

Scheduling a dashboard report

To schedule a dashboard report (either a pre-defined or user-created portlet), you must first create a view and schedule it, and then configure the portlet as described here.



Note: You can schedule only those reports that are not filtered by user.

1. In Cognos®, copy the report and save it under a new name.
2. In Cognos®, open the copied report and save it as a view with the same name as the original report. Save it in the *Unica Dashboard/Product* folder, where *Product* is the appropriate product folder
3. In Cognos®, schedule the view.

4. In Unica, add the report to the dashboard, if you have not done so already.
5. Only if the report is one of the pre-defined portlets, do the following in Unica.
 - On the Dashboard Administration page, click the **Edit portlet** icon next to the portlet.
 - Select **Yes** next to **Has this report been scheduled?**
 - Click **Save**.

Adding a pre-defined portlet to a dashboard

Use this procedure to add a pre-defined portlet to a dashboard.

1. In Unica, select **Dashboard** and then select the tab for the dashboard you want to work with.
2. Click **Manage portlets** to view a list of enabled portlets.

You can also access the Manage portlets page from the Administration tab, by clicking the Manage Portlets icon on the dashboard.

3. Select the check box next to one or more portlets to select it for addition to the dashboard.

Use the following features to assist you in selecting portlets.

- Filter the list of portlets by name or by the product that is the source of the portlet.
 - Display all portlets at once or page through the list.
 - Click column headings to sort the list alphabetically by source or portlet name, in ascending or descending order.
4. Click **Update**.

The selected portlets are added to the dashboard.

Dashboards and partitions

If you are administering dashboards in a multi-partition environment, read this section to understand how multiple partitions affect dashboards.

In a multi-partition environment, a user can view or administer only those dashboards associated with the partition to which the user belongs.

When a dashboard administrator creates a dashboard, the following partition-related rules apply.

- Any dashboard that is created is available only to members of the same partition as the user who created it.
- Only those pre-defined portlets that are enabled in the partition to which the administrator belongs are available for inclusion in the dashboard.
- Only groups and users assigned to the same partition as the administrator are available for assignment to the dashboard.

Partitions and security management

Partitions in Unica Campaign and related products provide a way to secure the data associated with different groups of users. With partitioning, a user's partition appears as if it were a separate running instance of Unica Campaign, with no indication that other partitions are running on the same system. This section describes special security management considerations in a multi-partition environment.

User membership in a partition

You assign users to a partition based on their group membership. You assign a group to a partition and then assign users to a group to give them access to a partition.

A group or subgroup may be assigned to just one partition, and parent groups do not acquire the partition assignments of their subgroups. Only the `platform_admin` user, or another account with the `PlatformAdminRole` role, can assign a group to a partition.

You should make a user a member of only one partition.

About roles and partitions

A role always exists in the context of a partition. In a single-partition environment, all roles are automatically created within the default partition, `partition1`. In a multi-partition

environment, a role is created in the partition of the user who created it. The exception is the platform_admin user and any other accounts with the PlatformAdminRole role; these accounts can create roles in any partition.

More information about partitions

This section provides instructions on assigning a group to a partition, and assigning users to groups. For complete details on configuring partitions, see the Unica Campaign installation documentation.

Dashboard management

Dashboards are configurable pages that contain information useful to groups of users who fill various roles within your company. The components that make up dashboards are called portlets. Dashboards can contain pre-defined portlets or portlets that you create.

You can create and configure dashboards yourself, or you can use the pre-assembled dashboards. Pre-assembled dashboards contain pre-defined portlets in combinations that are designed to be useful to users in a variety of roles within your organization.

You can also create your own custom portlets from Unica product pages, pages on your company intranet, or pages on the internet.

Custom portlets

Topics in this section describe how to create and use custom portlets.

Enabling or disabling pre-defined portlets

Perform this task before you begin to create dashboards. You should enable only those portlets that reference Unica products that you have installed.

1. Log in to Unica and select **Settings > Dashboard portlets**.
2. Click the check box next to portlet names to enable or disable them.

A check mark enables a portlet, and clearing the check box disables a portlet.

The portlets you selected are enabled and are available for inclusion in dashboards.

Creating a pre-assembled dashboard

Use this procedure to create a pre-assembled dashboard.

1. Ensure that the portlets that comprise the pre-assembled dashboard you want to create are enabled.
2. In Unica, select **Dashboard** to open the Dashboard administration page.
3. Click **Create dashboard**.
4. For the **Type** select **Use pre-assembled dashboards**.

The available pre-assembled dashboards are listed.

5. Select the pre-assembled dashboard you want to use and click **Next**.

A list of the portlets comprising the selected pre-assembled dashboard is displayed. The list lets you know when a portlet is not available, either because the required product is not installed or because the portlet has not been enabled.

6. Click **Save** to finish creating the dashboard.

Your new dashboard appears as a tab on the Dashboard administration page, and is listed on the Administration tab. You can now modify the portlets it contains, if necessary.

Single sign-on between Unica and IBM Digital Analytics

If your organization uses IBM Digital Analytics, you can enable single sign-on between Digital Analytics and Unica.

Single sign-on allows users to navigate to Digital Analytics reports from within the Unica user interface without being prompted to log in.

Also, if Digital Analytics reports are referenced in Unica dashboards, single sign-on allows users to view these reports (if they have access to them in Digital Analytics).

Two options for enabling single sign-on between Unica and IBM Digital Analytics

You can choose between two options for enabling single sign-on.

- You can configure Digital Analytics to automatically create an Digital Analytics user account the first time an Unica user navigates to Digital Analytics.

You might want to choose this option if you want all of your Unica users to have single sign-on with Digital Analytics.

- You can configure Unica user accounts for single sign-on by adding each user's existing Digital Analytics login name to his or her detail page in Unica.

When you choose this option, users who require access to Digital Analytics must have an Digital Analytics account.

You might want to choose this option if you want a subset of your Unica users to have single sign-on with Digital Analytics.

Permissions in Digital Analytics for single sign-on users

When the automatic account creation option is **not** selected in Digital Analytics, single sign-on users have the permissions in Digital Analytics that they would have if they log in to Digital Analytics directly.

When the automatic account creation option is selected in Digital Analytics, single sign-on users have permissions in Digital Analytics as follows.

- By default, users have the permissions granted to the Digital Analytics group the administrator has configured for all automatically created users.

Administrators can modify the permissions associated with this group.

- In addition, the administrator can override automatic account creation for users who already have a Digital Analytics account. If the override is in place for a user, that user has the permissions he or she would have when he or she logs in to Digital Analytics directly.

Server clock coordination

The clock on the server on which Unica Platform is deployed must match the time on the Digital Analytics server clock. For single sign-on, the Digital Analytics server allows for up to 15 minutes of difference (900 seconds) between server clock times.

As a best practice, you should synchronize server clocks. To ensure synchronization, you should use the Network Time Protocol (NTP).

If you cannot synchronize your server clock, and there might be at least 15 minutes of difference between the clocks, you can set the **Clock skew adjustment (seconds)** configuration property under the Coremetrics® category in Unica Platform to a number that reflects the difference between the clocks.

Implementation of one-way SSL

This section describes one-way SSL in Unica.

Any communication that needs to be secured between two applications connecting over a network can be transmitted using the Secure Sockets Layer (SSL) protocol.

SSL provides secure connections by:

- Allowing an application to authenticate the identity of another application
- Using a private key to encrypt and decrypt data transferred over the SSL connection

When applications are configured for SSL, web traffic is over HTTPS instead of HTTP as reflected in the URLs.

When processes communicate with each other, the process making a request acts as the client and the process responding to a request acts as the server. For complete security, SSL should be implemented for all forms of communication with Unica products.

SSL can be configured one-way or two-way. With one-way SSL, the server is required to present a certificate to the client but the client is not required to present a certificate to the server. To successfully negotiate the SSL connection, the client must authenticate the server. The server accepts a connection from any client.

Preparing the URL from a Digital Analytics report

Use this procedure for Digital Analytics reports.

If you want users to be able to view Digital Analytics reports in dashboards without having to log in to Digital Analytics, you must enable single sign-on between Unica and Digital Analytics.

1. Log in to Digital Analytics and navigate to the report that you want to add as a portlet.
2. Copy the URL shown in your browser.

The link is copied to your clipboard and is ready to be pasted into the IBM® Digital Analytics URL field in the Create Custom Portlet window in Unica Platform.

To ensure the URL is not overwritten should you copy something else before using it to create a portlet, you can paste it into a text editor.

The Create Custom Portlet page

Refer to this table if you need help completing the fields on the Custom Portlet page.

Table 90. Fields on the Create Custom Portlet page

Field	Description
Type	Select the portlet type: a portlet that is not from Digital Analytics, or a portlet that is from Digital Analytics.
Name	Enter an appropriate name for the portlet.
Description	Enter a description for the portlet that lets other administrators know why it is part of this dashboard.
URL or Digital Analytics URL	Paste in your prepared URL.
Hidden Variables	Available only when the portlet is not from Digital Analytics. If your portlet requires users to log in, you can enter name/value pairs to securely send these credentials to the site. You must obtain the expected variable name from the web site.

Dynamic tokens

When you define a custom dashboard portlet, you can use pre-defined tokens that are replaced with the values stored in Unica Platform for the current user when the portlet is invoked.

This feature is not available for custom portlets from Digital Analytics.

The following tokens are supported.

- `<user_name>`
- `<user_first_name>`
- `<user_last_name>`
- `<user_email>`

The URL is invoked with hidden variables passed as request parameters.

The values must be present in the user details in Unica Platform. Also, you must know the names of the variables used by the target web site.

To use these tokens, enter the name value pairs in the **Hidden Variables** field of the Create Custom Portlet page. If you use multiple tokens, separate them with a semicolon.

For example, suppose you want to send a user's first and last name in a portlet URL. In this example, the receiving web site expects `fname` and `lname` to contain the user's first and last names respectively. You would complete the **URL** and **Hidden Variables** fields as follows.

- **URL** - `www.example.com`
- **Hidden Variables** - `fname=<user_first_name>;lname=<user_last_name>`

The dashboard administrator

If you have been designated a dashboard administrator, you are responsible for managing the membership, layout, and content of that dashboard. This section describes how to manage dashboard membership.

Granting or removing dashboard membership

Use this procedure to grant or remove dashboard membership.

1. In Unica, select **Dashboard** and then select the tab for the dashboard you want to work with.
2. Click the **Manage Permissions** icon at the bottom of the dashboard you want to work with.

A Manage Permissions tab opens.

3. Click the **Manage Dashboard Users** icon.

A Manage Dashboard Users page opens.

4. Select or deselect the checkbox to grant or remove access to the dashboard.

Users whose names are selected can view the dashboard.

You can do the following to find users.

- Filter the list by entering all or part of a user name in the **Search** field.
- Display all users, or only unassigned users, or only assigned users.
- Sort the list by clicking column headings.
- Display all users at once (based on your filtering criteria) or page through the list.

5. Click **Update**.

Adding a pre-defined portlet to a dashboard

Use this procedure to add a pre-defined portlet to a dashboard.

1. In Unica, select **Dashboard** and then select the tab for the dashboard you want to work with.
2. Click **Manage portlets** to view a list of enabled portlets.

You can also access the Manage portlets page from the Administration tab, by clicking the Manage Portlets icon on the dashboard.

3. Select the check box next to one or more portlets to select it for addition to the dashboard.

Use the following features to assist you in selecting portlets.

- Filter the list of portlets by name or by the product that is the source of the portlet.
- Display all portlets at once or page through the list.
- Click column headings to sort the list alphabetically by source or portlet name, in ascending or descending order.

4. Click **Update**.

The selected portlets are added to the dashboard.

The Manage Portlets page

Refer to this table if you need help completing the fields in the Manage Portlets page.

Table 91. Fields on the Manage Portlets page

Field	Description
Filter	Enter part or all of a product name or portlet name to filter the portlet list based on the product that supplies the report or the name of the portlet.
Create Custom Portlet	Click to open a page where you can create a portlet that uses a URL you have obtained.
Create Quick Link Portlet	Click to open a page where you can create a quick link portlet.

Dashboards and partitions

If you are administering dashboards in a multi-partition environment, read this section to understand how multiple partitions affect dashboards.

In a multi-partition environment, a user can view or administer only those dashboards associated with the partition to which the user belongs.

When a dashboard administrator creates a dashboard, the following partition-related rules apply.

- Any dashboard that is created is available only to members of the same partition as the user who created it.
- Only those pre-defined portlets that are enabled in the partition to which the administrator belongs are available for inclusion in the dashboard.
- Only groups and users assigned to the same partition as the administrator are available for assignment to the dashboard.

Enabling or disabling pre-defined portlets

Perform this task before you begin to create dashboards. You should enable only those portlets that reference Unica products that you have installed.

1. Log in to Unica and select **Settings > Dashboard portlets**.
2. Click the check box next to portlet names to enable or disable them.

A check mark enables a portlet, and clearing the check box disables a portlet.

The portlets you selected are enabled and are available for inclusion in dashboards.

Creating a dashboard that is not pre-assembled

Use this procedure to create a dashboard that is not pre-assembled

1. In Unica, select **Dashboard** to open the Dashboard administration page.

All dashboards associated with your partition are shown.

2. Click **Create dashboard** to open the Create dashboard page.
3. Enter a unique title (required) and description (optional).
4. Select basic permissions.
 - If you want to restrict access to users who belong to a group associated with the dashboard, select **User or group-specific dashboard**.
 - If you want all users in the partition to be able to view the dashboard, select **Global dashboard for everyone**.
5. For the **Type** select **Create dashboard**.

6. Click **Save**.

Your new dashboard appears as a tab on the Dashboard administration page, and is listed on the Administration tab.

You can now add portlets.

Creating a pre-assembled dashboard

Use this procedure to create a pre-assembled dashboard.

1. Ensure that the portlets that comprise the pre-assembled dashboard you want to create are enabled.
2. In Unica, select **Dashboard** to open the Dashboard administration page.
3. Click **Create dashboard**.
4. For the **Type** select **Use pre-assembled dashboards**.

The available pre-assembled dashboards are listed.

5. Select the pre-assembled dashboard you want to use and click **Next**.

A list of the portlets comprising the selected pre-assembled dashboard is displayed. The list lets you know when a portlet is not available, either because the required product is not installed or because the portlet has not been enabled.

6. Click **Save** to finish creating the dashboard.

Your new dashboard appears as a tab on the Dashboard administration page, and is listed on the Administration tab. You can now modify the portlets it contains, if necessary.

Overview of working with dashboards in a multi-partition environment

When you have multiple partitions configured, follow these guidelines when you set up dashboards.

1. Before working with dashboards, associate one or more groups with each partition, and assign the appropriate users to each group.

Only the platform_admin user, or another user with the PlatformAdminRole permissions can perform this task.

2. For each partition, ensure that at least one user has the Administer Dashboards permission, and make a note of these user names.

The Unica Platform AdminRole role has this permission by default, but you might want to create a role with more restricted access for dashboard administrators. These dashboard administrators can administer all dashboards within their partition.

3. For each partition configured in your system, do the following.
 - a. Use an account that is a member of the partition and that can administer all dashboards in a partition to sign in to Unica.

Refer to the list of users you created in the previous step.

- b. On the **Settings > Dashboard portlets** page, enable pre-defined portlets as needed.
- c. On the Dashboard Administration page, create the needed dashboards and add portlets.
- d. For each non-global dashboard, assign users who can view the dashboard.

You can assign individual users or groups to the dashboard.

- e. For each dashboard, assign one or more users as dashboard administrator.

Quick link portlets

Quick links are pre-defined links to Unica products. Some quick links enable users to perform basic actions in the Unica product within the dashboard, without navigating to the product. You can configure portlets that contain a set of quick links that you choose.

Quick links for Unica products are installed when the product is installed. As of the 9.0.0 release, only Unica Plan provides quick links. The same security considerations apply for quick links as for pre-defined portlets.

To add a quick links portlet to one of your dashboards, click **Manage Portlets > Create Quick Link Portlet** and select the quick links you want to include.

The following table describes the quick links available when Unica Plan is installed.

Table 92. List of quick link portlets

Quicklink	Function
Create New Project Request	Opens up a popup window where you can choose a project template to create a Project Request. You can also click Continue to open the Project Request wizard in the application.
Create New Project	Opens up a popup window where you can choose a Project template to create a Project. You can also click Continue to open the Project wizard in the application.
Add Invoice	Opens the Add Invoice wizard in the application.
Projects	Opens the Project List page in the application.
Reports	Opens the Analytics > Operational Analytics page.
Resource Library	Opens the Asset Library page in the application.
Approvals	Opens the Approvals List page in the application.

Creating a quick link portlet

Use this procedure create a quick link portlet.

1. In the dashboard to which you want to add a quick link portlet, click **Manage Portlets**.
A Manage Portlet page opens, listing the pre-defined portlets.
2. Click **Create Quick Link Portlet**.
3. Enter a portlet name and description, and select the quick links you want to include in the portlet.
4. Click **Save** to finish creating the portlet and to add it to the dashboard.

Preparing the URL from a Digital Analytics for On Premises report

Use this procedure for reports in a Digital Analytics for On Premises installation.

1. In Digital Analytics for On Premises, display the report you want to export.

If you are using a Digital Analytics for On Premises dashboard, only the top left report on the dashboard is exported.

2. Click the **Export** icon  located in the toolbar at the upper right of the report.

The Export options window opens.

3. Complete the fields as follows.

- Select **Portlet URL** from the **Export Type** drop-down.
- Select `Web Browser` from the **Format of Report** drop-down.
- Specify the number of values to include in the report.
- Specify the width of the report graphic, in pixels. Path reports self-adjust their size, regardless of the width you specify. Stacked bar reports automatically increase the width you specify by 30%.
- Choose to hide the report header, as the portlet has a title that you can edit.

4. Click **Export**.

The report URL is displayed in a dialog box.

5. Copy the URL and paste it into a text editor.

6. Add the following to the beginning of the report URL:

`Your_HCL_Unica_URL/suiteSignOn?target=`

where `Your_HCL_Unica_URL` is the login URL for your installation of Unica.

For example, suppose you have the following information.

- Your report URL is `MyReportURL`
- The login URL for your installation of Unica is `http://myHost.myDomain:7001/unica`

Your final URL would be `http://myHost.myDomain:7001/unica/suiteSignOn?target=MyReportURL`

Preparing the URL from an IBM® Cognos® dashboard report

The format of an IBM® Cognos® dashboard portlet URL is as follows.

For information about creating dashboard reports with IBM® Cognos®, see the Unica Reports Installation and Configuration Guide.

```
http(s)://HOST.DOMAIN:port/unica/reports/jsp/dashboard_portlet.jsp?
product=Product& report=ReportName
```

where

- *Product* is the name of the Unica application's subfolder in the **Unica Dashboards** folder on the IBM® Cognos® system. That is: Campaign, Interact, or Plan for Unica Plan. (Plan was the previous name of the Unica Plan application.)
- *ReportName* is the name of the dashboard report. For example: Campaign Performance Comparison

For example,

```
http://serverX.example.com:7001/unica/reports/jsp/dashboard_portlet.jsp?
product=Campaign&report=Campaign Performance Comparison
```

If you have scheduled the report, add the following to the end of the URL:

```
&isView=true
```

Preparing the URL from a Digital Analytics report

Use this procedure for Digital Analytics reports.

If you want users to be able to view Digital Analytics reports in dashboards without having to log in to Digital Analytics, you must enable single sign-on between Unica and Digital Analytics.

1. Log in to Digital Analytics and navigate to the report that you want to add as a portlet.
2. Copy the URL shown in your browser.

The link is copied to your clipboard and is ready to be pasted into the IBM® Digital Analytics URL field in the Create Custom Portlet window in Unica Platform.

To ensure the URL is not overwritten should you copy something else before using it to create a portlet, you can paste it into a text editor.

Adding a custom portlet to a dashboard

Perform this procedure to add a custom portlet to a dashboard.

Before performing this procedure, you should have done the following.

- Prepared a URL as described elsewhere in this section
- Added the URL to the `Platform_Admin_URL.properties` file, which is located in the `conf` directory under your Unica Platform installation
- Stopped and restarted the Unica Platform web application

1. In Unica, select **Dashboard** and then select the tab for the dashboard you want to work with.

2. Click **Manage Portlets**.

A **Manage Portlets** window opens.

3. Click **Create Custom Portlet**.

A **Create Custom Portlet** window opens.

4. Do one of the following sets of steps, depending on the type of portlet you are adding.

If you are creating a portlet that is not a Digital Analytics report portlet, do the following.

- For the **Type**, select **Custom**.
- Complete the **Name** and **Description** fields.
- Paste the contents of your clipboard (which contains the URL you obtained earlier) into the **URL** field.

If you are creating a Digital Analytics report portlet, do the following.

- For the **Type**, select **IBM Digital Analytics**.
- Complete the **Name** and **Description** fields.
- Paste the contents of your clipboard (which contains the URL you obtained earlier) into the **IBM Digital Analytics URL** field.

5. Click **Save**.

The window closes and you return to the Administration tab. The new portlet is located in the upper left corner, where it may overlay a previously added portlet. Click and drag the portlet heading to place the portlet in an appropriate position in the dashboard.

Overview of the portlet creation process

This section provides an overview of the steps for creating a portlet, which are described in detail elsewhere in this guide.

See the related references if you need more information about performing this procedure.

1. Obtain and prepare the URL of the page you want to use as a portlet.

To do this, you obtain the URL and modify it as needed.

You can create portlets from the following sources.

- Digital Analytics for On Premises report
- IBM Cognos® report
- Digital Analytics report
- NetInsight OnDemand report and pages on the internet or your company intranet

2. Add the URL to the `Platform_Admin_URL.properties` file.

The `Platform_Admin_URL.properties` file is located in the `conf` directory under your Unica Platform installation.

3. Stop and restart the Unica Platform web application.

4. Add the portlet to a dashboard.

Scheduling a dashboard report

To schedule a dashboard report (either a pre-defined or user-created portlet), you must first create a view and schedule it, and then configure the portlet as described here.



Note: You can schedule only those reports that are not filtered by user.

1. In Cognos®, copy the report and save it under a new name.
2. In Cognos®, open the copied report and save it as a view with the same name as the original report. Save it in the *Unica Dashboard/Product* folder, where *Product* is the appropriate product folder
3. In Cognos®, schedule the view.
4. In Unica, add the report to the dashboard, if you have not done so already.
5. Only if the report is one of the pre-defined portlets, do the following in Unica.
 - On the Dashboard Administration page, click the **Edit portlet** icon next to the portlet.
 - Select **Yes** next to **Has this report been scheduled?**
 - Click **Save**.

Preparing the URL from an IBM® Cognos® dashboard report

The format of an IBM® Cognos® dashboard portlet URL is as follows.

For information about creating dashboard reports with IBM® Cognos®, see the Unica Reports Installation and Configuration Guide.

```
http(s)://HOST.DOMAIN:port/unica/reports/jsp/dashboard_portlet.jsp?  
product=Product& report=ReportName
```

where

- *Product* is the name of the Unica application's subfolder in the **Unica Dashboards** folder on the IBM® Cognos® system. That is: Campaign, Interact, or Plan for Unica Plan. (Plan was the previous name of the Unica Plan application.)
- *ReportName* is the name of the dashboard report. For example: Campaign Performance Comparison

For example,

```
http://serverX.example.com:7001/unica/reports/jsp/dashboard_portlet.jsp?  
product=Campaign&report=Campaign Performance Comparison
```

If you have scheduled the report, add the following to the end of the URL:

```
&isView=true
```

Difference between the Unica Campaign Schedule process and Unica Scheduler

Starting with the 8.0 release of Unica Platform, the Unica Scheduler is intended to replace the Unica Campaign Schedule process for scheduling runs of an entire flowchart. The Unica Scheduler is more efficient, as it does not consume any server system resources when the flowchart is not actually running.

The Unica Scheduler starts a flowchart even if it is not running, while the Unica Campaign Schedule process in a flowchart works only if the flowchart is running.

The Unica Campaign Schedule process is preserved for full compatibility with earlier versions, and for other use cases not handled by the Unica Scheduler. For example, you might want to use the Unica Campaign Schedule process to send Unica Campaign triggers or to delay execution of dependent processes.

Do not use the Unica Scheduler to schedule a flowchart that uses the Unica Campaign Schedule process as the top-level process that starts a flowchart run. Typically, only one or the other is necessary. However, if the Schedule process appears in a flowchart that is started by the Unica Scheduler, it functions as configured; conditions required by the Unica Scheduler and the Schedule process must be met before subsequent processes run.

Unlike the Unica Scheduler, the Unica Campaign Schedule process can send external triggers to call command-line scripts. The Unica Scheduler can send triggers only to its own schedules.

The Unica Scheduler

The Unica Scheduler enables you to configure a process to run at intervals that you define.

Items that you can schedule

You can schedule the following.

- Unica Campaign flowchart runs



Note: The Unica Scheduler is completely independent of the Schedule process in Unica Campaign.

- Unica Optimize optimization session and post-optimization flowchart runs
- IBM eMessage mailings
- Unica Plan bulk deactivations
- Calls to external APIs
- Unica alerts and notifications
- External batch or shell scripts

Schedules and runs

The scheduler uses two basic concepts: schedules and runs.

- A schedule is any task that you want to run once or on a recurring basis. When you define a schedule you specify the Unica object, the start and end dates, and optionally, the frequency with which the task is run (called a recurrence pattern).
- A run is an execution instance of a schedule.

Types of schedules

There are three types of schedules.

- Time-based - Runs occur at specified times.
- Trigger-based - Runs occur when a schedule receives a specified trigger (for example, when another schedule sends a trigger on success or failure of its run, or when the scheduler utility sends a trigger).
- Multiple-run-based - Runs are dependent on other schedules, and occur only when multiple other schedules have finished their runs

Schedule notifications

You can set up notifications that are sent to yourself for schedules you create, and administrators can set up notifications that are sent to groups of users for schedules created by anyone.

Schedule triggers that are sent from an external script

The Unica Scheduler can respond to triggers sent by an external application. The `scheduler_console_client` utility enables this feature. This utility issues triggers that can launch one or more schedules set up to listen for that trigger.

Because `scheduler_console_client` is a batch script application, it can be called by external applications, possibly using another batch script.

For example, if you set up a schedule that is listening for a trigger "T1," you could run the `scheduler_console_client` utility with the following command to send the T1 trigger:

```
scheduler_console_client.bat -v -t T1
```

The utility can provide the following information.

- A list of the schedules that are configured to listen for any given trigger.
- Whether it has successfully sent the trigger. Note that the utility cannot report whether the schedule that is listening for the trigger executed successfully. That information is available on the scheduler management pages.

You can not use this utility to set up a schedule to listen for a trigger or to modify a trigger for which a schedule is listening. You must perform these actions in the scheduler user interface.

Example script

Here is an example of a script to that causes the `scheduler_console_client` utility to issue the string "example_trigger". This trigger would set off a run of a schedule set up to listen for "example_trigger".

You could call a script like this from an external application when that application generates an event.

The example script assumes that the script is in the same directory as the utility.

```
@rem*****
@rem This script is used to call the Platform
@rem scheduler_console_client.
@rem*****

echo Now starting scheduler trigger.
set JAVA_HOME=c:\jdk15_12
call scheduler_console_client.bat -v -t example_trigger

@rem*****
```

Security considerations

Scheduling within the enterprise applications is considered to be an administrator's activity. It is assumed that any user who has execute permission in the host operating system for the `scheduler_console_client` utility is also authorized to issue triggers.

To prevent any user from using this utility to issue a trigger, you should revoke execute permission for the `scheduler_console_client` utility for that user.

scheduler_console_client

Jobs configured in the Unica Scheduler can be listed and kicked off by this utility, if they are set up to listen for a trigger.

What to do if SSL is enabled

When the Unica Platform web application is configured to use SSL, the JVM used by the `scheduler_console_client` utility must use the same SSL certificate that is used by the web application server on which the Unica Platform is deployed.

Take the following steps to import the SSL certificate

- Determine the location of the JRE used by the `scheduler_console_client`.
 - If `JAVA_HOME` is set as a system environment variable, the JRE it points to is the one used by the `scheduler_console_client` utility.
 - If `JAVA_HOME` is not set as a system environment variable, the `scheduler_console_client` utility uses the JRE set either in the `setenv` script located in the `tools/bin` directory of your Unica Platform installation, or on the command line.
- Import the SSL certificate used by the web application server on which the Unica Platform is deployed to the JRE used by `scheduler_console_client`.

The Sun JDK includes a program called `keytool` that you can use to import the certificate. Consult the Java™ documentation for complete details on using this program, or access the help by entering `-help` when you run the program.

- Open the `tools/bin/schedulerconsoleclient` file in a text editor and add the following properties. These differ depending on the web application server on which Unica Platform is deployed.
 - For WebSphere®, add these properties to the file.
 - Djavax.net.ssl.keyStoreType=JKS
 - Djavax.net.ssl.keyStore="Path to your key store JKS file"
 - Djavax.net.ssl.keyStorePassword="Your key store password"
 - Djavax.net.ssl.trustStore="Path to your trust store JKS file"
 - Djavax.net.ssl.trustStorePassword="Your trust store password"
 - DisUseIBMSSLSocketFactory=false
 - For WebLogic, add these properties to the file.
 - Djavax.net.ssl.keyStoreType="JKS"

```
-Djavax.net.ssl.trustStore="Path to your trust store JKS file"
```

```
-Djavax.net.ssl.trustStorePassword="Your trust store password"
```

If the certificates do not match, the Unica Platform log file contains an error such as the following.

```
Caused by: sun.security.provider.certpath.SunCertPathBuilderException: unable  
to find valid certification path to requested target
```

Prerequisites

The Unica Platform must be installed, deployed, and running.

Syntax

```
scheduler_console_client -v -t trigger_name user_name
```

```
scheduler_console_client -s -t trigger_name user_name
```

Commands

-v

List the scheduler jobs configured to listen for the specified trigger.

Must be used with the `-t` option.

-s

Send the specified trigger.

Must be used with the `-t` option.

Options

```
-t trigger_name
```

The name of the trigger, as configured in the scheduler.

Example

- List jobs configured to listen for a trigger named `trigger1`.

```
scheduler_console_client -v -t trigger1 myLogin
```

- Execute jobs configured to listen for a trigger named `trigger1`.

```
scheduler_console_client -s -t trigger1 myLogin
```

Scheduler throttling

Throttling is used to manage performance when a large number of processes are likely to place high demands on the system. Throttling is based on scheduler groups that you set up on the **Settings > Configuration** page. You assign a throttling threshold to a group, and associate schedules with that group.

The throttling threshold is the highest number of runs associated with that group that can run concurrently. To reduce resource consumption on the server, you can set the throttling threshold to a smaller value. Only schedules created in the Unica Scheduler are subject to throttling.

Unlimited threshold in the default group

All schedules must belong to a throttling group. If you do not want to enable throttling for a schedule, make it a member of the Default scheduler group (the default selected option in the **Scheduler Group** field when you create a schedule). This group has a high throttling threshold, which effectively means that no throttling is in place.

Throttling exception

If you run a flowchart from within Unica Campaign or by using the Unica Campaign `unica_svradm` utility, these runs do not count in the throttling threshold, and they begin execution immediately.

Throttling examples

- If system resources are a concern, you can use throttling to manage the load on a server. For example, if many complex Unica Campaign flowcharts must be run, you can assign them to a throttling group that limits the number of flowcharts that can be run at the same time. This throttling helps to manage the load on the Unica Campaign server or the marketing database.
- You can use throttling to set priorities for schedules. By assigning high-priority schedules to a group with a high throttling threshold, you ensure that runs of these schedules are performed using system resources as efficiently as possible. You should assign lower-priority schedules to groups with lower throttling thresholds.
- If you have a flowchart that is scheduled with a recurrence pattern, you can use throttling to ensure that runs occur in sequence, without overlapping. For example, suppose you have scheduled a flowchart with a recurrence pattern set to execute a run every hour for 10 hours. If the flowchart takes more than one hour to complete a run, the next run could attempt to begin before the previous run is completed, resulting in failure because the still running flowchart would be locked. To ensure that this does not happen, you can create a throttling group with a threshold of 1, and assign the flowchart's schedule to this group.

Setting up throttling for the Unica Scheduler

You must set up a throttling group for each type of object being scheduled.

1. On the Configuration page, navigate to one of the throttling group templates under `Platform > Scheduler > Schedule registrations > [Product] > [Object] > Throttling group`.
2. Create a category from the throttling group template.

The number you set for the `Throttling threshold` property is the highest number of runs associated with that group that can execute concurrently. Any schedules eligible to run that exceed the throttling threshold are queued to run in the order in which the run notification is received by the scheduler.

The configured scheduler groups appear in the **Scheduler Group** drop-down list in the Scheduler user interface for creating and editing schedules.

You must create a throttling group for each type of object whose runs you want to control in this way. For example, flowchart throttling groups are available only for scheduling flowcharts; mailing throttling groups are available only for scheduling mailings.

3. Assign one or more schedules to the group, as needed.

Whitelist prerequisite for external tasks (with FixPack 10.0.0.1 only)

Only if you have applied Unica Platform FixPack 10.0.0.1, a whitelist prerequisite applies to any external tasks that you create to schedule API calls or scripts.

Before you can schedule an external task, you must add the API or script to a whitelist located in the `conf` directory under your Unica Platform installation.

Adding an API to the whitelist

Only if you have applied Unica Platform FixPack 10.0.0.1, perform this procedure before you create any external tasks that schedule an API call.

1. Open and edit the whitelist file for APIs in a text editor.

The whitelist file for APIs `Platform_Admin_Scheduler_API.properties`. This file is located in the in the `conf` directory under your Unica Platform installation.

2. Enter the URI of the API you plan to schedule, and if query parameters are used, include these parameter names, without including values.

For example suppose you want to schedule the following API call, using all of the query parameters shown.

```
http://www.example.com/tickets?  
fields=id&state=open&sort=updated_at
```

You would make the following entry in the whitelist file, listing all of the parameters.

```
http://www.example.com/tickets?fields&state&sort
```

With this whitelist entry, you can schedule API calls that use some or all of the listed parameters. For example:

- `http://www.example.com/tickets`
- `http://www.example.com/tickets?fields=id`
- `http://www.example.com/tickets?fields=id&state=open`
- `http://www.example.com/tickets?fields=id&state=open&sort=updated_at`
- `http://www.example.com/tickets?fields=id&sort=updated_at`
- `http://www.example.com/tickets?fields=id&state=open`

API calls that use non-listed query parameters cannot be scheduled. Scheduler validation fails if any parameters are used that are not present in the whitelist.

3. Save and close the whitelist file.

Now you can schedule the API call on the Schedules tab of the **Settings > Schedule management** page.

Adding a script to the whitelist

Only if you have applied Unica Platform FixPack 10.0.0.1, perform this procedure before you create any external tasks that schedule a script.

The script must be on the web application server where Unica Platform is deployed.

1. Open the whitelist file for scripts in a text editor.

The whitelist file for scripts is

`Platform_Admin_Scheduler_Scripts.properties`. This file is located in the `conf` directory under your Unica Platform installation.

2. Enter the full path of the batch or shell script you plan to schedule, and include the number of parameters that are used in the script you are scheduling.

For example, suppose you want to schedule a script that is named `RunETLJobs.bat` and that takes these three parameters: `username`, `password`, `db_table`.

You would make the following entry in the whitelist file. The entry includes the absolute path of the script, followed by a space and the number of parameters used. The parameter count must exactly match the number of parameters that are used in the scheduled script.

```
C:\Scripts\RunETLJobs.bat 3
```

When you create the schedule, in the **Run parameters** field you specify the parameter names between double number signs (##) followed by a space, as shown in the following example.

```
C:\Scripts\RunETLJobs.bat ##username## ##password##  
##db_table##
```

3. Save and close the whitelist file.

Now you can schedule the script on the Schedules tab of the **Settings > Schedule management** page.

Time zone support

You can schedule runs to occur in the context of any one of a large number of worldwide time zones.

When you create a schedule, the default is always the time zone of the server on which Unica Platform is installed. However, you can select from any other time zones listed in the **Select time zone** drop down list. These options are expressed as GMT times followed by the commonly used term for that time zone. For example, (GMT-08:00) Pitcairn Islands or (GMT-08:00) Pacific Time (US & Canada).


The selected time zone is applied to all aspects of the schedule, including the following.

- Information shown on the Schedules and Runs tabs
- Recurrence patterns and triggers

Schedules that depend on completion of multiple runs

You can configure a schedule to run only when multiple other schedules have finished their runs by using the **On completion of other tasks** option in the **When to start** drop down list.

For example, suppose you have a schedule, S1, that is set up with a recurrence pattern. S1 has a trigger that is sent every time an S1 run completes successfully. Three schedules, S2, S3, and S4, are configured to start when they receive the outbound trigger from S1. You can set up an additional schedule, S5, that runs when S2, S3, and S4 complete successfully. S5 runs only when all three of the runs on which it is dependent complete. The following diagram illustrates this example.



To set up a scenario like the one described in the example, you would configure S5 using the **On completion of other tasks** option in the **When to start** drop down list.

When you configure a run to be dependent on other runs in this way, you must keep in mind the following considerations.

- The schedules on which the schedule you are configuring depends must be non-recurring. In the example above, S2, S3, and S4 must be non-recurring. However, because S1 recurs, S2, S3, and S4 effectively recur, based on S1 runs.
- The schedule that is dependent on other schedules must also be non-recurring. In the example, S5 must be non-recurring. Again, because S1 recurs, S5 effectively recurs as well.

- The schedule that is dependent on other schedules cannot be used as one of the criteria in the **On completion of other tasks** option for any other schedule. In the example, S5 cannot be used as a criterion in the **On completion of other tasks** option for any other schedule.
- If you want to delete a schedule that is configured with the **On completion of other tasks** option, you must first change the configuration to remove the **On completion of other tasks** option. Then you can delete the schedule.

To create a schedule wizard

This section describes in detail the pages you use when you create a schedule.

The following table describes the fields you use when you schedule runs of Unica Campaign flowcharts, IBM eMessage mailings, Unica Optimize sessions, external scripts, and API calls.

Table 93. Fields in the create a schedule wizard

Field	Description
Select a task type	<p>The type of object to be scheduled. The following options are available.</p> <ul style="list-style-type: none"> • External task - script Allows you to schedule invocation of tasks defined in batch or shell scripts external to Unica. Only if you have applied Unica Platform FixPack 10.0.0.1, the script must be listed in a whitelist file located in the <code>conf</code> directory under your Unica Platform installation. Also, the script must be on the web application server where Unica Platform is deployed. • External task - API Allows you to schedule invocation of APIs external to Unica.

Table 93. Fields in the create a schedule wizard (continued)

Field	Description
	<p>Only if you have applied Unica Platform FixPack 10.0.0.1, the API must be listed in a whitelist file located in the <code>conf</code> directory under your Unica Platform installation.</p> <ul style="list-style-type: none"> • Unica Campaign flowchart Allows you to schedule invocation of Unica Campaign flowcharts. Selecting this option takes you to the Unica Campaign list page where you select a campaign, optionally set flowchart override parameters, and schedule the flowchart run. • Unica Optimize session Allows you to schedule invocation of Unica Optimize sessions. Selecting this option takes you to the Unica Optimize sessions list page where you select a session and schedule the session. • IBM eMessage mailing Allows you to schedule invocation of IBM eMessage mailings. Selecting this option takes you to the IBM eMessage mailings list page where you select and schedule the mailing. • Unica Plan bulk deactivation Allows you to schedule bulk deactivation of projects in Unica Plan. Selecting this option takes you to the Unica Plan Administrative Settings page where you click Deactivation Administration and schedule the bulk deactivation. • Alert Allows you to schedule alerts for users of Unica. Selecting this option opens a window where you set the message title, message body, and severity. After you click Schedule this alert, you can create a schedule for the alert.

Table 93. Fields in the create a schedule wizard (continued)

Field	Description
	<p>Users can manage their notification subscriptions based on severity.</p> <ul style="list-style-type: none"> • Notification <p>Allows you to schedule notifications for users of Unica. Selecting this option opens a window where you set the message title, message body, and severity. After you click Schedule this notification, you can create a schedule for the notification.</p> <p>Users can manage their notification subscriptions based on severity.</p>
Schedule name	Enter a name for the schedule.
Scheduler group	If you have created one or more throttling groups, you can associate this schedule with a group to limit the number of runs of this schedule that can execute at the same time. Throttling groups configured on the Configuration page appear as options in this field
Description	Enter a description for the schedule.
Run parameters	<p>Used when you schedule APIs and scripts.</p> <p>Only if you have applied Unica Platform FixPack 10.0.0.1, a whitelist prerequisite applies to any external tasks that you create to schedule API calls or scripts. Before you can schedule an external task, you must add the API or script to a whitelist located in the <code>conf</code> directory under your Unica Platform installation.</p> <ul style="list-style-type: none"> • For API schedules, enter the URI, plus any parameters in the format shown in the examples. <p>API with no parameters: <code>http://example.com</code></p>

Table 93. Fields in the create a schedule wizard (continued)

Field	Description
	<p>API with parameters: <code>http://www.example.com/tickets?fields=id&state=open&sort=updated_at</code></p> <p>Currently, there is no support for Unica Platform tokens in the URI.</p> <ul style="list-style-type: none"> • For script schedules, enter the full path to the script on the Unica Platform server, plus any parameters in the format shown in the examples. Specify the parameter names between double number signs (##) followed by a space. <ul style="list-style-type: none"> ◦ Windows™ examples <p>Script with no parameters: <code>C:\Scripts\ExecuteDatabaseJob.bat</code></p> <p>Script with parameters: <code>C:\Scripts\RunETLJobs.bat ##username## ##password## ##db_table##</code></p> ◦ UNIX™ examples <p>Script with no parameters: <code>/opt/ExecuteDatabaseJob.sh</code></p> <p>Script with parameters: <code>/opt/RunETLJobs.sh ##username## ##password## ##db_table##</code></p> <p>Execution of these tasks is asynchronous. Unica Platform does not track success or failure of script and API tasks. Status indicates only whether they are launched successfully.</p>
On successful completion, send a trigger	If you want runs of this schedule to send a trigger when the run completes successfully, enter the trigger text here. Other schedules can be set to listen for this trigger.

Table 93. Fields in the create a schedule wizard (continued)

Field	Description
On error, send a trigger	If you want runs of this schedule to send a trigger when the run fails, enter the trigger text here. Other schedules can be set to listen for this trigger.
Search tags / keywords	Enter any tags you want you associate with the schedule for use in searches. Separate multiple entries with commas.
Schedule status	Whether the schedule is enabled or disabled. Disabling a schedule applies only to future or queued runs of that schedule. Any run currently underway is not affected. The default status is Enabled .
Select time zone	If you select an option other than the server default, the Start, End, and Last updated columns on the Schedule management page show both the server default time and the time in the selected zone.
When to start	<p>Select one of the following options to specify the first time the schedule runs. The start time applies only to the first run; it defines the time when a schedule is first eligible to run. The actual first run might be after the start date if any of the following conditions are present.</p> <ul style="list-style-type: none"> • The schedule is configured to wait for a trigger. • The schedule is a member of a throttling group. • The schedule uses a recurrence pattern. <ul style="list-style-type: none"> • Now • On a date and time - Select a date and time. • On a trigger - Select an existing trigger or enter a new one. If you enter a new one, you must configure a schedule to send this same string on success or failure. • On a trigger after a date - Select an existing trigger or enter a new one, and select a date and time. If you enter a new trig-

Table 93. Fields in the create a schedule wizard (continued)

Field	Description
	<p>ger, you must configure a schedule to send this same string on success or failure.</p> <ul style="list-style-type: none"> • On completion of other tasks - Select from a list of existing schedules. The schedule runs only when the selected other schedules have finished their runs.
Number of runs	<p>Select one of the following options to specify the number of runs.</p> <ul style="list-style-type: none"> • Run once only - The schedule runs one time. It is eligible to execute the run on the start date and time you specify. • Stop after n occurrences - Runs stop after the specified number of runs have occurred (whether the runs succeed or fail) or the end date arrives, whichever is first. • Stop by a date and time - Runs are initiated as many times as defined until the specified end date and time is reached. A run might execute after this time if the run execution has been delayed due to throttling constraints. • On completion of other tasks - The schedule runs only when all the other tasks selected for this option complete successfully. <p>When you click the Set up recurrences button, you can select one of the following options.</p> <ul style="list-style-type: none"> • Use a pre-defined recurrence pattern - Select a pattern from the list. The Unica Platform provides a set of pre-defined patterns, and you can create your own by adding properties on the Configuration page. • Use a simple custom recurrence pattern - Select an interval. • Use a cron recurrence expression - Enter a valid cron expression.

Schedule management

You can manage all schedules from the **Settings > Schedule management** page. You must have the Administer Scheduled tasks page permission in Unica Platform to manage schedules.

These are the tabs on the Scheduled tasks page.

- **Schedules** - On this tab you can create schedules and view or delete schedule definitions. You can click the schedule name to edit a definition, including adding notifications and enabling or disabling the schedule.
- **Runs** - On this tab you can view queued and completed runs of every schedule, cancel a queued run, and delete a run. You can click the schedule name to edit a definition, including adding notifications and enabling or disabling the schedule.

Schedules and partitions

In a multi-partition environment, you see only the schedules that are created in the partition to which you belong, unless you have the PlatformAdminRole role, which allows you to see all scheduled runs across all partitions.

Unknown status

If you see a large number of runs with a status of Unknown, you can adjust the Scheduler polling frequency by setting the **Platform | Scheduler | Maximum Unknown Status Polling Count** property on the **Settings > Configuration** page. This property specifies the number of times the Scheduler checks the status of a run before reporting a status of Unknown.

The Unknown status indicates that Unica Platform can not determine whether the job is still running, completed or failed.

If your organization has a large number of scheduled jobs, increasing polling frequency can affect performance.

The schedule list filter

You can filter the schedule list on the Runs and Schedules tabs.

You can enter text in the box at the top right of the list for a quick filter that compares your search term against the values in all of the columns in the list. If your search string is contained in any of the columns, the schedule or run is included in the search result.

For advanced search, you can click **Edit the schedule list filter** to open a window where you can set criteria to evaluate against the attributes of the listed schedules or runs.

Disabling and enabling multiple schedules (with FixPack 10.0.0.1 only)

If you have applied Unica Platform FixPack 10.0.0.1, you can select multiple schedules on the Schedules tab and disable or enable them by clicking the **Disable** or **Enable** button at the top of the list.

You can use this bulk disable and enable feature in conjunction with the filter to obtain a list of the schedules you want to disable or enable. For example, if you added search tags when you created schedules, you can filter the list to show only schedules with a specific tag.

Then you can select all of these schedules and disable or enable them with a single click.

When you disable a scheduled task, any schedules that depend on a trigger from the disabled task are not disabled, but they will not run because they will not receive the trigger.

The Schedule management pages

You access the scheduler management pages by selecting **Settings > Schedule Management** or by selecting **View when scheduled** from a flowchart's **Run** menu.

The Schedules tab

Table 94. Fields and links on the Schedules tab

Field or link	Description
 Disable	Disable one or more selected schedules. Available only if you have applied Unica Platform FixPack 10.0.0.1.

Table 94. Fields and links on the Schedules tab (continued)

Field or link	Description
 Enable	Enable one or more selected schedules. Available only if you have applied Unica Platform FixPack 10.0.0.1.
Create a schedule	Click to open a wizard where you can set up a schedule.
Edit the schedule list filter	Click to create an advanced filter for the list.
Delete	Delete one or more selected schedules. You can select schedules by clicking in the column at the left of the schedule. To select all schedules, click at the top of the left side column.
Refresh	Click to refresh the list.
Filter	Click to create a simple filter for the list.
Schedule name	The schedule of which the run is an instance.
Schedule state	Whether the schedule is enabled or disabled.
Scheduled item	The name of the object to be run.
Item type	The type of object to be run.
Created by	The user name of the account that created the schedule.
Start trigger	If the schedule depends on a trigger, the trigger that causes the schedule to run.
Start	Date and time when the first run of this task is scheduled.
Recurrence pattern	A description of the recurrence pattern.
End	Date and time when the last run of this task is scheduled.

Table 94. Fields and links on the Schedules tab (continued)

Field or link	Description
	 Note: Applies to recurring scheduled tasks only.
Previous 1 and next 2 runs	<p>Date and time of the previous run and next two scheduled runs.</p>  Note: Applies to recurring scheduled tasks only. <p>The information about previous one and next two scheduled runs is shown as per the scheduler definition. It is not currently validated against the exclusion rules.</p>
Dependencies	If the scheduled object depends on other objects, they are listed here.
On success trigger	The string that is sent if the product reports that a run of this schedule has completed successfully. This field is blank if no on success trigger is specified.
On failure trigger	The string that is sent if the product reports that a run of this schedule has failed. This field is blank if no on failure trigger is specified.

The Runs tab

Table 95. Fields and links on the Runs tab

Field or link	Description
Edit the schedule list filter	Click to create an advanced filter for the list.
Delete	Delete one or more selected schedules. You can select schedules by clicking in the column at the left of the schedule. To select all schedules, click at the top of the left side column.
Mark as cancelled	Cancel one or more selected schedules.

Table 95. Fields and links on the Runs tab (continued)

Field or link	Description
Refresh	Click to refresh the list.
Filter	Click to create a simple filter for the list.
Run id	The identification number assigned to the run in the Unica Platform system tables.
Schedule name	The name specified for the schedule by its creator.
Scheduled item	The name of the object to be run.
Item type	The type of object to be run.
Start	The date and time when the run started.
Last updated	The date and time when the information for this run was updated.
Execution state	<p>State of the run as defined in the scheduler, as follows.</p> <ul style="list-style-type: none"> • Scheduled - The run has not begun. • Queued - The scheduler has started the run, but the Unica product has not begun executing the scheduled run due to throttling constraints. • Completed- The run has completed and has returned a status of Failed or Succeeded. • Cancelled - A user has cancelled a run by clicking Mark as Cancelled on the Scheduled Runs page. If the run was queued when the user marked it as cancelled, it does not execute. If the run was executing, this action does not stop the run, but it is marked as cancelled, and any triggers configured for this run are not sent. Also, runs that depend on the cancelled run do not execute. • Unknown - Indicates that Unica Platform can not determine whether the job is still running, completed or failed.

Table 95. Fields and links on the Runs tab (continued)

Field or link	Description
Run status	Status of the object's run as defined by the product executing the run. If the run sends a status of Cancelled, and the run is later started again and sends any other status to the scheduler, the status is updated in this field.
Details	Information about the run as provided by the product. For example, for a flowchart run, details include the flowchart name and ID, the error if the run fails, and the elapsed time if the run succeeds.

Edit the schedule list filter - Schedules

Table 96. Edit the schedule list filter on the Schedules tab

Column	Description
Filter by search tags / keywords	Select this check box if you want to include search tags or keywords in your filter. The string you enter here is matched with strings entered in the Search tags / keywords fields when schedules are created.
Search tags / keywords	Enter the search tags or keywords you want to use in your filter.
Filter on other criteria	Select this check box if you want to include additional criteria in your filter.
Run metadata	<p>Select one of the following options to include in your rule.</p> <p>The options are:</p> <ul style="list-style-type: none"> • Schedule name • Schedule state • Item type

Table 96. Edit the schedule list filter on the Schedules tab (continued)

Column	Description
	<ul style="list-style-type: none"> • Created by • Scheduled item
Condition	<p>Select one of the following options to determine how your rule is evaluated.</p> <ul style="list-style-type: none"> • Matches • Starts with • Ends with • Contains
Value	<p>Enter or select the value you want to apply to the rule. The options vary depending on the metadata you select for the rule.</p> <ul style="list-style-type: none"> • Schedule name Enter any characters. • Schedule state Value options are Enabled and Disabled. • Item type Value options are the various schedule types. • Created by Enter any characters. Your value is compared with user login names. • Scheduled item Enter any characters. The string you enter here is compared with the text in the Scheduled item column.
And / Or	Select one of these operators for each rule you create.

Edit the schedule list filter - Runs

Table 97. Edit the schedule list filter on the Runs tab

Column	Description
Filter based on time	Select this check box if you want to show runs that occurred within a specified time interval.
Time zone	If you select an option other than the server default, the search uses the selected time zone to calculate which schedules fall within the date range you specify.
List runs for the last n instances	For recurring runs, specify how many previous runs to show in the list.
List runs from	Specify a time interval for the runs shown in the list.
Filter on other criteria	Select this check box if you want to include additional criteria in your filter.
Run metadata	<p>Select one of the following options to include in your filter.</p> <p>The options are:</p> <ul style="list-style-type: none"> • Schedule name • Execution state • Run status • Scheduled item
Condition	<p>Select one of the following options to determine how your criteria are evaluated.</p> <ul style="list-style-type: none"> • Matches • Starts with • Ends with • Contains

Table 97. Edit the schedule list filter on the Runs tab (continued)

Column	Description
Value	<p>Enter or select the value you want to apply to the filter. The options vary depending on the metadata you select for the rule.</p> <ul style="list-style-type: none"> • Schedule name Enter any characters. • Execution state Value options are: <ul style="list-style-type: none"> ◦ Queued ◦ Running ◦ Completed ◦ Unknown ◦ Cancelled • Run status Value options are Succeeded, Running, Cancelled, Failed, and Unknown. • Scheduled item Enter any characters. The string you enter here is compared with the text in the Scheduled item column.
And / Or	Select one of these operators for each rule you create.

scheduler_console_client

Jobs configured in the Unica Scheduler can be listed and kicked off by this utility, if they are set up to listen for a trigger.

What to do if SSL is enabled

When the Unica Platform web application is configured to use SSL, the JVM used by the `scheduler_console_client` utility must use the same SSL certificate that is used by the web application server on which the Unica Platform is deployed.

Take the following steps to import the SSL certificate

- Determine the location of the JRE used by the `scheduler_console_client`.
 - If `JAVA_HOME` is set as a system environment variable, the JRE it points to is the one used by the `scheduler_console_client` utility.
 - If `JAVA_HOME` is not set as a system environment variable, the `scheduler_console_client` utility uses the JRE set either in the `setenv` script located in the `tools/bin` directory of your Unica Platform installation, or on the command line.
- Import the SSL certificate used by the web application server on which the Unica Platform is deployed to the JRE used by `scheduler_console_client`.

The Sun JDK includes a program called `keytool` that you can use to import the certificate. Consult the Java™ documentation for complete details on using this program, or access the help by entering `-help` when you run the program.

- Open the `tools/bin/schedulerconsoleclient` file in a text editor and add the following properties. These differ depending on the web application server on which Unica Platform is deployed.
 - For WebSphere®, add these properties to the file.
 - Djavax.net.ssl.keyStoreType=JKS
 - Djavax.net.ssl.keyStore="Path to your key store JKS file"
 - Djavax.net.ssl.keyStorePassword="Your key store password"
 - Djavax.net.ssl.trustStore="Path to your trust store JKS file"
 - Djavax.net.ssl.trustStorePassword="Your trust store password"
 - DisUseIBMSSLSocketFactory=false
 - For WebLogic, add these properties to the file.
 - Djavax.net.ssl.keyStoreType="JKS"

```
-Djavax.net.ssl.trustStore="Path to your trust store JKS file"
```

```
-Djavax.net.ssl.trustStorePassword="Your trust store password"
```

If the certificates do not match, the Unica Platform log file contains an error such as the following.

```
Caused by: sun.security.provider.certpath.SunCertPathBuilderException: unable  
to find valid certification path to requested target
```

Prerequisites

The Unica Platform must be installed, deployed, and running.

Syntax

```
scheduler_console_client -v -t trigger_name user_name
```

```
scheduler_console_client -s -t trigger_name user_name
```

Commands

-v

List the scheduler jobs configured to listen for the specified trigger.

Must be used with the `-t` option.

-s

Send the specified trigger.

Must be used with the `-t` option.

Options

-t *trigger_name*

The name of the trigger, as configured in the scheduler.

Example

- List jobs configured to listen for a trigger named `trigger1`.

```
scheduler_console_client -v -t trigger1 myLogin
```

- Execute jobs configured to listen for a trigger named `trigger1`.

```
scheduler_console_client -s -t trigger1 myLogin
```

Schedule triggers that are sent from an external script

The Unica Scheduler can respond to triggers sent by an external application. The `scheduler_console_client` utility enables this feature. This utility issues triggers that can launch one or more schedules set up to listen for that trigger.

Because `scheduler_console_client` is a batch script application, it can be called by external applications, possibly using another batch script.

For example, if you set up a schedule that is listening for a trigger "T1," you could run the `scheduler_console_client` utility with the following command to send the T1 trigger:

```
scheduler_console_client.bat -v -t T1
```

The utility can provide the following information.

- A list of the schedules that are configured to listen for any given trigger.
- Whether it has successfully sent the trigger. Note that the utility cannot report whether the schedule that is listening for the trigger executed successfully. That information is available on the scheduler management pages.

You can not use this utility to set up a schedule to listen for a trigger or to modify a trigger for which a schedule is listening. You must perform these actions in the scheduler user interface.

Example script

Here is an example of a script that causes the `scheduler_console_client` utility to issue the string "example_trigger". This trigger would set off a run of a schedule set up to listen for "example_trigger".

You could call a script like this from an external application when that application generates an event.

The example script assumes that the script is in the same directory as the utility.

```
@rem*****
@rem This script is used to call the Platform
@rem scheduler_console_client.
@rem*****

echo Now starting scheduler trigger.
set JAVA_HOME=c:\jdk15_12
call scheduler_console_client.bat -v -t example_trigger

@rem*****
```

Security considerations

Scheduling within the enterprise applications is considered to be an administrator's activity. It is assumed that any user who has execute permission in the host operating system for the `scheduler_console_client` utility is also authorized to issue triggers.

To prevent any user from using this utility to issue a trigger, you should revoke execute permission for the `scheduler_console_client` utility for that user.

Creating a category from a template

Use this procedure to create a category from a template on the Configuration page.

1. On the Configuration page, navigate to the template category you want to duplicate.

Unlike other categories, template category labels are in italics and enclosed in parentheses.

2. Click the template category.
3. Enter a name in the **New category name** field (required).

4. You can edit properties within the new category now, or later.
5. Click **Save changes** to save the new configuration.

The new category appears in the navigation tree.

Setting up throttling for the Unica Scheduler

You must set up a throttling group for each type of object being scheduled.

1. On the Configuration page, navigate to one of the throttling group templates under `Platform > Scheduler > Schedule registrations > [Product] > [Object] > Throttling group`.
2. Create a category from the throttling group template.

The number you set for the `Throttling threshold` property is the highest number of runs associated with that group that can execute concurrently. Any schedules eligible to run that exceed the throttling threshold are queued to run in the order in which the run notification is received by the scheduler.

The configured scheduler groups appear in the **Scheduler Group** drop-down list in the Scheduler user interface for creating and editing schedules.

You must create a throttling group for each type of object whose runs you want to control in this way. For example, flowchart throttling groups are available only for scheduling flowcharts; mailing throttling groups are available only for scheduling mailings.

3. Assign one or more schedules to the group, as needed.

SAML 2.0 single sign-on

Unica Platform supports SAML 2.0 based single sign-on.

In this mode, Unica users can be authenticated against any external or corporate identity provider that follows the standard SAML 2.0 protocol. Identity providers generate the SAML assertion, which is then used by Unica Platform to allow users to log in. Therefore, a fully functional SAML 2.0 IdP server is a prerequisite for this integration.


After you set up the required configuration properties and a metadata file, users who attempt to log in through the Unica Platform login page are authenticated through your organization's SAML 2.0 Identity Provider (IdP) server.

A configuration property, **Add authenticated users to Platform**, enables automatic creation of a Unica Platform account for any authenticated user who does not have a Unica Platform account. These users are automatically added to a default user group, **ExternalUsersGroup**, which has only the **PlatformUser** role initially. Alternatively, you can specify a custom group to which users are added.

If the **Add authenticated users to Platform** property is not enabled, users must have a Unica Platform account to log in.

A Unica Platform administrator can manage group memberships and roles to configure access to Unica products for the automatically created users.

The following diagram illustrates the SAML 2.0 based single sign-on mode in Unica.



Setting SAML 2.0 configuration properties

To configure SAML 2.0 single sign-on, set properties on the **Configuration > Settings** page.

Set the following properties.

- Set the value of the **Login method** property to **SAML 2.0**.

This property is located under the **Unica Platform | Security** node.

Stop and restart the Unica Platform web application so that this change takes effect.

- Set properties located under the **Unica Platform | Security | Login method details | SAML 2.0** node as required.

See the context help for these properties for details.

Platform | Security | Login method details | SAML 2.0

Properties in this category configure single sign-on through a SAML 2.0 IdP server.

IdP server URL for single sign-in

Description

The URL of the page that appears when users open the single sign-on URL to Unica.

Default value

[CHANGE ME]

IdP server URL for single sign-out

Description

Optional. When users log out, they can be redirected to the page you set here so that their logout also logs them out of the IdP server. Your IdP server is likely to provide a URL for this purpose.

Default value

[CHANGE ME]

Error page URL for SSO error

Description

If an error occurs during single sign-on due to a configuration or integration issue, users can be redirected to the page specified here. This setting overrides the default error page provided by Unica Platform.

Default value

[CHANGE ME]

Destination URL

Description

The URL of the service provider (application) to which the user is redirected after successful authentication through the IdP server. This URL appears in every SAML request under the <AuthnRequest Destination> tag.

Default value

[CHANGE ME]

Consumer service URL

Description

The assertion consumer service URL that the service provider (application) consumes and parses for SAML assertions. This URL appears in every SAML request under the <AuthnRequest AssertionConsumerServiceURL> tag. This value can be the same as the value of the **Destination URL** property.

Default value

[CHANGE ME]

Application ID

Description

The application ID assigned to Unica Platform in the IdP server. This ID is included in every SAML request to the IdP server. This ID appears in every SAML request under the <Issuer> tag.

Default value

[CHANGE ME]

Service provider name qualifier

Description

The service provider's name qualifier. This name qualifier appears in every SAML request under the <NameIDPolicy SPNameQualifier> tag.

Default value

[CHANGE ME]

Metadata path

Description

The location of the metadata file on the Unica Platform server.

Default value

[CHANGE ME]

Entity ID

Description

The entity ID of the IdP server. Set this property to the value of *entityID* in the XML declaration at the top of the metadata file produced by the IdP server.

Unica Platform uses this ID during assertion validation to load the IdP configurations and digital certificate.

Default value

[CHANGE ME]

Attributes NVP for response parsing

Description

User account attributes are sent to Unica Platform by the IdP server. You can use this configuration property to capture attributes for users created in Unica Platform automatically, when the **Add authenticated users to Platform** property is enabled.

The IdP server might use a different name for an attribute compared to the name that Unica Platform uses. You can use this property to map the IdP attribute to the corresponding attribute in Unica Platform. This eliminates the need for code changes.

For example, the IdP server might use **emailAddress** as the name for an attribute that is named **Email** in Unica Platform. You would enter **Email=emailAddress** as a value in this property to map the attribute.

Use the following values for the user attributes in Unica Platform.

- FirstName
- LastName
- Department
- Organization
- Country
- Email
- Address1
- Address2
- Phone1

Use for work phone.

- Phone2

Use for mobile phone.

- Phone3

Use for home phone.

- AltLogin

- ExternalUsersGroup

If you enable the **Add authenticated users to Unica Platform** property, a user authenticated from the IdP server is created in Unica Platform if that user does not already have a Unica Platform account. These users are automatically added to a default user group, **ExternalUsersGroup**. However, you can also specify a custom group to which users are added. If you implement this option, set the value of the **ExternalUsersGroup** attribute to the name of the custom user group. For example, if you want a user to be added to a group named MyGroup, you would set this value to `ExternalUserGroup=MyGroup`.

Separate multiple name-value pairs with a semi-colon.

Default value

```
omit-xml-declaration=yes;
```

Process encrypted IdP response

Description

If your IdP server is configured to send encrypted responses, enable this property to indicate that the SAML response from the IdP server must be decrypted using the configured shared key before Unica Platform processes it.

If you enable this property, you must also set the value of **Shared secret key** to the secret key that is used to decrypt the response.

Default value

```
Disabled
```

Shared secret key

Description

When the **Process encrypted IdP response** option is enabled, set this property value to the path of the keystore file.

Default value

[CHANGE ME]

Key store credential holder

Description

Set this value to the login name of the Unica user account that holds the SAML shared secret in a data source.

Default value

[CHANGE ME]

Key store credential data source

Description

Set this value to the name of the data source created to hold the shared secret used for decryption. The password in the data source is the password for the key store file.

Default value

[CHANGE ME]

Certificate alias

Description

When the **Process encrypted IdP response** option is enabled, set this property value to the certificate alias of the private key stored in the keystore file. This is used in decrypting the encrypted SAML response sent by the IDP server.

Default value

[CHANGE ME]

Add authenticated users to Platform

Description

When this option is enabled, a user authenticated from the IdP server is created in Unica Platform if that user does not already have a Unica Platform account.

Newly created users are automatically added to a default group, **ExternalUsersGroup**.

The **ExternalUsersGroup** has only the Unica Platform **UserRole**. An administrator must grant additional permissions for the newly created users to access and use Unica products. An administrator can grant additional permissions by making users members of groups with different application access levels.

Alternatively, the SAML response can contain a custom user group name, and newly created users are added to this group.

When this option is disabled, a user authenticated from the IdP server can not access Unica Platform, if that user does not have an account in Unica Platform.

Default value

Disabled

Redirect to SSO

Description

When this value is **True**:

- Users who log in to Unica are redirected to the IdP single sign on page
- After users log in, they go to the standard Unica Platform landing page.
- The standard Unica Platform login screen is never available

Setting configuration properties on the Configuration page

Set configuration properties on the **Settings > Configuration** page to configure federated authentication in Unica.

Set configuration properties under the following categories.

- **Unica Platform | Security | Federated Authentication**
- **Unica Platform | Security | Federated Authentication | partitions | partition[n]**

See each property's context help or the related topic links in this section for instructions on setting the values.

Platform | Security | Federated authentication

The properties in this category are used in implementing SAML (Security Assertion Markup Language) 2.0 based federated authentication, which enables single sign-on among diverse applications.

Allow federated login

Description

Select the check box in this property to enable federated authentication in an integrated environment.

Default value

Disabled

Identity provider URL

Description

The URL of the identity provider server.

Certificate issuer

Description

The URL of the Certificate Authority that issued the certificate on the identity provider server. If you generate your own certificates using the Java™ keytool utility, set this value to the IdP server URL.

Platform | Security | Federated authentication | partitions | partition[n]

The properties in this category are used in implementing SAML (Security Assertion Markup Language) 2.0 based federated authentication between Unica applications and other and third party applications.

Keystore path

Description

The location of the trusted keystore file in the web application server.

Keystore passkey

Description

The passkey for the keystore in the web application server.

Keystore alias

Description

The alias for the keystore in the web application server.

Configuring JWT authentication between applications

JSON web token (JWT) authentication is used for Journey Designer+Unica Campaign. JWT authentication allows single sign-on between applications.

A request that comes from a calling application contains the JWT token. Unica Platform validates the request by calling the public key service (PKS). After the JWT token is validated, the request is authenticated and allowed.

This procedure applies only when the 10.0.0.1 FixPack is applied. In version 10.0.0.0, JWT authentication does not use PKS.

Use this procedure to import certificates and set configuration properties to enable JWT authentication.

1. Retrieve the certificate from the public key service (PKS) site.
2. Use the Java keytool to import the certificate into the application server JVM. If your applications are running on different JVMs, import the certificate on each application server JVM.

For example,

```
/keytool -import -file PKS_Certificate.cer -alias PKS_alias -keystore  
AppServer_JRE_home/lib/security/cacerts
```

Provide a password. The default keytool password is `changeit`.

3. Set JWT configuration properties on the **Settings > Configuration** page under **Unica Platform | Security | JWT authentication**.

Platform | Security | JWT authentication

JWT authentication is used for Journey Designer+Unica Campaign. JWT authentication allows single sign-on between applications.

Enable JWT authentication

Description

When the check box for this property is selected, JWT authentication is enabled.

This property applies only in environments where Journey Designer is integrated with Unica Campaign.

Default value

`disabled`

JWT service URL

Description

The URL of the JWT service. This value differs, depending on whether you have applied Unica Platform FixPack 10.0.0.1. Refer to the following examples.

- If you have **not** applied FixPack 10.0.0.1:

`http://IP_ADDRESS/jwt/api/v1/tokens`

- If you have applied FixPack 10.0.0.1:

`http://IP_ADDRESS/api/v1/keys`

This property applies only in environments where Journey Designer is integrated with Unica Campaign.

JWT shared secret

Description

The shared secret key that is sent from Unica Platform to the JWT service for authentication. This key is shared between Unica Platform and Journey Designer. The JWT issuer is mapped to the JWT shared secret within the JWT service.

This property applies only in environments where Journey Designer is integrated with Unica Campaign, and where Unica Platform is version 10.0.0.0 (that is where Unica Platform FixPack 10.0.0.1 is **not** applied).

JWT issuer

Description

The issuer name and version that is sent from Unica Platform to the JWT service for authentication.

This property applies only in environments where Journey Designer is integrated with Unica Campaign.

Setting up single sign-on between Unica and Digital Analytics using manual user account creation

Use this procedure to set up single sign-on between Unica and Digital Analytics using manual user account creation.

1. Determine the Digital Analytics Client ID you want to use for single sign-on between Unica and Digital Analytics.

Make a note of the Client ID, as you will need it in a later step.

2. Log in to Digital Analytics as an Admin user with access to the Client ID you selected in the previous step, click the Admin link, and navigate to the Global User Authentication page.
 - In the **Enterprise Marketing Management Shared Secret** field, enter a string that conforms to the rules stated in the instructions next to the field.

Make a note of this string, as you will need it in a later step.

- Under Automatic User Account Creation, click **Disabled**.
3. Log in to Unica as an Admin user and navigate to the **Settings > Users** page.
 4. Select or create a user and configure a data source for this user as follows.
 - **Data Source** - Enter a name.
 - **Data Source Login** - Enter the Client ID you noted in step 1.
 - **Data Source Password** - Enter the Shared Secret you noted in step 2.

If you have multiple partitions, you must perform this task in every partition where you have users who should have single sign-on.

Alternatively, you can use the platform_admin user account for this step. Because this user is a member of all partitions, the data source is available in all partitions.

5. In Unica Platform, navigate to the **Settings > User groups** page and do the following.
 - Create a new group and add the DMUser role to that group.
 - Make each user who should have single sign-on a member of that group.

If you have multiple partitions, you must perform this task in every partition where you have users who should have single sign-on.

6. In Unica Platform, navigate to the **Settings > Configuration** page and set configuration properties as follows.

Table 98. Configuration properties for enabling single sign-on with Digital Analytics

Property	Value
Digital Analytics Enable IBM Digital Analytics	True
Digital Analytics Integration partitions partition[n] Platform user for IBM Digital Analytics account	Enter the login name for Unica Platform user account that you used in step 4.
Digital Analytics Integration partitions partition[n] Datasource for IBM Digital Analytics account	Enter the name of the data source you created in step 4.

If you have multiple partitions, you must use the **Digital Analytics | Integration | partitions | partitionTemplate** to create a set of configuration properties for every partition where you have users who should have single sign-on.

The name of the category you create with the template must exactly match the name of the corresponding Unica Campaign partition.

7. In Unica Platform, navigate to the **Settings > Users** page.
8. For each user for whom you want to enable single sign-on, enter that user's Digital Analytics login name in the **IBM Digital Analytics user name** field on the user's Edit properties page.



Note: If a user has exactly the same login names in both Unica and Digital Analytics, you do not have to perform this step.

9. Configure your web application server for single sign-on with Digital Analytics.

Configuring WebLogic for single sign-on between Digital Analytics and Unica

Perform the procedure below in the WebLogic domain where Unica Platform is deployed to ensure that users can view Digital Analytics reports in dashboards without having to log in.

1. Open the `setDomainEnv` script, located in the `bin` directory under your WebLogic domain directory.
2. Add `-Dweblogic.security.SSL.ignoreHostnameVerification=true` to `JAVA_OPTIONS`.

Configuring WebSphere® for single sign-on between Digital Analytics and Unica

Perform the procedure below in WebSphere® cell and node where Unica Platform is deployed to ensure that users can view Digital Analytics reports in dashboards without having to log in.

1. Log in to the WebSphere® administrative console.
2. Expand **Security** and click **SSL certificate and key management**.
3. Under **Configuration settings**, click **Manage endpoint security configurations**.
4. Navigate to the outbound configuration for the cell and node where the Unica Platform is deployed.
5. Under **Related Items**, click **Key stores and certificates** and click the **NodeDefaultTrustStore** key store.
6. Under **Additional Properties**, click **Signer certificates** and **Retrieve From Port**.

Complete fields as follows.

- **Host name:** `welcome.coremetrics.com`
- **Port:** `443`
- **Alias:** `coremetrics_cert`

Next steps

After you install the custom proxy server and import the Digital Analytics certificate, your next steps are to enable single sign-on and configure integration between Digital Analytics and Unica Campaign.

To finish setting up your environment, perform the following procedures.

- Set up single sign on as described in the *Unica Platform Administrator's Guide, in the chapter titled "Single sign-on between Unica and Digital Analytics."*
- Set up integration as described in the *Unica Campaign Administrator's Guide, in the chapter titled "Unica Campaign integration with other products."*



Important: The integration procedure includes setting the `ServiceURL` configuration property under **Campaign | partitions | partition[n] | Coremetrics**. When you use the custom proxy, you must set this property to `http://WebSphere_host:Port/proxy`, and restart the Unica Platform web application.

Campaign | partitions | partition[n] | Coremetrics

The properties in this category specify integration settings for Digital Analytics and Unica Campaign for the selected partition.

If your Unica Campaign installation has multiple partitions, set these properties for each partition that you want to affect. For these properties to take effect, `UC_CM_integration` must be set to `yes` for the partition (under `partitions | partition[n] | server | internal`).

ServiceURL

Description

The `ServiceURL` specifies the location of the Digital Analytics integration service that provides the integration point between Digital Analytics and Unica Campaign. Note that the default port for https is 443.

Default value

```
https://export.coremetrics.com/eb/segmentapi/1.0/api.do
```

Valid values

The only supported value for this release is the default value shown above.

CoremetricsKey**Description**

Unica Campaign uses the `CoreMetricsKey` to map IDs exported from Digital Analytics to the corresponding Audience ID in Unica Campaign. The value defined for this property must exactly match the value used in the translation table.

Default value

```
registrationid
```

Valid values

The only supported value for this release is `registrationid`.

ClientID**Description**

Set this value to the unique Digital Analytics Client ID assigned to your company.

Default value

No default value defined.

TranslationTableName**Description**

Specify the name of the translation table being used to translate Digital Analytics keys to Unica Campaign Audience IDs. For example, `Cam_CM_Trans_Table`. If you do not specify a table name, an error will occur if users run a flowchart that uses Digital Analytics segments as input, because without the table name, Unica Campaign does not know how to map IDs from one product to the other.



Note: When you map or re-map a translation table, the **Table Name** assigned in the Table Definition dialog must exactly match (including case) the `TranslationTableName` defined here.

Default value

No default value defined.

ASMUserForCredentials

Description

The `ASMUserForCredentials` property specifies which Unica account is allowed to access the Digital Analytics integration service. See below for additional information.

If no value is specified, Unica Campaign checks the currently logged-in user's account to see if the `ASMDatasourceForCredentials` value is specified as a data source. If it is, then access is allowed. If not, access is denied.

Default value

`asm_admin`

ASMDatasourceForCredentials

Description

The `ASMDatasourceForCredentials` property identifies the data source assigned to the Unica Platform account specified in the **ASMUserForCredentials** setting. The default is `UC_CM_ACCESS`. This "data

source for credentials" is the mechanism that Unica Platform uses to store the credentials that provide access to the integration service.

Although a default value of `UC_CM_ACCESS` is supplied, a data source of that name is not provided, nor do you have to use that name.



Important: You must choose **Settings > Users**, select the user specified in `ASMUserForCredentials`, click the **Edit Data Sources** link, and add a new data source whose name exactly matches the value defined here (for example, `UC_CM_ACCESS`). For Data Source Login and Data Source Password, use the credentials associated with your Digital Analytics Client ID. For information about data sources, user accounts, and security, see the *Unica Platform Administrator's Guide*

Default value

`UC_CM_ACCESS`

Setting up single sign-on between Unica and Digital Analytics using automatic user account creation

Use this procedure to set up single sign-on between Unica and Digital Analytics using automatic user account creation.

1. Determine the Digital Analytics Client ID you want to use for single sign-on between Unica and Digital Analytics.

Make a note of the Client ID, as you will need it in a later step.

2. Log in to Digital Analytics as an Admin user with access to the Client ID you selected in the previous step, click the Admin link, and navigate to the Global User Authentication page.

- In the **Enterprise Marketing Management Shared Secret** field, enter a string that conforms to the rules stated in the instructions next to the field.

Make a note of this string, as you will need it in a later step.

- Under Automatic User Account Creation, click **Enabled**.

- Select a user group to which you want all automatically created users to belong.

This group should have at least the following Web Analytics permissions.

- Dashboards > View Standard Dashboards
- Reports > Site Metrics
- Reports > Insights

3. Log in to Unica as an Admin user and navigate to the **Settings > Users** page.

4. Select or create a user and configure a data source for this user as follows.

- **Data Source** - Enter a name.
- **Data Source Login** - Enter the Client ID you noted in step 1.
- **Data Source Password** - Enter the Shared Secret you noted in step 2.

If you have multiple partitions, you must perform this task in every partition where you have users who should have single sign-on.

Alternatively, you can use the platform_admin user account for this step. Because this user is a member of all partitions, the data source is available in all partitions.

5. In Unica Platform, navigate to the **Settings > User groups** page and do the following.

- Create a new group and add the CMUser role to that group.
- Make each user who should have single sign-on a member of that group.

If you have multiple partitions, you must perform this task in every partition where you have users who should have single sign-on.

6. In Unica Platform, navigate to the **Settings > Configuration** page and set configuration properties as follows.

Table 99. Configuration properties for enabling single sign-on with Digital Analytics

Property	Value
Digital Analytics Enable IBM Digital Analytics	True
Digital Analytics Integration partitions partition[n] Platform user for IBM Digital Analytics account	Enter the login name for the Unica Platform user account that you used in step 4.

Property	Value
Digital Analytics Integration partitions partition[n] Datasource for IBM Digital Analytics account	Enter the name of the data source you created in step 4.

If you have multiple partitions, you must use the **Digital Analytics | Integration | partitions | partitionTemplate** to create a set of configuration properties for every partition where you have users who should have single sign-on.

The name of the category you create with the template must exactly match the name of the corresponding Unica Campaign partition.

7. For any user for whom you want to override automatic account creation, do the following.

- In Unica Platform, navigate to the **Settings > Users** page.
- Enter the user's Digital Analytics login name in the **Digital Analytics Username** field on the user's detail page.

This works only for users who already have an Digital Analytics account.



Note: If an account does not exist in Digital Analytics with this login name, an account will be created for this user with the name you enter here, rather than with the user's Unica Platform login name.

8. Configure you web application server for single sign-on with Digital Analytics.

Setting up single sign-on between Unica and Digital Analytics using manual user account creation

Use this procedure to set up single sign-on between Unica and Digital Analytics using manual user account creation.

1. Determine the Digital Analytics Client ID you want to use for single sign-on between Unica and Digital Analytics.

Make a note of the Client ID, as you will need it in a later step.

2. Log in to Digital Analytics as an Admin user with access to the Client ID you selected in the previous step, click the Admin link, and navigate to the Global User Authentication page.
 - In the **Enterprise Marketing Management Shared Secret** field, enter a string that conforms to the rules stated in the instructions next to the field.

Make a note of this string, as you will need it in a later step.
 - Under Automatic User Account Creation, click **Disabled**.
3. Log in to Unica as an Admin user and navigate to the **Settings > Users** page.
4. Select or create a user and configure a data source for this user as follows.
 - **Data Source** - Enter a name.
 - **Data Source Login** - Enter the Client ID you noted in step 1.
 - **Data Source Password** - Enter the Shared Secret you noted in step 2.

If you have multiple partitions, you must perform this task in every partition where you have users who should have single sign-on.

Alternatively, you can use the platform_admin user account for this step. Because this user is a member of all partitions, the data source is available in all partitions.

5. In Unica Platform, navigate to the **Settings > User groups** page and do the following.
 - Create a new group and add the DMUser role to that group.
 - Make each user who should have single sign-on a member of that group.

If you have multiple partitions, you must perform this task in every partition where you have users who should have single sign-on.

6. In Unica Platform, navigate to the **Settings > Configuration** page and set configuration properties as follows.

Table 100. Configuration properties for enabling single sign-on with Digital Analytics

Property	Value
Digital Analytics Enable IBM Digital Analytics	True

Property	Value
Digital Analytics Integration partitions partition[n] Platform user for IBM Digital Analytics account	Enter the login name for Unica Platform user account that you used in step 4.
Digital Analytics Integration partitions partition[n] Datasource for IBM Digital Analytics account	Enter the name of the data source you created in step 4.

If you have multiple partitions, you must use the **Digital Analytics | Integration | partitions | partitionTemplate** to create a set of configuration properties for every partition where you have users who should have single sign-on.

The name of the category you create with the template must exactly match the name of the corresponding Unica Campaign partition.

- In Unica Platform, navigate to the **Settings > Users** page.
- For each user for whom you want to enable single sign-on, enter that user's Digital Analytics login name in the **IBM Digital Analytics user name** field on the user's Edit properties page.



Note: If a user has exactly the same login names in both Unica and Digital Analytics, you do not have to perform this step.

- Configure your web application server for single sign-on with Digital Analytics.

Digital Analytics configuration properties

This section describes the Digital Analytics configuration properties on the Configuration page.

These configuration properties are used in configuring single sign-on between Digital Analytics and Unica. See the Unica Platform Administrator's Guide for details about this integration.

About Distinguished Names

To enable directory server integration in Unica, you must determine the Distinguished Name (DN) for a user and for groups. The DN of an object on the directory server is the complete path through the directory server tree structure to that object.

DNs are made up of these components:

- **Organizational Unit (OU).** This attribute is used to specify a namespace based on organizational structure. An OU is usually associated with a user-created directory server container or folder.
- **Common Name (CN).** This attribute represents the object itself within the directory server.
- **Domain Component (DC).** A Distinguished Name that uses DC attributes has one DC for every domain level below root. In other words, there is a DC attribute for every item separated by a dot in the domain name.

Use your directory server's Administration console to determine an object's Distinguished Name.

Obtaining required information

Obtain the required information about the directory server with which you want to integrate. You use this information during the configuration process, to store directory server credentials and to set configuration property values.

Obtain the following information.

- Obtain the server host name and port.
- Identify a user who has search permissions on the directory server, and gather the following information about the user.
 - login name
 - password
 - Distinguished Name (DN)
- Obtain the following for the directory server.

- Fully qualified host name or IP address
- The port on which server listens
- Determine the string that your directory server uses for the user attribute in the Group object. Typically, this value is `uniquemember` in LDAP servers and `member` in Windows™ Active Directory servers. You should verify this on your directory server.
- Obtain the following required user attributes.
 - Determine the string that your directory server uses for the user login attribute. This string is always required. Typically, this value is `uid` in LDAP servers and `sAMAccountName` in Windows™ Active Directory servers. Verify this string on your directory server.
 - Only if Unica Campaign is installed in a UNIX™ environment, determine the string that your directory server uses for the alternate login attribute.
- If you are using attribute based synchronization, obtain the strings used for the attributes (one or more) that you want to use for this purpose.
- If you want Unica Platform to import additional (optional) user attributes stored in your directory server, determine the strings that your directory server uses for the following.
 - First name
 - Last name
 - User title
 - Department
 - Company
 - Country
 - User email
 - Address 1
 - Work phone
 - Mobile phone
 - Home phone

Configuration process roadmap: Active Directory integration

Use this configuration process roadmap to scan the tasks required to integrate Unica with Windows™ Active Directory. The Topic column provides links to the topics that describe the tasks in detail.

Table 101. Configuration process roadmap: Active Directory integration

Topic	Information
Obtaining required information (on page 164)	Obtain information about your Windows™ Active Directory server, which is required for integration with Unica.
Group membership, mapping, and application access (on page 165)	If you are using group based synchronization, identify or create the groups in Unica Platform to which you will map your Active Directory groups.
Storing directory server credentials in Unica Platform (on page 166)	If your directory server does not allow anonymous access (the most common configuration), configure an Unica user account to hold a directory server administrator user name and password.
<ul style="list-style-type: none"> • Setting LDAP login method connection properties in Unica (on page 168) • Setting LDAP synchronization properties (on page 168) • Setting user attributes map properties (on page 169) • Mapping LDAP groups to Unica groups (on page 171) 	Configure the Unica Platform for integration by setting values on the Configuration page.

Table 101. Configuration process roadmap: Active Directory integration (continued)

Topic	Information
Testing synchronization (on page 171)	Verify that users are imported as expected, and if you are using group based synchronization, verify that users and groups are synchronizing properly.
Setting up an Active Directory user with PlatformAdminRole permissions (on page 172)	Set up administrator access to Unica Platform, required when NTLMv2 authentication is enabled.
Setting the security mode to enable NTLMv2 authentication (on page 172)	Set the security mode values on the Configuration page.
Configuring Internet Explorer (on page)	Set a custom security level in every instance of Internet Explorer that is used to access Unica. This is required with NTLMv2 authentication, to prevent users from being presented with the Unica login screen.
Restarting the web application server (on page 173)	This step is required to ensure that all of your changes are applied.
Testing login as an Active Directory user (on page 173)	Verify that you can log in to Unica as an Active Directory user.

The user management pages

Refer to this table if you need help completing the fields on the Users page.

The New user page

Table 102. Fields on the New user page

Field	Description
First name	The user's first name.
Last name	The user's last name.
Login	<p>The user's login name. This is the only required field. Only the following special characters are allowed in login names.</p> <ul style="list-style-type: none"> • Upper and lower case alphabetic characters (A-Za-z) • Numbers (0-9) • The 'at' sign (@) • Hyphen (-) • Underscore (_) • Dot (.) • Double byte characters (such as Chinese characters) <p>Do not include other special characters (including spaces) in the login name.</p>
Password	<p>A password for the user. Follow these rules when creating a password.</p> <ul style="list-style-type: none"> • Passwords are case-sensitive. For example, <code>password</code> is not the same as <code>Password</code>. • You may use any character when you create or reset a password in Unica. <p>Additional password requirements are set on the Configuration page. To see what they are for your installation of Unica, click the Password Rules link next to the Password field.</p>
Confirm password	The same password you entered in the Password field.

Table 102. Fields on the New user page (continued)

Field	Description
Title	The user's title.
Department	The user's department.
Company	The user's company.
Country	The user's country.
Address	The user's address.
Work phone	The user's work phone number.
Mobile phone	The user's mobile phone number.
Home phone	The user's home phone number.
Email address	The user's email address. This field must conform to email addresses as defined in RFC 821. See RFC 821 for details.
Alternate login	The user's UNIX™ login name, if one exists. An alternate login is typically required when the Unica Campaignlistener runs as root on a UNIX™-type system.
Status	Select ACTIVE or DISABLED from the drop-down list. ACTIVE is selected by default. Disabled users are prevented from logging in to all Unica applications.

The Edit properties page

The fields are the same as the fields on the New user page, except for the ones shown in the following table.

Table 103. Fields on the Edit properties page

Field	Description
Password	This field is not available on the Edit properties page.

Table 103. Fields on the Edit properties page (continued)

Field	Description
Login	This field is not available on the Edit properties page.
Password expiration	The date in the format appropriate for your locale (for example, for en_US, the format is <code>MM, dd, YYYY</code>). You cannot change a user's expiration date when the system-wide expiration date is set to never expire.
IBM® Digital Analytics user name	When integration is enabled with IBM Digital Analytics, and you choose to create users manually, you enter the user's Digital Analytics user name here as part of the configuration process.

The Reset password page

Table 104. Fields on the Reset password page

Field	Description
Password	The new password.
Confirm	The same password you entered in Password field.

The New Data Source and Edit Data Source Properties pages

Table 105. Fields on the Data Source pages

Field	Description
Data source	The name of a data source you want the user to be able to access from an Unica application. Unica names preserve case for display purposes, but use case-insensitive rules for comparison and creation (for example, you cannot create both <code>customer</code> and <code>Customer</code> data source names).
Data source login	The login name for this data source.

Table 105. Fields on the Data Source pages (continued)

Field	Description
Data source password	The password for this data source. You can leave this field empty, if the data source account does not have a password.
Confirm password	The password again (leave empty if you left the Data Source Password field empty).

Active Directory integration features

Unica Platform integration with Windows™ Active Directory provides the features described in this section.

Authentication with Active Directory integration

Unica applications query Unica Platform for user authorization information.

- Previous versions of Unica Platform supported NTLMv1 based Microsoft Windows Integrated login. With the arrival of Microsoft Windows 2008 Server and Microsoft Windows 7, the default minimum standard has changed and requires the NTLMv2 protocol. NTLMv2 is not natively supported by Unica Platform.

However, you can configure NTLMv2 authentication, so that users are authenticated to all Unica applications when they log in to the corporate network, and no password is required to log in to Unica applications. User authentication is based on their Windows™ login, bypassing the applications' login screens.

To configure NTLMv2 authentication, you perform the steps described in this chapter.

- If NTLMv2 authentication is not enabled, users must still log in on the Unica login screen, using their Windows™ credentials.

Managing internal and external users

When NTLMv2 authentication is enabled, all users are created and maintained in the Active Directory server. (You do not have the option of creating some users in Unica Platform,

which are known as internal users in this guide). If you require the ability to create internal users, do not enable NTLMv2 authentication.

When integration is configured, you cannot add, modify, or delete the imported user accounts in Unica Platform. You must perform these management tasks on the LDAP side, and your changes are imported when synchronization occurs. If you modify imported user accounts in Unica Platform, users may encounter problems with authentication.

Any user accounts you delete on the LDAP side are not deleted from Unica Platform. You should disable these accounts manually in Unica Platform. It is safer to disable these deleted user accounts rather than deleting them, because users have folder ownership privileges in Unica Campaign, and if you delete a user account that owns a folder, objects in that folder will no longer be available.

Synchronization

When Unica is configured to integrate with an Active Directory server, users and groups are synchronized automatically at pre-defined intervals.

Automatic synchronization has limited functionality.

- Automatic synchronization updates user attributes only. Because group membership changes such as adding, removing, or changing members in a group require administrator oversight, import of these changes is confined to the manual synchronization process by default.
- Users deleted from the LDAP server are not deleted during automatic synchronization.

You can force a full synchronization of all users and groups by using the Synchronize function in the Users area of Unica. Alternatively, you can contact Services to request that they set a hidden configuration property that causes the automatic synchronization to perform a full synchronization.

Importing users based on groups or attributes

You can choose one of two types of filtering to select the user accounts that are imported from the LDAP server into Unica Platform.

You must choose between group based or attribute based import; multiple methods are not supported simultaneously.

Group based import

Unica Platform imports groups and their users from the directory server database through a periodic synchronization task that automatically retrieves information from the directory server. When Unica Platform imports users and groups from the server database, group memberships are not changed. To pick up these changes, you must perform a manual synchronization.

You can assign Unica privileges by mapping an Active Directory group to an Unica group. This mapping allows any new users added to the mapped Active Directory group to assume the privileges set for the corresponding Unica group.

A subgroup in Unica Platform does not inherit the Active Directory mappings or user memberships assigned to its parents.

Details for configuring group based import are provided in the remainder of this chapter.

Attribute based import

If you do not want to create groups in your Active Directory server that are specific to Unica products, you have the option to control the users who are imported by specifying attributes. To achieve this, you would do the following during the configuration process.

1. Determine the string used in your Active Directory server for the attribute on which you want to filter.
2. Set the **Unica Platform | Security | LDAP synchronization | LDAP user reference attribute name** property to DN.

This indicates to Unica Platform that the synchronization is not based on a group with member references but is based on an Org Unit or an Org.

3. When you configure the **LDAP reference map** property, set the Filter portion of the value to the attribute on which you want to search. For the Filter, use the string you determined in step 1.

When you use attribute based synchronization, the periodic synchronization is always a full synchronization, instead of a partial synchronization, which is done for group based synchronization. For attribute based synchronization, you should set the **LDAP sync interval** property to a high value, or set it to 0 to turn off automatic synchronization and rely on manual full synchronization when users are added to the directory.

Follow the instructions provided in the remainder of this chapter to configure integration, using the instructions above in the steps where you set configuration properties.

About Active Directory and partitions

In multi-partition environments, user partition membership is determined by the group to which the user belongs, when that group is assigned to a partition. A user can belong to only one partition. Therefore, if a user is a member of more than one Active Directory group, and these groups are mapped to Unica groups that are assigned to different partitions, the system must choose a single partition for that user.

You should try to avoid this situation. However, if it occurs, the partition of the Unica group most recently mapped to an Active Directory group is the one that the user belongs to. To determine which Active Directory group was most recently mapped, look at the LDAP group mappings displayed in the Configuration area. They are displayed in chronological order, with the most recent mapping listed last.

Special characters in login names

Only three special characters are allowed in login names: dot (.), underscore (_), and hyphen (-). If any other special characters (including spaces) are present in the login name of a user you plan to import into Unica Platform from your Active Directory server, you must change the login name so that the user does not encounter issues when logging out or performing administrative tasks (if the user has administration privileges).

Forcing synchronization of external users

Use this procedure to force synchronization of users when Unica is integrated with an LDAP server or web access control system.

1. Log in to Unica and click **Settings > Users**.
2. Click **Synchronize**.

Users and groups are synchronized.

LDAP integration features

Unica Platform integration with LDAP provides the features described in this section.

Authentication with LDAP integration

Unica applications query Unica Platform for user authorization information. When LDAP integration is implemented, users enter their valid LDAP user name and password for authentication to Unica applications.

Managing internal and external users

When integration is configured, you cannot add, modify, or delete the imported user accounts in Unica Platform. You must perform these management tasks on the LDAP side, and your changes will be imported when synchronization occurs. If you modify imported user accounts in Unica Platform, users may encounter problems with authentication.

Any user accounts you delete on the LDAP side are not deleted from Unica Platform. You should disable these accounts manually in Unica Platform. It is safer to disable these deleted user accounts rather than deleting them, because users have folder ownership privileges in Unica Campaign, and if you delete a user account that owns a folder, objects in that folder will no longer be available.

Synchronization

When Unica is configured to integrate with an LDAP server, users and groups are synchronized automatically at pre-defined intervals.

Automatic synchronization has limited functionality.

- Automatic synchronization updates user attributes only. Because group membership changes such as adding, removing, or changing members in a group require administrator oversight, import of these changes is confined to the manual synchronization process by default.
- Users deleted from the LDAP server are not deleted during automatic synchronization.

You can force a full synchronization of all users and groups by using the Synchronize function in the Users area of Unica. Alternatively, you can contact Services to request that they set a hidden configuration property that causes the automatic synchronization to perform a full synchronization.

Importing users based on groups or attributes

You can choose one of two types of filtering to select the user accounts that are imported from the LDAP server into Unica Platform.

You must choose between group based or attribute based import; multiple methods are not supported simultaneously.

Group based import

Unica Platform imports groups and their users from the directory server database through a periodic synchronization task that automatically retrieves information from the directory server. When Unica Platform imports users and groups from the server database, group memberships are not changed. To pick up these changes, you must perform a manual synchronization.



Note: The LDAP groups must have a unique name even if the groups are configured for separate partitions.

You can assign Unica privileges by mapping an LDAP group to an Unica group. This mapping allows any new users added to the mapped LDAP group to assume the privileges set for the corresponding Unica group.

A subgroup in Unica Platform does not inherit the LDAP mappings or user memberships assigned to its parents.

Details for configuring group based import are provided in the remainder of this chapter.

Attribute based import

If you do not want to create groups in your LDAP server that are specific to Unica products, you have the option to control the users who are imported by specifying attributes. To achieve this, you would do the following during the LDAP configuration process.

1. Determine the string used in your LDAP server for the attribute on which you want to filter.
2. Set the **Platform | Security | LDAP synchronization | LDAP user reference attribute name** property to DN.

This indicates to Unica Platform that the synchronization is not based on a group with member references but is based on an Org Unit or an Org.

3. When you configure the **LDAP reference map** property, set the Filter portion of the value to the attribute on which you want to search. For the Filter, use the string you determined in step 1.

When you use attribute based synchronization, the periodic synchronization is always a full synchronization, instead of a partial synchronization, which is done for group based synchronization. For attribute based synchronization, you should set the **LDAP sync interval** property to a high value, or set it to 0 to turn off automatic synchronization and rely on manual full synchronization when users are added to the directory.

About LDAP and partitions

In multi-partition environments, user partition membership is determined by the group to which the user belongs, when that group is assigned to a partition. A user can belong to only one partition. Therefore, if a user is a member of more than one LDAP group, and these groups are mapped to Unica groups that are assigned to different partitions, the system must choose a single partition for that user.

You should try to avoid this situation. However, if it occurs, the partition of the Unica group most recently mapped to an LDAP group is the one that the user belongs to. To determine which LDAP group was most recently mapped, look at the LDAP group mappings displayed

in the Configuration area. They are displayed in chronological order, with the most recent mapping listed last.

Support for internal and external users

Unica supports two types of user accounts and groups.

- **Internal** - User accounts and groups that are created within Unica using the Unica security user interface. These users are authenticated through Unica Platform.
- **External** - User accounts and groups that are imported into Unica through synchronization with a supported LDAP server. This synchronization occurs only if Unica has been configured to integrate with the LDAP server. These users are authenticated through the LDAP server.

You may want to have both types of users and groups if, for example, you want to give your customers access to Unica applications without adding them to your LDAP server as full corporate users.

Using this hybrid authentication model requires more maintenance than a pure LDAP authentication model does.

Special characters in login names

Only three special characters are allowed in login names: dot (.), underscore (_), and hyphen (-). If any other special characters (including spaces) are present in the login name of a user you plan to import into Unica Platform from your LDAP server, you must change the login name so that the user does not encounter issues when logging out or performing administrative tasks (if the user has administration privileges).

Storing directory server credentials in Unica Platform

If your directory server does not allow anonymous access, you must configure an Unica user account to hold the user name and password of a directory server user, as described in the following procedure.

1. Log in to Unica as a user with Admin access.
2. Select or create an Unica user account to hold the directory server credentials of an LDAP user with read access over all of the user and group information in the LDAP server. Follow these guidelines.
 - In a later step, you will set the value of the `Unica Platform user for LDAP credentials` configuration property to the user name for this Unica user account. The default value of this property is `asm_admin`, a user that exists in every new Unica Platform installation. You can use the `asm_admin` account to hold the directory server credentials.
 - The user name of this Unica user account must not match the user name of any directory server user.
3. Add a data source for this Unica user account to store the credentials that Unica Platform uses to connect with the LDAP server. Follow these guidelines.

Table 106. Data source fields for storing credentials

Field	Guideline
Data Source Name	You can enter any name, but note that in a later step, the value of the <code>Data source for LDAP credentials</code> configuration property must match the data source name you use. To match the default value of this property so that you do not have to set the value, name your data source <code>LDAPServer</code> .
Data Source Login	Enter the Distinguished Name (DN) of the administrative user with read access over all of the directory server user and group information that will be synchronized with Unica. The DN resembles the following: <code>uidcn=user1,ou=someGroup,dc=systemName,dc=com</code> Alternatively, you can use the root user account that has access to all groups on your LDAP server. The default root user and how to specify this user for the supported directory servers are as follows.

Field	Guideline
	<ul style="list-style-type: none"> • The root user for Active Directory Server is Administrator. You can specify this user as follows. <code>domain\ldap_admin_username</code> • The root user for Oracle Directory Server is Directory Manager. You can specify this user as follows. <code>cn=Directory Manager</code> • The root user for IBM Security Directory Server is root. You can specify this user as follows. <code>cn=root</code>
Data Source Password	Enter the password of the administrative user whose login name you entered in the Data Source Login field.

Unica Platform | Security | Login method details | LDAP

Properties in this category are used to configure LDAP integration.

LDAP server host name

Description

Specifies the name or IP address of the LDAP server. Set the value to the machine name or IP address of the LDAP server. For example:

`machineName.companyDomain.com`

If you are integrating with Windows™ Active Directory, use the server name instead of the DNS name.

Default value

Undefined

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

LDAP server port

Description

Specifies the port on which the LDAP server listens. Set the value to the appropriate port number. Typically, the port number is 389 (636 if SSL is used).

Default value

389

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

User search filter

Description

Specifies the filter to use to search for users. Valid values are any valid LDAP search filter (see [RFC 2254](#)). Note that you must XML-escape any XML characters in this value.

Typically, the value for the user login attribute is `uid` for LDAP servers and `sAMAccountName` for Windows™ Active Directory servers. You should verify this on your LDAP or Active Directory server. If your LDAP server is Windows™ Active Directory, you should change the default value of this property to use `sAMAccountName` rather than `uid`. For example:

```
(&( |(objectClass=user)(objectClass=person))(sAMAccountName={0}))
```

Default value

```
(&( |(objectClass=user)(objectClass=person))(uid={0}))
```

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

Use credentials stored in Unica Platform

Description

Specifies whether the Unica Platform uses credentials from the Unica Platform database when searching the LDAP or Windows™ Active Directory server during user authentication (at login time).

If this value is `true`, the Unica Platform uses credentials from the Unica Platform database, and you must set the appropriate values for the `Unica Platform user for LDAP credentials` and `Data source for LDAP credentials` properties in this category.

If your LDAP or Windows™ Active Directory server does not allow anonymous access, set this value to `true`.

If this value is `false`, the Unica Platform connects with the LDAP or Windows™ Active Directory server anonymously. You may set this value to `false` if your LDAP or Windows™ Active Directory server allows anonymous access.

Default value

`false`

Valid Values

`true` | `false`

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

Unica Platform user for LDAP credentials

Description

Specifies the name of the Unica user that has been given LDAP administrator login credentials. Set this value if you set the `Use credentials stored in Unica Platform` property in this category to `true`.

Set the value of this property to the user name you created for the Unica user when you configured LDAP integration. This property works in conjunction with the `Data source for LDAP credentials` property in this category.

Default value

`asm_admin`

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

Data source for LDAP credentials**Description**

Specifies the Unica Platform data source for LDAP administrator credentials. Set this value if you set the `Use credentials stored in Unica Platform` property in this category to `true`.

Set the value of this property to the data source name you created for the Unica user when you configured LDAP integration. This property works in conjunction with the `Unica Platform user for LDAP credentials` property in this category.

Default value

Undefined

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

Base DN**Description**

Specifies the base distinguishing name (DN) pointing to the root of the LDAP directory structure.

Default value

[CHANGE ME]

Valid Values

Any valid DN (see [RFC 1779](#), [RFC 2253](#))

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

Require SSL for LDAP connection

Path

Unica Platform | Security | LDAP

Description

Specifies whether the Unica Platform uses SSL when it connects to the LDAP server to authenticate users. If you set the value to `true`, the connection is secured using SSL.

Default value

`false`

Valid Values

`true` | `false`

Setting LDAP login method connection properties in Unica

LDAP login method properties specify connection details the system uses to connect to the directory server.

1. Click **Settings > Configuration** and navigate to the **Unica Platform | Security | Login method details | LDAP** category.
2. Set values of the following configuration properties.

See the related reference for details on how to set each property.

- LDAP server host name
- LDAP server port
- User search filter
- Use credentials stored in Unica Platform
- Unica Platform user for LDAP credentials
- Data source for LDAP credentials
- Base DN
- Require SSL for LDAP connection

Setting LDAP synchronization properties

LDAP synchronization properties specify details that the system uses to log into the directory server and identify users to import. Some of these properties also control the frequency and other details of the automatic synchronization process.

1. Click **Settings > Configuration** and navigate to the **Platform | Security | LDAP Synchronization** category.
2. Set values of the following configuration properties in the **LDAP properties** section.

See each property's context help or the related topic link in this section for instructions on setting the values.

- LDAP sync enabled
- LDAP sync interval
- LDAP sync delay
- LDAP sync timeout
- LDAP sync scope
- LDAP provider URL
- Require SSL for LDAP connection (optional)
- LDAP config Unica Platform group delimiter
- LDAP reference config delimiter
- Unica Platform user for LDAP credentials
- Data source for LDAP credentials
- LDAP user reference attribute name

- LDAP BaseDN periodic search disabled
- User login
- Various user attributes such as department, country, and user title (optional)

Platform | Security | LDAP synchronization

LDAP synchronization properties specify details that the system uses to log into the directory server and identify users to import. Some of these properties also control the frequency and other details of the automatic synchronization process.

LDAP sync enabled

Description

Set to `true` to enable LDAP or Active Directory synchronization.

Default value

`false`

Valid Values

`true` | `false`

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

LDAP sync interval

Description

The Unica Platform synchronizes with the LDAP or Active Directory server at regular intervals, specified in seconds here. If the value is zero or less, the Unica Platform does not synchronize. If the value is a positive integer, the new value takes effect without a restart within ten minutes. Subsequent changes take effect within the configured interval time.

Default value

600, or ten minutes

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

LDAP sync delay

Description

This is the time (in 24 hour format) after which the periodic synchronization with the LDAP server begins, after the Unica Platform is started. For example, an `LDAP sync delay` of 23:00 and an `LDAP sync interval` of 600 mean that when the Unica Platform starts, the periodic synchronization starts to execute at 11:00 PM and executes every 10 minutes (600 seconds) thereafter.

Default value

23:00, or 11:00pm

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

LDAP sync timeout

Description

The LDAP sync timeout property specifies the maximum length of time, in minutes, after the start of a synchronization before the Unica Platform marks the process ended. The Platform allows only one synchronization process to run at a time. If a synchronization fails, it is marked as ended whether it completed successfully or not.

This is most useful in a clustered environment. For example, if the Unica Platform is deployed in a cluster, one server in the cluster might start an LDAP synchronization and then go down before the process is marked as ended. In that case, the Unica Platform will wait for the amount of time specified in this property, and then it will start the next scheduled synchronization.

Default value

600, (600 minutes, or ten hours)

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

LDAP sync scope

Description

Controls the scope of the initial query to retrieve the set of users. You should retain the default value of `SUBTREE` for synchronizing with most LDAP servers.

Default value

`SUBTREE`

Valid Values

The values are standard LDAP search scope terms.

- `OBJECT` - Search only the entry at the base DN, resulting in only that entry being returned
- `ONE_LEVEL` - Search all entries one level under the base DN, but not including the base DN.
- `SUBTREE` - Search all entries at all levels under and including the specified base DN.

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

LDAP provider URL

Description

For most implementations, set to the LDAP URL of the LDAP or Active Directory server, in one of the following forms:

- `ldap://IP_address:port_number`
- `ldap://machineName.domain.com:port_number`

On LDAP servers, the port number is typically 389 (636 if SSL is used).

If Unica is integrated with an Active Directory server, and your Active Directory implementation uses serverless bind, set the value of this property to the URL for your Active Directory server, using the following form:

```
ldap:///dc=example,dc=com
```

Default value

Undefined

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

Require SSL for LDAP connection

Path

```
Platform | Security | LDAP synchronization
```

Description

Specifies whether the Unica Platform uses SSL when it connects to the LDAP server to synchronize users. If you set the value to `true`, the connection is secured using SSL.

Default value

```
false
```

Valid Values

```
true | false
```

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

LDAP config Unica Platform group delimiter

Description

In the LDAP reference to Unica Platform group map category, if you want to map one LDAP or Active Directory group to multiple Unica Platform groups, use the delimiter specified here. It can be any single character that does not appear in the names it is separating.

Default value

; (semicolon)

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

LDAP reference config delimiter

Description

Specifies the delimiter that separates the SEARCHBASE and FILTER components that make up the LDAP or Active Directory reference (described in the LDAP references for Unica Platform user creation category).

FILTER is optional: if omitted, the Unica Platform server dynamically creates the filter based on the value of the LDAP user reference attribute name property.

Default value

; (semicolon)

Valid Values

Any single character that does not appear in the names it is separating.

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

Unica Platform user for LDAP credentials

Description

Specifies the name of Unica user that has been given LDAP administrator login credentials.

Set the value of this property to the user name you created for the Unica user when you configured LDAP integration. This property works in conjunction with the `Data source for LDAP credentials` property in this category.

Default value

`asm_admin`

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

Data source for LDAP credentials

Description

Specifies the Unica Platform data source for LDAP administrator credentials.

Set the value of this property to the data source name you created for the Unica user when you configured LDAP integration. This property works in conjunction with the `Unica Platform user for LDAP credentials` property in this category.

Default value

Undefined

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

LDAP user reference attribute name

Description

For group based import of users, set to the name that your LDAP or Active Directory server uses for the user attribute in the Group object. Typically, this value is `uniquemember` in LDAP servers and `member` in Windows™ Active Directory servers.

For attribute based import of users, set this property to `DN`, and when you configure the **LDAP reference map** property, set the `FILTER` portion of the value to the string your LDAP server uses for the attribute on which you want to search.

Default value

`member`

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

LDAP BaseDN periodic search disabled

Description

When this property is set to `True`, the Unica Platform performs the LDAP synchronization search using the distinguished name set in the `Base DN` property under the **Unica Platform | Security | LDAP** category. If this property is set to `False`, the Unica Platform performs the LDAP synchronization search using the groups mapped to LDAP groups under **LDAP reference to Unica Platform group map**.

The following table describes whether changes are picked up in periodic synchronization, depending on the value set for this property.

Table 107. Effect of this property on periodic synchronization behavior

Change	Is the change picked up when the value is set to True?	Is the change picked up when the value is set to False?
In Unica Platform, delete a user synchronized from the LDAP server	Yes	No
Remove a user from an LDAP group mapped to a Unica Platform group	No	No
In Unica Platform, remove a user from a Unica Platform group mapped to an LDAP group.	No	No
Add a new user to the LDAP server	Yes	Yes
Add a user to an LDAP group mapped to a Unica Platform group	Yes	No
Change user attributes on the LDAP server	Yes	Yes

Default value

False

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

User login**Description**

Maps the Unica user's login to the equivalent user attribute in your LDAP or Active Directory server. `User login` is the only required mapping. Typically, the value for this attribute is `uid` for LDAP servers and `sAMAccountName` for Windows™ Active Directory servers. You should verify this on your LDAP or Active Directory server.

Default value

`uid`

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

First name

Description

Maps the First Name user attribute in the Unica Platform to the equivalent user attribute in your LDAP or Active Directory server.

Default value

`givenName`

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

Last name

Description

Maps the Last Name user attribute in the Unica Platform to the equivalent user attribute in your LDAP or Active Directory server.

Default value

`sn`

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

User title

Description

Maps the Title user attribute in the Unica Platform to the equivalent user attribute in your LDAP or Active Directory server.

Default value

title

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

Department

Description

Maps the Department user attribute in the Unica Platform to the equivalent user attribute in your LDAP or Active Directory server.

Default value

Undefined

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

Company

Description

Maps the Company user attribute in the Unica Platform to the equivalent user attribute in your LDAP or Active Directory server.

Default value

Undefined

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

Country

Description

Maps the Country user attribute in the Unica Platform to the equivalent user attribute in your LDAP or Active Directory server.

Default value

Undefined

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

User email

Description

Maps the Email Address attribute in the Unica Platform to the equivalent user attribute in your LDAP or Active Directory server.

Default value

mail

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

Address 1

Description

Maps the Address user attribute in the Unica Platform to the equivalent user attribute in your LDAP or Active Directory server.

Default value

Undefined

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

Work phone

Description

Maps the Work Phone user attribute in the Unica Platform to the equivalent user attribute in your LDAP or Active Directory server.

Default value

telephoneNumber

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

Mobile phone

Description

Maps the Mobile Phone user attribute in the Unica Platform to the equivalent user attribute in your LDAP or Active Directory server.

Default value

Undefined

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

Home phone

Description

Maps the Home Phone user attribute in the Unica Platform to the equivalent user attribute in your LDAP or Active Directory server.

Default value

Undefined

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

Alternate login

Description

Maps the Alternate Login user attribute in the Unica Platform to the equivalent user attribute in your LDAP or Active Directory server.

Default value

Undefined

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

Setting user attributes map properties

These properties specify the user attributes that the system imports from the directory server.

1. Click **Settings > Configuration** and navigate to the **Platform | Security | LDAP Synchronization** category.
2. Set values in the **User attributes map** section to map the listed Unica user attributes to the user attributes in your directory server.

If you are using group based synchronization, the only property you are required to map is `User login`. Typically, this value is `uid` in LDAP servers and `sAMAccountName` in Windows™ Active Directory servers. Use the value you verified as described in "Obtaining required information."

If you are using attribute based synchronization, map the attributes on which you want to search.

Note the following.

- The properties that you map here are replaced for the imported users each time Unica Platform synchronizes with your directory server.
- Unica Platform requires that email addresses conform to the definition stated in [RFC 821](#). If the email addresses on your directory server do not conform to this standard, do not map them as attributes to be imported.
- If your directory server database allows an attribute to have more characters than is allowed in the Unica Platform system tables, as shown in the following table, the attribute value is truncated to fit.

Table 108. Number of characters allowed for user attributes

Attribute	Allowed length
User login (required)	256
First name	128
Last name	128
User title	128
Department	128
Company	128
Country	128
User email	128
Address 1	128
Work phone	20
Mobile phone	20

Attribute	Allowed length
Home phone	20
Alternate login (required on UNIX™)	256

Configuration process roadmap: LDAP integration

Use this configuration process roadmap to scan the tasks required to integrate Unica with LDAP. The Topic column provides links to the topics that describe the tasks in detail.

Table 109. Configuration process roadmap: LDAP integration

Topic	Information
Obtaining required information (on page 164)	Obtain information about your LDAP server, which is needed for integration with Unica.
Group membership, mapping, and application access (on page 165)	If you are using group based synchronization, identify or create the groups in Unica Platform to which you will map your LDAP groups.
Storing directory server credentials in Unica Platform (on page 166)	If your directory server does not allow anonymous access (the most common configuration), configure an Unica user account to hold a directory server administrator user name and password.
<ul style="list-style-type: none"> • Setting LDAP login method connection properties in Unica (on page 168) • Setting LDAP synchronization properties (on page 168) 	Configure the Unica Platform for integration by setting values on the Configuration page.

Table 109. Configuration process roadmap: LDAP integration (continued)

Topic	Information
<ul style="list-style-type: none"> • Setting user attributes map properties (on page 169) • Mapping LDAP groups to Unica groups (on page 171) 	
Testing synchronization (on page 171)	Verify that users are imported as expected, and if you are using group based synchronization, verify that groups are synchronizing properly.
Setting the security mode to LDAP (on page 187)	Set the security mode values on the Configuration page.
Restarting the web application server (on page 173)	This step is required to ensure that all of your changes are applied.
Testing login as an LDAP user (on page 187)	Verify that you can log in to Unica as an LDAP user.

Platform | Security | LDAP synchronization | LDAP reference to Unica Platform group map

Properties in this category are used to configure LDAP integration.

LDAP reference map

Description

Users who are members of the LDAP or Active Directory group specified here are imported to the Unica Platform group specified in the `Unica Platform group` property.

Set the value of this property using the following syntax: `SEARCHBASE DELIMITER FILTER` where:

`SEARCHBASE` is the Distinguished Name (DN) of the object.

`DELIMITER` is the value of the `LDAP config AM group delimiter` property.

`FILTER` is the LDAP or Active Directory attribute filter. `FILTER` is optional when you use group based import: if omitted, the Unica Platform server dynamically creates the filter based on the value of the `LDAP user reference attribute name` property.

If you use attribute based import, set the value of `FILTER` to the string your LDAP server uses for the attribute on which you want to search. Also, you must set value of the **LDAP user reference attribute name** property to `DN`.

Default value

Undefined

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

Unica Platform group

Description

Users who are members of the LDAP or Active Directory group specified in the `LDAP reference group` property are imported to the Unica Platform group specified here.

Default value

Undefined

Availability

This property is used only when the Unica Platform is configured to integrate with a Windows™ Active Directory or other LDAP server.

Mapping LDAP groups to Unica groups

Users who belong to the directory server groups you map here are imported and made members of the Unica Platform group or groups specified here.



Important: Do not map any of the groups that have the `asm_admin` user as a member.

1. Click **Settings > Configuration** and navigate to the **Unica | Unica Platform | Security | LDAP Synchronization | LDAP reference to Unica Platform group map** category.
2. For each directory server group you want to map to a Unica Platform group, create an **LDAP reference to Unica Platform group** category by selecting the *(LDAP reference to Unica Platform group map)* template. Set the following properties.
 - New category name
 - LDAP reference map
 - Unica Platform group

For example, the following values map the `LDAPMarketingPlatformUsers` group to the Unica Platform `marketingopsUsers` and `campaignUsers` groups (`FILTER` is omitted).

- LDAP reference: `cn=MarketingPlatformUsers,cn=Users,dc=myCompany,dc=com`
- Unica Platform group: `marketingopsUsers;campaignUsers`

Adding an internal group

Use this procedure to add an internal group.

1. Click **Settings > User groups**.
2. Click **New group** above the **Group Hierarchy** list.
3. Complete the **Group name** and **Description** fields.



Important: Do not give the group a the same name as system-defined roles. For example, do not name a group "Admin," which is a role name used in Unica Campaign. Doing so can cause problems during upgrades.

4. Click **Save changes**.

The new group's name appears in the **Group hierarchy** list.

Assigning a role to or removing a role from a group

If you add a role to a group or remove a role from a group, members of that group acquire or lose that role.

1. Click **Settings > User groups**.
2. Click the name of the group that you want to work with.
3. Click **Assign roles**.

Roles that are not assigned to the group are shown in the **Available roles** box on the left. Roles that are currently assigned to the group are shown in the **Roles** box on the right.

4. Click a role name in the Available roles box to select it.
5. Click **Add** or **Remove** to move the role name from one box to the other.
6. Click **Save changes** to save your changes.
7. Click **OK**.

Adding a user to a group or subgroup

Use this procedure to add a user to a group or subgroup.

1. Click **Settings > Users**.



Note: You can perform the same task on the **User groups** page by clicking the group name and then clicking **Edit Users**.

2. Click the user name you want to change.
3. Click the **Edit groups** link at the bottom of the page.
4. Click a group name in the **Available groups** box to select it.
5. Click the **Add** button.

The group name moves to the **Groups** box.

6. Click **Save changes** to save your changes.
7. Click **OK**.

The user account details are displayed, with the group or subgroup you assigned listed.

Setting up an Active Directory user with PlatformAdminRole permissions

When NTLMv2 authentication is enabled, you can not log in to Unica as `platform_admin`, so you must perform the following procedure in order to have administrator access to Unica Platform.

1. Log in to Unica as an internal user (a user created in Unica Platform rather than a user imported from Active Directory). This must be a user with PlatformAdminRole permissions in the Unica Platform.
2. Create a Unica Platform group and assign the PlatformAdminRole role to it.
3. Ensure that at least one Windows™ Active Directory user is a member of this group.

Platform | Security | Login method details | Web access control

Properties in this category are used to configure integration with web access control software.

Username pattern

Description

Java™ regular expression used to extract the user login from the HTTP header variable in web access control software. Note that you must XML-escape any XML characters in the regular expression. The recommended value for SiteMinder and IBM Security Access Manager is `\w*`

You should also use this value when you use a custom proxy to integrate Unica Campaign hosted on premises and Digital Analytics in the cloud.

Default value

Undefined

Valid Values

Any Java™ regular expression.

Availability

This property is used only when the Unica Platform is configured to integrate with web access control software.

Web access control header variable

Description

Specifies the HTTP header variable configured in the web access control software, which is submitted to the web application server. By default, SiteMinder uses `sm_user` and IBM Security Access Manager (SAM) uses `iv-user`. For SAM, set this value to the user name component of the Raw string, not the HTTP string.

Default value

Undefined

Valid Values

Any string

Availability

This property is used only when the Unica Platform is configured to integrate with web access control software.

Setting the security mode to enable NTLMv2 authentication

Only if you want to enable NTLMv2 authentication, set configuration properties as described in this procedure.

Configure NTLMv2 authentication.

Click **Settings > Configuration** and set configuration properties as shown in the following table.

Table 110. Configuration property values for NTLMv2

Property	Value
Platform Security Login method	Select the <code>web access control</code> option.
Platform Security Login method details Web access control Web access control header variable	Enter the variable name as specified in the re-write rules.
Platform Security Login method details Web access control Username pattern	Enter <code>\w*</code>
General Navigation Platform URL	Enter the IIS site URL.

Platform | Security | Login method details | Web access control

Properties in this category are used to configure integration with web access control software.

Username pattern

Description

Java™ regular expression used to extract the user login from the HTTP header variable in web access control software. Note that you must XML-escape any XML characters in the regular expression. The recommended value for SiteMinder and IBM Security Access Manager is `\w*`

You should also use this value when you use a custom proxy to integrate Unica Campaign hosted on premises and Digital Analytics in the cloud.

Default value

Undefined

Valid Values

Any Java™ regular expression.

Availability

This property is used only when the Unica Platform is configured to integrate with web access control software.

Web access control header variable

Description

Specifies the HTTP header variable configured in the web access control software, which is submitted to the web application server. By default, SiteMinder uses `sm_user` and IBM Security Access Manager (SAM) uses `iv-user`. For SAM, set this value to the user name component of the Raw string, not the HTTP string.

Default value

Undefined

Valid Values

Any string

Availability

This property is used only when the Unica Platform is configured to integrate with web access control software.

HCL Unica | General | Navigation

Properties in this category specify values that are used internally to navigate among Unica products.

TCP port for secure connections

Description

Specifies the SSL port in the web application server on which the Unica Platform is deployed. This property is used internally for communication among Unica products.

Default value

7001

TCP port for standard connections**Description**

Specifies the HTTP port in the web application server on which the Unica Platform is deployed. This property is used internally for communication among Unica products.

Default value

7001

Unica Platform URL**Description**

Specifies the URL used for Unica Platform. This is set at installation time and normally should not be changed. Note that the URL contains the domain name, as shown in the following example.

```
protocol://machine_name_or_IP_address.domain_name:port_number/  
context-root
```

The machine name should not be `localhost`.

If users access Unica products with the Chrome browser, use the fully qualified domain name (FQDN) in the URL. If the FQDN is not used, the Chrome browser cannot access the product URLs.



Important: If Unica products are installed in a distributed environment, you must use the machine name rather than an IP address in the navigation URL for all of the applications in the suite. Also, if you are on a clustered environment and choose to use ports that are different from the default ports 80 or 443 for your deployment, do not use a port number in the value of this property.

Default value

Not defined

Example

In an environment configured for SSL, the URL might look like this:

```
https://machineName.companyDomain.com:8080/unica
```

Setting web access control connection properties in Unica

To configure web access control integration, you set some configuration properties.

On the **Settings & Configuration** page, set values of the properties as described in the following table.

See the related reference for details on how to set each property.

Table 111. Properties for configuring web access control integration

Property	Value
Unica Unica Platform Security Login method details	Select <code>Web access control</code> .
Unica Unica Platform Security Login method details Web access control User-name pattern	A Java™ regular expression used to extract the user login from the HTTP header variable in web access control software. You must XML-escape any XML characters in the regular expression. The recommended value for SiteMinder and IBM Security Access Manager is <code>\w*</code>
Unica Unica Platform Security Login method details Web access control Web access control header variable	The HTTP header variable configured in the web access control software, which is submitted to the web application server. By default, SiteMinder uses <code>sm_user</code> , and IBM Security Access Manager uses <code>iv-user</code> . For IBM Security Access Manager, set this value to the user name component of the IBM® Raw string, not the IBM® HTTP string.

Property	Value
Unica General Navigation Unica Platform URL	Set to <code>http://sm_host:sm_port/sm_realm/unica</code> where <ul style="list-style-type: none"> • <code>sm_host</code> is the name of the machine on which SiteMinder is installed • <code>sm_port</code> is the SiteMinder port number • <code>sm_realm</code> is the SiteMinder realm

Implementation of one-way SSL

This section describes one-way SSL in Unica.

Any communication that needs to be secured between two applications connecting over a network can be transmitted using the Secure Sockets Layer (SSL) protocol.

SSL provides secure connections by:

- Allowing an application to authenticate the identity of another application
- Using a private key to encrypt and decrypt data transferred over the SSL connection

When applications are configured for SSL, web traffic is over HTTPS instead of HTTP as reflected in the URLs.

When processes communicate with each other, the process making a request acts as the client and the process responding to a request acts as the server. For complete security, SSL should be implemented for all forms of communication with Unica products.

SSL can be configured one-way or two-way. With one-way SSL, the server is required to present a certificate to the client but the client is not required to present a certificate to the server. To successfully negotiate the SSL connection, the client must authenticate the server. The server accepts a connection from any client.

Configuring integration with an SSL type of WebSEAL junction

Follow this procedure to configure Unica Platform integration with IBM Security Access Manager using an SSL type of WebSEAL junction.

For details on these procedures, see the documentation provided with IBM Security Access Manager and your web application server.

1. Generate or purchase SSL certificates and configure your web application server to use them.
2. Create a webSEAL certificate and configure IBM Security Access Manager to use it.
3. Import your webSEAL certificate into your web application server.
4. Import your web application server certificate into IBM Security Access Manager.
5. Create an SSL type of WebSEAL junction in IBM Security Access Manager.

If you install multiple Unica products, create a separate junction for each product.

6. Set the navigation URL configuration property on the **Settings & Configuration** page for each installed product.

The value should reflect the webSEAL junction used for that product. Follow this pattern:

```
https://machine_name_or_IP_address.domain_name:port_number/  
webSEAL_junction/context-root
```

To access Unica, use a URL such as the following:

```
https://machine_name_or_IP_address.domain_name:port_number/  
webSEAL_junction//unica
```

7. Unprotect URLs in IBM Security Access Manager as described elsewhere in this guide.

Configuring SiteMinder for Unica products

Unprotect objects in SiteMinder as described in this procedure to enable correct functioning of your Unica products.

1. Log in to the **Administer Policy Server** area of SiteMinder and click **Domains**.
2. Select the realm that applies to your installations, right-click **unprotecturl**, and select **Properties of Realm**.
3. For each of the applicable URLs as described in the following table, enter the URL in the **Resource Filter** text box, and under **Default Resource Protection**, select **Unprotected**.

Table 112. Un-protected objects required for Unica products

Product or feature	Objects
Unica Campaign	<ul style="list-style-type: none"> • <code>/Campaign/services/CampaignServices30Service</code> • <code>/Campaign/api/campaign/rest</code> • <code>/Campaign/FlowchartNotifyScheduler</code> • <code>/Campaign/OperationMonitor</code> • <code>http://host:port/Campaign/api/campaign/rest/deepsearch/partition</code> <p>Replace partition with the partition name.</p> <p>The following apply when integration with Engage is implemented.</p> <p>In the following URLs, replace partition with the partition name.</p> <ul style="list-style-type: none"> • <code>http://host:port/Campaign/jsp/engage/engageHome.jsp</code> • <code>http://host:port/Campaign/api/campaign/rest/engage/offers</code> • <code>http://host:port/Campaign/api/campaign/rest/engage/offer</code> • <code>http://host:port/Campaign/servlet/EngageUpload</code> • <code>http://host:port/Campaign/api/campaign/rest/engageimportlist/partition</code>

Product or feature	Objects
	<ul style="list-style-type: none"> • <code>http://host:port/Campaign/api/campaign/rest/engageimportlist/partition/jobid</code> <p>This URL is for checking the status of an import job. Replace jobid with your job ID.</p> <ul style="list-style-type: none"> • <code>http://host:port/Campaign/api/campaign/rest/engageimportlist/partition/schedule</code> • <code>http://host:port/Campaign/api/campaign/rest/engageimportlist/partition/channel/schedule</code> <p>This URL is for sending push or SMS messages. Channel is either <code>sms</code> or <code>push</code>.</p>
Unica Collaborate	<ul style="list-style-type: none"> • <code>/collaborate/affiniumcollaborate.jsp</code> • <code>/collaborate/services/CollaborateIntegrationServices1.0</code> • <code>/collaborate/flowchartRunNotifyServlet</code> • <code>/collaborate/js/js_messages.jsp</code> • <code>/collaborate/js/format_symbols.jsp</code> • <code>/collaborate/alertsService</code>
IBM eMessage	<ul style="list-style-type: none"> • <code>/Campaign/emessage/eventSinkServlet</code>
Unica Interact	<ul style="list-style-type: none"> • <code>/Campaign/interact/saveFlowchartAction.udo</code> • <code>/Campaign/interact/flowchartEventPatterns.udo</code> • <code>/Campaign/interact/testRunFlowchart.udo</code> • <code>/Campaign/interact/getProfileDataAction.udo</code> • <code>/Campaign/interact/manageIPB.udo</code>

Product or feature	Objects
	<ul style="list-style-type: none"> • /Campaign/interact/flowchartRTAttrs.udo • /Campaign/initOfferListResolution.udo • /Campaign/getOfferListResolutionStatus.udo
Unica Plan	<ul style="list-style-type: none"> • /plan/errorPage.jsp • /plan/alertsService • /plan/services • /plan/services/collabService • /plan/services/PlanIntegrationServices/1.0 • /plan/affiniumplan.jsp • /plan/invalid_user.jsp • /plan/js/js_messages.jsp • /plan/js/format_symbols.jsp • /unica/servlet/AJAXProxy • /plan/api/plan/flowchartApproval/flowchartApproval/validate
Unica Optimize	<ul style="list-style-type: none"> • /Campaign/optimize/ext_runOptimizeSession.do • /Campaign/optimize/ext_optimizeSessionProgress.do • /Campaign/optimize/ext_doLogout.do
IBM SPSS Modeler Advantage Enterprise Marketing Management Edition	/unica/rest/spssUser
Unica Platform data filters	/unica/servlet/DataFiltering

Product or feature	Objects
Unica notifications	<ul style="list-style-type: none"> • <code>unica/servlet/alertAJAXProxy</code> • <code>unica/notification/alertsCount</code>
Unica Scheduler	<code>/unica/servlet/SchedulerAPIServlet</code>

Enabling single logouts with SiteMinder

To enable a logout of SiteMinder when a user logs out of an Unica application, configure SiteMinder as follows.

1. Log in to the **Administer Policy Server** area of SiteMinder and set the `logoffUri` property to the URI of the Unica logout page.

For example: `/sm_realm/unica/j_spring_security_logout` where `sm_realm` is the SiteMinder security realm and `unica` is the Unica Platform context root.

2. Unprotect the Unica logout page, `/unica/jsp/frameworklogout.jsp` to ensure that SiteMinder does not force the user to sign in again to view the logout page.

Two ways to create data filters: automatic generation and manual specification

Unica Platform provides a utility, `datafilteringScriptTool`, that processes XML to create the data filters in the Unica Platform system tables. Depending on how you write the XML, you can use this utility in two ways: automatic generation and manual specification.

Automatic generation

The `datafilteringScriptTool` utility can automatically generate data filters from a database table or view accessible using JDBC. The utility automatically creates data filters based on unique combinations of values in fields that you specify in the XML (one data filter for each unique combination).

You might want to use this method if you must create many data filters based on unique combinations of values in different fields.

Manual specification

The `datafilteringScriptTool` utility can create data filters one by one, based on field values that you specify.

You might want to use this method if you want to create a set of data filters that does not include every unique combination of field values.

datafilteringScriptTool

The `datafilteringScriptTool` utility reads an XML file to populate the data filtering tables in the Unica Platform system table database.

Depending on how you write the XML, you can use this utility in two ways.

- Using one set of XML elements, you can auto-generate data filters based on unique combinations of field values (one data filter for each unique combination).
- Using a slightly different set of XML elements, you can specify each data filter that the utility creates.

See Unica Platform the Administrator's Guide for information about creating the XML.

When to use datafilteringScriptTool

You must use `datafilteringScriptTool` when you create new data filters.

Prerequisites

The Unica Platform must be deployed and running.

Using datafilteringScriptTool with SSL

When the Unica Platform is deployed using one-way SSL you must modify the `datafilteringScriptTool` script to add the SSL options that perform handshaking. To modify the script, you must have the following information.

- Truststore file name and path
- Truststore password

In a text editor, open the `datafilteringScriptTool` script (`.bat` or `.sh`) and find the lines that look like this (examples are Windows™ version).

```
:callexec

"%JAVA_HOME%\bin\java" -DUNICA_PLATFORM_HOME="%UNICA_PLATFORM_HOME%"

com.unica.management.client.datafiltering.tool.DataFilteringScriptTool %*
```

Edit these lines to look like this (new text is in **bold**). Substitute your truststore path and file name and truststore password for `myTrustStore.jks` and `myPassword`.

```
:callexec

SET SSL_OPTIONS=-Djavax.net.ssl.keyStoreType="JKS"

-Djavax.net.ssl.trustStore="C:\security\myTrustStore.jks"

-Djavax.net.ssl.trustStorePassword=myPassword

"%JAVA_HOME%\bin\java" -DUNICA_PLATFORM_HOME="%UNICA_PLATFORM_HOME%"

%SSL_OPTIONS%

com.unica.management.client.datafiltering.tool.DataFilteringScriptTool %*
```

Syntax

```
datafilteringScriptTool -r pathfile
```

Commands

```
-r path_file
```

Import data filter specifications from a specified XML file. If the file is not located in the `tools/bin` directory under your installation, provide a path and enclose the `path_file` parameter in double quotation marks.

Example

- Use a file named `collaborateDataFilters.xml`, located in the `C:\unica\xml` directory, to populate the data filter system tables.

```
datafilteringScriptTool -r "C:\unica\xml\collaborateDataFilters.xml"
```

ManagerSchema_PurgeDataFiltering.sql

The `ManagerSchema_PurgeDataFiltering.sql` script removes all data filtering data from the Unica Platform system tables without removing the data filter tables themselves. This script removes all data filters, data filter configurations, audiences, and data filter assignments from Unica Platform.

When to use ManagerSchema_PurgeDataFiltering.sql

You might want to use `ManagerSchema_PurgeDataFiltering.sql` if you need to remove all data filters without removing other data in the Unica Platform system tables.



Important: The `ManagerSchema_PurgeDataFiltering.sql` script does not reset the values of the two data filter properties, `Default table name` and `Default audience name`. If these values are no longer valid for the data filters you want to use, you must set the values manually on the Configuration page.

Populating the data filter system tables

Run the `datafilteringScriptTool` utility, which uses your XML to populate the data filter system tables.

For details on using the `datafilteringScriptTool` utility, see the full description elsewhere in this guide.



Note: If you need to delete data filters, run the `ManagerSchema_PurgeDataFiltering.sql` script, described elsewhere in this guide.

Creating the XML to specify data filters

Create the XML file that specifies the customer data used as criteria in each data filter. In the next step you will run a utility that populates the system tables with these specifications.

To create the data filters, the `datafilteringScriptTool` utility uses an XML representation of the data to insert entries into the Unica Platform system table database.

Here is an overview of the elements in the XML that you create.

- `<Execute Batch>` - Command that initiates the data insertion process. This is repeated several times within the XML.
- `<AddDataConfiguration>` - Defines the data configurations, which are groups of related data filters.
- `<AddLogicalFields>` - Defines the fields on which to filter, and the data type of the fields.
- `<AddDataFilter>` - When you use **manual specification**, references a defined logical field, and specifies the field constraints.
- `<GenerateDataFilters>` - When you use **automatic specification**, references the fields and the values that limit the records considered for unique combinations of values used to define a set of data filters.
- `<AddDataTable>` - Defines the relationship between logical fields and their physical tables and columns. One logical field can apply to different physical tables, which allows one filter to apply to several tables.
- `<addAudiences>` - References a defined logical field, and specifies the audience level as defined in Unica Campaign.
- `<addAudienceTableAssociations>` - Defines the relationship between an audience level and the defined table and the defined data filter configuration.
- `<AddAssignments>` - When you **create assignments within the XML rather than using the user interface**, associates individual users or groups of users with defined data filters.

For additional information, including descriptions of additional elements that are nested within the elements described above, see these topics in this chapter:

- The detailed descriptions of each element in the XML
- The XML provided in the example scenarios

Data filter XML reference

This section describes the XML elements for which you must provide values.

Example: Manually specifying data filters

Jim needs to create a set of data filters based on sales territories.

In Unica Campaign, the customer tables have already been mapped and audience levels have been defined.

Obtaining information

Jim determines that the Territory table contains the fields he needs to specify field constraints for the data filters.

The following table illustrates the information Jim obtains about the customer fields and their Unica Campaign mappings.

Table 113. Territory table fields

Fields (physical name)	Fields (name in Unica Campaign)	Data	Data type
cust_region	CustomerRegion	<ul style="list-style-type: none"> • Africa • Asia • Europe • Middle East • North America 	java.lang-String
hh_id	HouseholdID	N/A	java.lang.Long
indiv_id	IndividualID	N/A	java.lang.Long

Jim learns that the audience names used in Unica Campaign are household and individual. He notes that the Territory table contains two audience fields. The hh_id field corresponds to the household audience. The indiv_id field in the Territory table corresponds to the individual audience.

Because Jim must create one logical field for each audience, and one for the field constraint field, he knows he needs a total of three logical fields.

Jim also knows he needs to group the data filters in a data configuration. He decides to name his data configuration Territory.

Jim is now ready to create the XML.

Creating the XML

Here is the XML that Jim creates. Values based on the information he obtained are shown in **bold**.

```
<ExecuteBatch>
    <!-- ***** -->
    <!--          Data configuration          -->
    <!-- ***** -->

    <name>SeedData</name>

    <operations>
        <ExecuteBatch>
            <name>DataFilters</name>
            <operations>
                <AddDataConfiguration>
                    <dataConfiguration>
                        <id>1</id>
                        <name>Territory</name>
                    </dataConfiguration>
                </AddDataConfiguration>
            </operations>
        </ExecuteBatch>
        <!-- ***** -->
        <!--          Logical fields          -->
        <!-- ***** -->

        <AddLogicalFields>
```

```

<logicalFields>
  <LogicalField>
    <id>1</id>
    <name>CustomerRegion</name>
    <type>java.lang.String</type>
  </LogicalField>
  <LogicalField>
    <id>2</id>
    <name>HouseholdID</name>
    <type>java.lang.Long</type>
  </LogicalField>
  <LogicalField>
    <id>3</id>
    <name>IndividualID</name>
    <type>java.lang.Long</type>
  </LogicalField>
</logicalFields>
</AddLogicalFields>
  <!-- ***** -->
  <!-- Territory field constraints -->
  <!-- ***** -->
<AddDataFilters>
  <dataFilters>
    <DataFilter>
      <configId>1</configId>
      <id>1</id>
      <fieldConstraints>
        <FieldConstraint>
          <logicalFieldId>1</logicalFieldId>
          <expression>Africa</expression>
        </FieldConstraint>
      </fieldConstraints>
    </DataFilter>
  </dataFilters>
</AddDataFilters>

```

```
</DataFilter>
<DataFilter>
  <configId>1</configId>
  <id>2</id>
  <fieldConstraints>
    <FieldConstraint>
      <logicalFieldId>1</logicalFieldId>
      <expression>Asia</expression>
    </FieldConstraint>
  </fieldConstraints>
</DataFilter>
<DataFilter>
  <configId>1</configId>
  <id>3</id>
  <fieldConstraints>
    <FieldConstraint>
      <logicalFieldId>1</logicalFieldId>
      <expression>Europe</expression>
    </FieldConstraint>
  </fieldConstraints>
</DataFilter>
<DataFilter>
  <configId>1</configId>
  <id>4</id>
  <fieldConstraints>
    <FieldConstraint>
      <logicalFieldId>1</logicalFieldId>
      <expression>Middle East</expression>
    </FieldConstraint>
  </fieldConstraints>
</DataFilter>
<DataFilter>
```

```

    <configId>1</configId>
    <id>5</id>
    <fieldConstraints>
      <FieldConstraint>
        <logicalFieldId>1</logicalFieldId>
        <expression>North America</expression>
      </FieldConstraint>
    </fieldConstraints>
  </DataFilter>
</dataFilters>
</AddDataFilters>
    <!-- ***** -->
    <!-- Map physical to logical fields -->
    <!-- ***** -->
<ExecuteBatch>
  <name>addTables</name>
  <operations>
    <AddDataTable>
      <dataTable>
        <id>1</id>
        <name>Territory</name>
        <fields>
          <TableField>
            <name>cust_region</name>
            <logicalFieldId>1</logicalFieldId>
          </TableField>
          <TableField>
            <name>hh_id</name>
            <logicalFieldId>2</logicalFieldId>
          </TableField>
          <TableField>
            <name>indiv_id</name>

```

```

        <logicalFieldId>3</logicalFieldId>
    </TableField>
</fields>
</dataTable>
</AddDataTable>
</operations>
</ExecuteBatch>
    <!--
***** -->
    <!-- Audience table associations
-->
    <!--
***** -->
<ExecuteBatch>
    <name>addAudiences</name>
    <operations>
    <AddAudience>
        <audience>
            <id>1</id>
            <name>household</name>
            <fields>
                <AudienceField>
                    <logicalFieldId>2</logicalFieldId>
                    <fieldOrder>0</fieldOrder>
                </AudienceField>
            </fields>
        </audience>
    </AddAudience>
    <AddAudience>
        <audience>
            <id>2</id>
            <name>individual</name>

```

```

    <fields>
      <AudienceField>
        <logicalFieldId>3</logicalFieldId>
        <fieldOrder>0</fieldOrder>
      </AudienceField>
    </fields>
  </audience>
</AddAudience>
</operations>
</ExecuteBatch>
  <!--
***** -->
  <!--          Associate table-audience pairs
-->
  <!--          with data configuration
-->
  <!--
***** -->
<ExecuteBatch>
  <name>addAudienceTableAssociations</name>
  <operations>
    <AddAudienceTableAssociation>
      <audienceTableAssociation>
        <audienceId>1</audienceId>
        <tableId>1</tableId>
        <configId>1</configId>
      </audienceTableAssociation>
    </AddAudienceTableAssociation>
    <AddAudienceTableAssociation>
      <audienceTableAssociation>
        <audienceId>2</audienceId>
        <tableId>1</tableId>

```

```
        <configId>1</configId>
    </audienceTableAssociation>
</AddAudienceTableAssociation>
</operations>
</ExecuteBatch>
</operations>
</ExecuteBatch>
```

Populating the system tables

Jim has named his data filter XML file `regionDataFilters.xml` and saved it in the `tools/bin` directory under his Unica Platform installation. He opens a command prompt and uses the `datafilteringScriptTool` utility to populate the data filter system tables.

Assigning users and groups to the data filters

Finally, Jim logs in to Unica with an account that has Admin access in Unica Platform.

He knows that groups have already been set up in Unica with users assigned by region.

He goes to the Data Filter section and sees that the field constraints from his data filters are available in the advanced search for data filters. He performs a search for a data filter, using Africa as a search criterion. The data filter he set up for the Africa region appears in the search results.

Next, Jim performs a search for the Africa user group, which has been set up in Unica to hold all field marketers who are responsible for marketing to customers in Africa. The Africa group appears in the search results.

Jim then selects the group and the data filter in the search results, and assigns the group to the data filter by clicking the Assign button.

He continues to perform searches for data filters and groups until all assignments are completed.

Example: Automatically generating a set of data filters

Jim needs to create a set of data filters based on countries, cities, and states.

In Unica Campaign, the customer tables have already been mapped and audience levels have been defined.

Obtaining the JDBC driver

Jim knows that his company's customer database is Microsoft™ SQL server. He downloads the appropriate Type 4 driver and places it on the machine where the Unica Platform is installed, making a note of the name and path of the driver.

- JDBC driver class name - `com.microsoft.sqlserver.jdbc.SQLServerDriver`
- JDBC driver path - `C:\tools\Java\MsJdbc\sqljdbc.jar`

Obtaining information

Jim obtains the name, host, and port of the customer database, and the credentials he needs to connect to it.

- Database name - Customers
- Database host name - companyHost
- Database port - 1433
- User name - sa
- Password - myPassword

Jim looks at the data in his company's customer database and sees that customers exist in every country, city, and state for which he wants to create a data filter. He determines that the Geographic table contains the fields he needs to specify fixed fields and profile fields for the data filters.

The following table illustrates the information Jim obtains about the customer fields and their Unica Campaign mappings.

Table 114. Geographic table fields

Fields (Physical name)	Fields (Name in Uni- ca Campaign)	Data	Data type
country	Country	<ul style="list-style-type: none"> • USA • France • Britain 	java.lang- .String
city	City	A finite set of distinct cities	java.lang- .String
state	State	A finite set of distinct states (or otherwise named regions, depending on country)	java.lang- .String
hh_id	HouseholdID	N/A	ja- va.lang.Long
indiv_id	IndividualID	N/A	ja- va.lang.Long

Jim learns that the audience names used in Unica Campaign are household and individual. He notes that the Geographic table contains two audience fields.

- The `hh_id` field corresponds to the household audience.
- The `indiv_id` field in the Geographic table corresponds to the individual audience.

Because Jim must create one logical field for each audience, and one for each of the fixed and profile fields, he knows he needs a total of five logical fields.

Jim also knows he needs to group the data filters in a data configuration. He decides to name his data configuration Geographic.

Jim is now ready to create the XML.

Creating the XML

Here is the XML that Jim creates. Values based on the information he obtained or decided to use are shown in **bold**.

```
<ExecuteBatch>
    <!-- ***** -->
    <!--          Data configuration          -->
    <!-- ***** -->
    <name>SeedData</name>
    <operations>
        <ExecuteBatch>
            <name>DataFilters</name>
            <operations>
                <AddDataConfiguration>
                    <dataConfiguration>
                        <id>1</id>
                        <name>Geographic</name>
                    </dataConfiguration>
                </AddDataConfiguration>
            </operations>
        </ExecuteBatch>
        <!-- ***** -->
        <!--          Logical fields          -->
        <!-- ***** -->
        <AddLogicalFields>
            <logicalFields>
                <LogicalField>
                    <id>1</id>
                    <name>Country</name>
                    <type>java.lang.String</type>
                </LogicalField>
                <LogicalField>
```

```

        <id>2</id>
        <name>City</name>
        <type>java.lang.String</type>
    </LogicalField>
    <LogicalField>
        <id>3</id>
        <name>State</name>
        <type>java.lang.String</type>
    </LogicalField>
    <LogicalField>
        <id>4</id>
        <name>HouseholdID</name>
        <type>java.lang.Long</type>
    </LogicalField>
    <LogicalField>
        <id>5</id>
        <name>IndividualID</name>
        <type>java.lang.Long</type>
    </LogicalField>
</logicalFields>
</AddLogicalFields>
    <!-- ***** -->
    <!--          Generate data filters          -->
    <!-- ***** -->
    <GenerateDataFilters>
        <!--
***** -->
        <!-- Specify the table to be scanned for unique
combinations -->
        <!-- of values  from which data filters will be defined.
-->
-->

```

```

        <!--
***** -->
        <tableName>Geographic</tableName>
        <!--
***** -->
        <!-- Identify the data configuration with which
-->
        <!-- generated data filters will be associated.
-->
        <!--
***** -->
        <configurationName>Geographic</configurationName>
        <!-- Specify the data source connection information. -->
        <jdbcUrl>
            jdbc:sqlserver://localhost:1433;databaseName=Customers
        </jdbcUrl>
        <jdbcUser>sa</jdbcUser>
        <jdbcPassword>myPassword</jdbcPassword>
        <jdbcDriverClass>
com.microsoft.sqlserver.jdbc.SQLServerDriver</jdbcDriverClass>
        <jdbcDriverClassPath>
            <string>C:\tools\Java\MsJdbc\sqljdbc.jar</string>
        </jdbcDriverClassPath>
        <!-- ***** -->
        <!-- Specify the fixed fields -->
        <!-- ***** -->
        <fixedFields>
            <FixedField>
                <expression>USA</expression>
                <logicalFieldName>Country</logicalFieldName>
                <physicalFieldName>country</physicalFieldName>

```

```

    </FixedField>
    <FixedField>
      <expression>France</expression>
      <logicalFieldName>Country</logicalFieldName>
      <physicalFieldName>country</physicalFieldName>
    </FixedField>
    <FixedField>
      <expression>Britain</expression>
      <logicalFieldName>Country</logicalFieldName>
      <physicalFieldName>country</physicalFieldName>
    </FixedField>
  </fixedFields>
  <!-- Specify the profile fields. -->
  <profileFields>
    <ProfileField>
      <logicalFieldName>State</logicalFieldName>
      <physicalFieldName>state</physicalFieldName>
    </ProfileField>
    <ProfileField>
      <logicalFieldName>City</logicalFieldName>
      <physicalFieldName>city</physicalFieldName>
    </ProfileField>
  </profileFields>
</GenerateDataFilters>
  <!-- ***** -->
  <!-- Map physical to logical fields -->
  <!-- ***** -->
<ExecuteBatch>
  <name>addTables</name>
  <operations>
    <AddDataTable>
      <dataTable>

```

```

<id>1</id>
<name>Geographic</name>
<fields>
  <TableField>
    <name>country</name>
    <logicalFieldId>1</logicalFieldId>
  </TableField>
  <TableField>
    <name>city</name>
    <logicalFieldId>2</logicalFieldId>
  </TableField>
  <TableField>
    <name>state</name>
    <logicalFieldId>3</logicalFieldId>
  </TableField>
  <TableField>
    <name>hh_id</name>
    <logicalFieldId>4</logicalFieldId>
  </TableField>
  <TableField>
    <name>indiv_id</name>
    <logicalFieldId>5</logicalFieldId>
  </TableField>
</fields>
</dataTable>
</AddDataTable>
</operations>
</ExecuteBatch>
<!--
***** -->
<!-- Audience table associations
-->

```

```

      <!--
***** -->

<ExecuteBatch>
  <name>addAudiences</name>
  <operations>
    <AddAudience>
      <audience>
        <id>1</id>
        <name>household</name>
        <fields>
          <AudienceField>
            <logicalFieldId>4</logicalFieldId>
            <fieldOrder>0</fieldOrder>
          </AudienceField>
        </fields>
      </audience>
    </AddAudience>
    <AddAudience>
      <audience>
        <id>2</id>
        <name>individual</name>
        <fields>
          <AudienceField>
            <logicalFieldId>5</logicalFieldId>
            <fieldOrder>0</fieldOrder>
          </AudienceField>
        </fields>
      </audience>
    </AddAudience>
  </operations>
</ExecuteBatch>

```

```

        <!--
***** -->
        <!--          Associate table-audience pairs
-->
        <!--          with data configuration
-->
        <!--
***** -->
    <ExecuteBatch>
        <name>addAudienceTableAssociations</name>
        <operations>
            <AddAudienceTableAssociation>
                <audienceTableAssociation>
                    <audienceId>1</audienceId>
                    <tableId>1</tableId>
                    <configId>1</configId>
                </audienceTableAssociation>
            </AddAudienceTableAssociation>
            <AddAudienceTableAssociation>
                <audienceTableAssociation>
                    <audienceId>2</audienceId>
                    <tableId>1</tableId>
                    <configId>1</configId>
                </audienceTableAssociation>
            </AddAudienceTableAssociation>
        </operations>
    </ExecuteBatch>
</operations>
</ExecuteBatch>

```

Populating the system tables

Jim has named his data filter XML file `geographicDataFilters.xml` and saved it in `tools/bin` directory under his Unica Platform installation. He opens a command prompt and uses the `datafilteringScriptTool` utility to populate the data filter system tables.

The utility creates many data filters. In each data filter, the criteria are a country (the fixed field) and a unique combination of city and state obtained when the utility queried the database for records containing the fixed field value. All unique combinations of city and state are used for each country specified as a fixed field.

Assigning users and groups to the data filters

Finally, Jim logs in to the Unica Platform with an account that has Admin access in Unica Platform.

He knows that groups have already been set up in Unica Platform with users assigned by city.

He goes to the Data Filter section and sees that the country, city, and state values from his data filters are available in the advanced search for data filters. He performs a search for a data filter, using Boston, a city in the USA, as a search criterion. The data filter for Boston appears in the search results.

Next, Jim performs a search for the Boston user group, which has been set up in Unica Platform to hold all field marketers who are responsible for marketing to customers in Boston. The Boston group appears in the search results.

Jim then selects the group and the data filter in the search results, and assigns the group to the data filter by clicking the Assign button.

He continues to perform searches for data filters and groups until all assignments are completed.

Setting required data filter configuration properties

Set required configuration properties to enable data filtering.

On the **Settings & Configuration** page, navigate to the **General | Data filtering** category and set the following properties.

- Default table name
- Default audience name

See each property's context help or the related topic link in this section for instructions on setting the values.

Optional configuration property to improve data filter performance

You can turn the data filter cache on for better performance.

To improve performance, set the value of the **General | Data filtering | Enable data filter cache** property to **true**. This property specifies whether Unica Platform retrieves data filter definitions from the database or from a cache. When this value is **true**, data filter definitions are stored in the cache and the cache is updated whenever there is any change in the data filter definitions.

You must restart the Unica Platform web application after you make a change in this property value before it can take effect.

HCL Unica | General | Data filtering

Properties in this category specify values used when data filtering is implemented.

Default table name

Description

This configuration property is required to enable data filters.

Set the value of this property to exactly match the name used for the `addTables | AddDataTable | dataTable | name` element in the XML used to create the data filters.

Default value

Undefined

Valid values

Maximum of 50 characters of type varchar.

Default audience name

Description

This configuration property is required to enable data filters.

Set the value of this property to exactly match the name used for the `AddAudience | audience | name` element in the XML used to create the data filters.

Default value

Undefined

Valid values

Maximum of 50 characters of type varchar.

Enable data filter cache

Description

This property is optional, and can be set to improve data filter performance.

This property specifies whether the Unica Platform retrieves data filter definitions from the database or from a cache. When this value is **true**, data filter definitions are stored in the cache and the cache is updated whenever there is any change in the data filter definitions.

You must restart the Unica Platform web application after you make a change in this property value before it can take effect.

Default value

False

Two ways to assign users and groups: in the user interface and in the XML

You have two options for assigning users and groups to data filters: through the user interface or in the XML you use to create the data filters. Assigning users in the XML is a useful method when you have many users, each of whom requires a separate filter.

Assigning users in the XML is available only when you create data filters using **manual specification**. When you assign users in the XML, you need the data filter IDs to specify the assignment, and these IDs are available only when you specify data filters using manual specification, not with automatic specification.

Details about using both methods for assigning users and groups are provided in this chapter.

Assigning users and groups to data filters

If you do not assign users or groups within the XML that you create, use the Unica data filter user interface to perform searches for users, groups, and data filters and then select items from the search results and assign them.

About assigning users and groups in the XML

You can assign users or groups to data filters in the XML, as an alternative to doing this through the user interface. Assigning users and groups to data filters in the XML is available only when you use manual specification to create the data filters.

You can use a wild card, `#user_login#`, that automatically creates data filters based on the user's Unica Platform login name.

You use the `AddAssignments` XML element block to associate users or groups with your data filters.

Scenario used in the example

The example uses the following scenario.

An organization uses Unica Collaborate and wants to create data filters that allow field marketers to see only the customers in the region to which they are assigned. Thus, each user requires his or her own data filter.

In Unica Collaborate the list display and the form templates are set up based on region. This configuration is described in more detail in the Unica Collaborate Administrator's Guide.

The audience level is Customer.

The data filters are created against four tables in the `exampleSchema` database, as described in the following table.

Table 115. Tables and fields used in the examples

Table	Fields
<code>exampleSchema.Corporate_Lists</code>	UserID, State, and RegionID This is the list display table set up in Unica Collaborate. The UserID column contains the Unica Platform login names of the field marketers. This table associates field marketer Unica Platform login names with their assigned region.
<code>exampleSchema.customer_contact</code>	Indiv_ID, Region_ID, and State fields for customers
<code>exampleSchema.lkup_state</code>	A lookup table for the <code>state_name</code> field
<code>exampleSchema.lkup_region</code>	A lookup table for the <code>region_id</code> field

Example: Using the wild card to assign group members to data filters

To create a separate data filter for each member of a specified group, you do the following.

- Create logical fields as usual.
- Create a single data filter with the wild card `#user_login#` in the `expression` element.


```

        <type>java.lang.String</type>
    </LogicalField>

    <LogicalField>
        <id>2</id>
        <name>AudienceLevel</name>
        <type>java.lang.String</type>
    </LogicalField>

    <LogicalField>
        <id>3</id>
        <name>UserID</name>
        <type>java.lang.String</type>
    </LogicalField>

    <LogicalField>
        <id>4</id>
        <name>State_code</name>
        <type>java.lang.String</type>
    </LogicalField>

    <LogicalField>
        <id>5</id>
        <name>Region</name>
        <type>java.lang.Long</type>
    </LogicalField>
</logicalFields>
</AddLogicalFields>

    <!-- ***** -->
    <!--      Wild card data filter      -->
    <!-- ***** -->

<AddDataFilters>

```

```

<dataFilters>
  <DataFilter><
    <configId>1</configId>
    <id>1</id>
    <fieldConstraints>
      <FieldConstraint>
        <logicalFieldId>3</logicalFieldId>
        <expression>#user_login#</expression>
      </FieldConstraint>
    </fieldConstraints>
  </DataFilter>
</dataFilters>
</AddDataFilters>

  <!--
***** -->
  <!--           Add data tables
-->

  <!--
***** -->

  <ExecuteBatch>
    <name>addTables</name>
    <operations>
      <!--
***** -->
      <!--           Table exampleSchema.Corporate_Lists
-->

      <!--
***** -->

      <AddDataTable>
        <dataTable>
          <id>1</id>

```

```

        <name>exampleSchema.Corporate_Lists</name>
        <fields>
            <TableField>
                <tableId>1</tableId>
                <name>UserID</name>
                <logicalFieldId>3</logicalFieldId>
            </TableField>
            <TableField>
                <tableId>1</tableId>
                <name>State</name>
                <logicalFieldId>4</logicalFieldId>
            </TableField>
            <TableField>
                <tableId>1</tableId>
                <name>Region_ID</name>
                <logicalFieldId>5</logicalFieldId>
            </TableField>
        </fields>
    </dataTable>
</AddDataTable>
<!--
***** -->
<!--          Table exampleSchema.customer_contact
-->
<!--
***** -->
<AddDataTable>
    <dataTable>
        <id>2</id>
        <name>exampleSchema.customer_contact</name>
        <fields>
            <TableField>

```

```

        <tableId>2</tableId>
        <name>Indiv_ID</name>
        <logicalFieldId>1</logicalFieldId>
    </TableField>
    <TableField>
        <tableId>2</tableId>
        <name>Region_ID</name>
        <logicalFieldId>5</logicalFieldId>
    </TableField>
    <TableField>
        <tableId>2</tableId>
        <name>State</name>
        <logicalFieldId>4</logicalFieldId>
    </TableField>
    </fields>
</dataTable>
</AddDataTable>
<!--
***** -->
<!--          Table exampleSchema.lkup_state
-->
<!--
***** -->
<AddDataTable>
    <dataTable>
        <id>3</id>
        <name>example.schema.lkup_state</name>
        <fields>
            <TableField>
                <tableId>3</tableId>
                <name>state_name</name>
                <logicalFieldId>4</logicalFieldId>

```

```

        </TableField>
    </fields>
</dataTable>
</AddDataTable>
<!--
***** -->
<!--          Table exampleSchema.lkup_region
-->
<!--
***** -->
<AddDataTable>
    <dataTable>
        <id>4</id>
        <name>exampleSchema.lkup_region</name>
        <fields>
            <TableField>
                <tableId>4</tableId>
                <name>Region_ID</name>
                <logicalFieldId>5</logicalFieldId>
            </TableField>
        </fields>
    </dataTable>
</AddDataTable>
</operations>
</ExecuteBatch>
<!--
***** -->
<!--          Audience table associations
-->
<!--
***** -->
<ExecuteBatch>

```

```
<name>addAudiences</name>
<operations>
  <AddAudience>
    <audience>
      <id>1</id>
      <name>Customer</name>
      <fields>
        <AudienceField>
          <logicalFieldId>2</logicalFieldId>
          <fieldOrder>0</fieldOrder>
        </AudienceField>
      </fields>
    </audience>
  </AddAudience>

  <AddAudience>
    <audience>
      <id>2</id>
      <name>default</name>
      <fields>
        <AudienceField>
          <logicalFieldId>2</logicalFieldId>
          <fieldOrder>0</fieldOrder>
        </AudienceField>
      </fields>
    </audience>
  </AddAudience>
</operations>
</ExecuteBatch>

<ExecuteBatch>
  <name>addAudienceTableAssociations</name>
```

```
<operations>
  <AddAudienceTableAssociation>
    <audienceTableAssociation>
      <audienceId>1</audienceId>
      <tableId>1</tableId>
      <configId>1</configId>
    </audienceTableAssociation>
  </AddAudienceTableAssociation>

  <AddAudienceTableAssociation>
    <audienceTableAssociation>
      <audienceId>1</audienceId>
      <tableId>2</tableId>
      <configId>1</configId>
    </audienceTableAssociation>
  </AddAudienceTableAssociation>

  <AddAudienceTableAssociation>
    <audienceTableAssociation>
      <audienceId>2</audienceId>
      <tableId>3</tableId>
      <configId>1</configId>
    </audienceTableAssociation>
  </AddAudienceTableAssociation>

  <AddAudienceTableAssociation>
    <audienceTableAssociation>
      <audienceId>2</audienceId>
      <tableId>4</tableId>
      <configId>1</configId>
    </audienceTableAssociation>
  </AddAudienceTableAssociation>
</operations>
```

```

        </operations>
    </ExecuteBatch>
        <!--
***** -->
        <!--          Link filters (dataObjectId) to group
-->
        <!--
***** -->
    <AddAssignments>
        <assignments>
            <AssignmentByName>
                <namespaceId>1</namespaceId>
                <dataObjectId>1</dataObjectId>
                <principalType>2</principalType>
                <principalName>FieldMarketer</principalName>
            </AssignmentByName>
        </assignments>
    </AddAssignments>
</operations>
</ExecuteBatch>

```

About assigning user and groups through the user interface

You can assign users and groups to data filters on the **Settings > Data filters** pages.

To work with data filters on the **Settings > Data filters** pages, the following must be true.

- The data filters must be set up in Unica Platform system tables.
- You must log in as a user with the Unica Platform permission **Administer data filters page**. The pre-configured Unica Platform **AdminRole** role has this permission.

Optional configuration property to improve data filter performance

You can turn the data filter cache on for better performance.

To improve performance, set the value of the **General | Data filtering | Enable data filter cache** property to **true**. This property specifies whether Unica Platform retrieves data filter definitions from the database or from a cache. When this value is **true**, data filter definitions are stored in the cache and the cache is updated whenever there is any change in the data filter definitions.

You must restart the Unica Platform web application after you make a change in this property value before it can take effect.

HCL Unica | General | Data filtering

Properties in this category specify values used when data filtering is implemented.

Default table name

Description

This configuration property is required to enable data filters.

Set the value of this property to exactly match the name used for the `addTables | AddDataTable | dataTable | name` element in the XML used to create the data filters.

Default value

Undefined

Valid values

Maximum of 50 characters of type varchar.

Default audience name

Description

This configuration property is required to enable data filters.

Set the value of this property to exactly match the name used for the `AddAudience | audience | name` element in the XML used to create the data filters.

Default value

Undefined

Valid values

Maximum of 50 characters of type varchar.

Enable data filter cache**Description**

This property is optional, and can be set to improve data filter performance.

This property specifies whether the Unica Platform retrieves data filter definitions from the database or from a cache. When this value is **true**, data filter definitions are stored in the cache and the cache is updated whenever there is any change in the data filter definitions.

You must restart the Unica Platform web application after you make a change in this property value before it can take effect.

Default value

False

Schedule notifications

You can set up notifications for any schedule, to alert you to the status of scheduled runs. In addition, users with Administrator permissions in Unica Platform can set up groups to which notifications are sent.

Individual schedule notifications

You can create notifications for your schedules only after you have created and saved the schedule, not during the creation process. You can configure which statuses trigger a

notification, and whether the notifications for each schedule are sent to your email account, or appear in your notification in-box, or both.

Group schedule notifications

If you want users other than the creator of a schedule to receive schedule notifications, you can enable group-based notifications. You must have administrator permissions in Unica Platform to set up group notifications.

A configuration property, **Group Name to receive the Job Notifications**, is included for each object type that can be scheduled under the **Platform | Scheduler | Schedule registration | [Product] | [Object type]** category on the **Settings > Configuration** page. All members of the group specified in this configuration property receive notifications for all schedules for that object type (for example, Campaign flowcharts).

Group members receive notifications set up for scheduled runs that have the **Long Duration** or **Not Started/Queued** status. They do not receive notifications for runs with the **On Failure**, **On Success**, or **Unknown/"Other" problem** status.

By adding or removing users in a group, you can control who receives these notifications.

Configuring email notifications in Unica

Follow this procedure to configure the Unica Platform to send system alert and notification emails to users. You must have an email server set up before you start.

Obtain the following information about your mail server.

- The protocol used by your mail server.
- The port on which the mail server listens.
- The name of the machine that hosts your mail server.
- Whether your mail server requires authentication.
- If your mail server requires authentication, an account name and password on the mail server.

 **Tip:** See the related references if you need additional details about performing this procedure.

1. If your mail server requires authentication, save a mail server account name and password as a data source in a Unica Platform user account.

Use an internal Unica Platform user account, not a user imported from an LDAP server.

Make a note of the Unica Platform user name and the data source name, as you will use them in step 3.

2. Log in to Unica as a user with administrative privileges in Unica Platform.
3. On the **Settings > Configuration** page, set the configuration properties in the following categories.

- General | Communication | Email
- Platform | Notifications

Use the information you obtained about your mail server to set values.

Alert and notification management

Unica Platform provides support for system alerts and user notifications sent by Unica products.

System alerts and user notifications sent by products appear in the user interface, as follows.

- **Alerts** contain information about system events. They appear in a pop-up window when a user logs in.

Examples are planned or unplanned server shutdowns.

- **Notifications** contain user-specific information about changes made to items in which the user has an interest, or tasks the user must perform. The user can view them by clicking the envelope icon in the top right of the window.

Examples are updates to a flowchart or mailing list, or reminders about a deadline for an assigned task.

Users can also subscribe to receive alerts and notifications by email, if Unica Platform has been configured to send them.

Within Unica Platform, the Unica Scheduler uses the notification feature.

HCL Unica | General | Communication | Email

Properties in this category are used to configure the Unica Platform to send emails to users for system alerts and notifications.

Enable email communication

Description

When set to `True`, the Unica Platform attempts to send emails to users for system alerts and notifications. The other properties in this category must also be set to enable this feature.

Default value

`False`

Email server protocol

Description

Specifies the protocol on the mail server that is used for sending system alerts and notifications to users. This is required for email notifications.

Default value

`smtp`

Email server host

Description

Specifies the name of the mail server used for sending system alerts and notifications to users. This is required for email notifications.

Default value

`localhost`

Email server port

Description

Specifies the port of the mail server used for sending system alerts and notifications to users. This is required for email notifications.

Default value

25

'From' address for emails

Description

Specifies the account from which system alert and notification emails are sent. If authentication is required on your mail server, use the email address of the account that you used when you saved a mail server account name and password as a data source in a Unica Platform user account. This is required for email notifications.

Default value

Not defined

Authentication required for mail server?

Description

Specifies whether the mail server requires authentication.

Default value

False

Unica user for email account

Description

Specifies the user name of the Unica Platform account where the email credentials are stored as a data source.

Required for notifications, only if your mail server requires authentication.

Default value

`asm_admin`

Data source for email account

Description

Specifies the name of the data source in the Unica Platform account where the email credentials are stored.

Required for notifications, only if your mail server requires authentication.

Default value

`emailDS`

Platform | Notifications

Properties in this category control system behavior for notifications that Unica products can send to users.

How many days to retain alerts

Description

Specifies the amount of time, in days, that a system alert is retained in the system for historical purpose after the expiry date, which is provided by the application that sent the alert. Alerts older than the specified number of days are deleted from the system.

Default value

90

How frequently to send emails (in minutes)

Description

Specifies how many minutes the system waits before sending any new notification emails.

Default value

30

Maximum re-tries for sending email

Description

Specifies how many times the system attempts to send notification emails when an initial attempt to send fails.

Default value

1

Configure your web application servers for SSL

On every application server on which an Unica application is deployed, configure the web application server to use the certificates you have decided to employ.

See your web application server documentation for details on performing these procedures.

SSL in Unica

Many application components can act as both server and client during normal operations, and some components are written in Java™ and some in C++. These facts determine the format of the certificates you use. You specify the format when you create a self-signed certificate or purchase one from a CA.

applications do not require a truststore when they act as a client making one-way SSL requests to an server component.

Java™ component acting as a server

For applications written in Java™, using the JSSE SSL implementation, and deployed on an application server, you must configure the application server to use your certificate. The certificate must be stored in JKS format.

You cannot use the default certificate provided with the application server.

You can create JKS certificates for your Java applications using Java keytool.

C++ component acting as a server

The Campaign listener, Optimize server component are written in C++, and require a certificate generated by OpenSSL.

Java™ component acting as a client

For applications written in Java™ and deployed on an application server, no truststore is needed. For ease of configuration, Java™ applications acting as a client do not authenticate the server during one-way SSL communications. However, encryption does take place.

C/C++ components acting as a client

For applications written in C/C++ and using the OpenSSL implementation, no truststore is required. The Campaign listener fall into this category.

How many certificates?

Ideally, you should use a different certificate for every machine that hosts an component acting as a server.

If you do not want to use multiple certificates, you can use the same certificate for all the components acting as servers. If you use one certificate for all applications, when users access applications for the first time, the browser asks whether they want to accept the certificate.

Configuring SSL in Unica Platform

Follow this procedure to configure SSL in Unica Platform.

1. Log in to Unica and click **Settings > Configuration**.
2. Set the value of the `General | Navigation | Unica Platform URL` property to Unica Platform URL.

For example: `https://host.domain:SSL_port/unica`

where:

- *host* is the name or IP address of the machine on which Unica Platform is installed
- *domain* is your company domain in which your Unica products are installed
- *SSL_Port* is the SSL port in the application server on which Unica Platform is deployed

Note `https` in the URL.

3. Locate the properties under the `Navigation` category for each of your installed Unica products where you set the HTTP and HTTPS ports. The names of the properties might vary by product, but their purpose should be obvious. For each product, set these values to the HTTP and HTTPS port in the application server on which the product is deployed.
4. If you have implemented LDAP integration, perform the procedure described in "Configuring SSL in Unica Platform with LDAP integration."
5. If you plan to use the data filtering feature, perform the procedure described in "Configuring SSL in Unica Platform with data filters."

Configuring SSL in Unica Platform with LDAP integration

Follow this procedure to configure SSL in Unica Platform.

1. Perform the procedure described in "Configuring SSL in Unica Platform" if you have not done so already.
2. Log in to Unica and click **Settings > Configuration**.

The Configuration page appears.

3. Navigate to the `Unica | Unica Platform | Security | Login Method details | LDAP` category and set the value of the `Require SSL for LDAP connection` property to `true`.

This setting requires Unica Platform to connect to the LDAP server using SSL when users log in.

4. Navigate to the `Unica | Unica Platform | Security | LDAP synchronization` category and set the following values.

- Set the value of the `LDAP_provider_URL` property to:

```
ldaps://host.domain:SSL_Port
```

where:

- `host` is the name or IP address of the LDAP server
- `domain` is the domain of the LDAP server
- `SSL_Port` is the SSL port of the LDAP server.

For example: `ldaps://LDAPMachine.myCompany.com:636`

Note the `ldaps` in the URL.

The default SSL port for LDAP servers is `636`.

- Set the value of the `Require SSL for LDAP connection` property to `true`.

This setting requires Unica Platform to connect to the LDAP server using SSL when it synchronizes with the LDAP server.

Configuring SSL in Unica Platform with data filters

When Unica Platform is deployed with SSL and you plan to use the data filtering feature, you must perform this procedure to add the SSL options that perform hand shaking.

1. Perform the procedure described in "Configuring SSL in Unica Platform" if you have not done so already.
2. Obtain the following.
 - A copy of the certificate file you created in Obtaining or creating certificates (*on page*)
 - The certificate password
3. Place the certificate file in the `JAVA_HOME/jre/lib/security` directory, where `JAVA_HOME` is the Java™ directory specified in the `tools/bin/setenv` script under your Unica Platform installation.

The `setenv` script specifies the Java™ instance used by Unica Platform utilities.

4. Use the `keytool` program to import the certificate into the `cacerts` file for your Java™ instance.

You can use the following example command as a guide.

```
keytool -import -trustcacerts -file name_of_your_certificate.cer  
-keystore cacerts
```

Enter the certificate password when prompted.

Security framework for Unica APIs

Unica Platform provides the security framework for the APIs implemented by Unica products.

A set of configuration properties on the **Settings > Configuration** page enables developers to set the following security for the APIs provided by Unica products.

- For a specific product API, you can block access to the product.
- For a specific product API, you can require HTTPS for communication between the specified API and the product.
- For a specific product API, you can require authentication for communication between the specified API and the product.

The configuration properties that control API security are located under the **Unica Platform | Security | API management** category. Each product has a configuration property template that you can use to create new security settings for the APIs provided by that product.

You can set and change the security settings for an API as appropriate for unit testing or deployment or during the overall lifecycle of APIs.

The security framework currently supports APIs for Unica Campaign only.

The Unica Platform security framework supports the following two authentication options for accessing protected APIs. You can use either one, depending on your environment.

- Internal users who are registered with Unica Platform can be authenticated using their Unica Platform login credentials to obtain a secure token.
- External users who are part of a federation that Unica Platform is set up to use can be authenticated through the Identity Provider server.

Internal user authentication with the Unica Platform login API

To authenticate internal users in client applications, use the Unica Platform `login` API to generate secure tokens. You can then invoke any protected APIs by passing the required parameters in the request header, in addition to the parameters expected by the API itself.

The security filter intercepts these protected requests, validates them, and then passes them through for processing.

After the Unica Platform user is authenticated, the Unica Platform security filter adds the user's login name to the request as an attribute of the `USER_NAME_STRING` key before passing it to the product for processing.

The secure tokens have a default life span of 15 seconds. After the life span of the token expires, it cannot be used to invoke a protected API. Each time the Unica Platform `login` API is invoked for a user, all previous security tokens for that user are invalidated.

You can change the life span of secure tokens by setting the value of the **Token lifetime** property located on the **Settings > Configuration** page under the **General | Miscellaneous** category.

Example URL

```
http[s]://host:port/unica/api/manager/authentication/login/
```

Header parameters

Table 116. Header parameters for the login API with internal users

Parameter	Description
<code>m_user_name</code>	The internal user's Unica Platform login name.
<code>m_user_password</code>	The internal user's Unica Platform password in plain text.

Response

When login succeeds, the response is HTTP 200 with the following JSON data.

- `m_tokenId` - randomly generated token
- `m_user_name` - user name of the logged in user
- `createDate` - timestamp in the format that is shown in the following example, where the time zone is IST:

```
Mon Jul 06 18:23:35 IST 2015
```

When login fails with bad credentials, the response is HTTP 401 (unauthorized). When the `login` API is configured to be blocked, the response is 403 (forbidden). When the `login` API is configured to use HTTPS and if it is invoked on HTTP, the response is 403 (forbidden).

To log out internal users, use the Unica Platform `logout` API.

Internal user logout with the Unica Platform `logout` API

Use the Unica Platform `logout` API to log out internal users and delete the secure token.

The `logout` API is protected by default. The authentication parameters are expected in the request header against pre-defined keys.

Example URL

```
http[s]://host:port/unica/api/manager/authentication/logout/
```

Header parameters

Table 117. Header parameters for the `logout` API

Parameter	Description
<code>m_user_name</code>	The internal user's Unica Platform login name.
<code>m_tokenId</code>	The secure token obtained through authentication.
<code>api_auth_mode</code>	Use the value <code>manager</code> for internal users.

Response

When authentication succeeds, the response is `HTTP 200`, and the secure token is deleted. If the response is HTTP 200, the client application should confirm the logout.

When authentication fails, the response is `HTTP 401`.

External user authentication and logout through a federation

When Unica Platform is integrated with a supported federation, users can log in to their own system, and the client application gets a token through the Identity Provider (IdP) server provided by Unica Platform.

After a federated user is authenticated, their corresponding Unica Platform login name is added to the request as an attribute of the `USER_NAME_STRING` key.

Log out should be done at the IdP server.

Header parameters

The following table describes the header parameters to use when authenticating through the IdP server provided by Unica Platform.

Table 118. Header parameters with a federation

Parameter	Description
<code>f_userId</code>	User ID in the federation.
<code>f_clientId</code>	Client ID in the federation.
<code>f_spld</code>	Service provider ID in the federation.
<code>f_tokenId</code>	Single sign-on token from the IdP server.
<code>api_auth_mode</code>	Use the value <code>f_sso</code> for federated authentication.

Response

The response is `HTTP 200`, with additional items depending on the API.

Platform | Security | API management | [Product] | (API configuration template)

Use the templates in this category to configure authentication for Unica APIs. You can block access, require HTTPS, or require authentication for APIs.

API URI

Description

For each product, the first part of the URI is resolved by the security framework, as follows: `http[s]://host:port/context root/api/product`

Therefore, in this field you should enter only the resource name or names of the API you want to configure. You can obtain the string you need to enter from the product's API documentation.

The value used for this property must start with a / (forward slash); otherwise the configuration is ignored by the security framework.

This property supports an exact URL match as well a pattern match for the configured APIs.

- For an exact match, the URI may end with a forward slash (/) or the resource name.
- For a pattern match, the URI must end with an asterisk (*).

If you set the value of this property to `/*` the settings you use for the other properties in the category apply to all APIs for the product.



Note: For the Unica Platform `login` API, this configuration property is read-only.

Default value

Undefined

Block API access

Description

Select this option when you want to prevent an API from accessing a product. This option is not selected by default.

When an API is blocked, the security filter returns the HTTP status code 403 (forbidden).

Secure API access over HTTPS

Description

Select this option when you want to allow the API to access a product only over HTTPS. This option is selected by default.

When an API with this property enabled is accessed over HTTP rather than HTTPS, the security filter returns the HTTP status code 403 (forbidden).

Require authentication for API access

Description

Select this option when you want to require an API to authenticate before it can access a product. This option is selected by default.

When an API with this property enabled is accessed with invalid credentials, the security filter returns the HTTP status code 401 (unauthorized).



Note: For the Unica Platform `login` API, this configuration property is disabled, as this API is the first to be called for API authentication.

Security framework for Unica APIs

Unica Platform provides the security framework for the APIs implemented by Unica products.

A set of configuration properties on the **Settings > Configuration** page enables developers to set the following security for the APIs provided by Unica products.

- For a specific product API, you can block access to the product.
- For a specific product API, you can require HTTPS for communication between the specified API and the product.
- For a specific product API, you can require authentication for communication between the specified API and the product.

The configuration properties that control API security are located under the **Unica Platform | Security | API management** category. Each product has a configuration property template that you can use to create new security settings for the APIs provided by that product.

You can set and change the security settings for an API as appropriate for unit testing or deployment or during the overall lifecycle of APIs.

The security framework currently supports APIs for Unica Campaign only.

The Unica Platform security framework supports the following two authentication options for accessing protected APIs. You can use either one, depending on your environment.

- Internal users who are registered with Unica Platform can be authenticated using their Unica Platform login credentials to obtain a secure token.
- External users who are part of a federation that Unica Platform is set up to use can be authenticated through the Identity Provider server.

Internal user authentication with the Unica Platform login API

To authenticate internal users in client applications, use the Unica Platform `login` API to generate secure tokens. You can then invoke any protected APIs by passing the required parameters in the request header, in addition to the parameters expected by the API itself.

The security filter intercepts these protected requests, validates them, and then passes them through for processing.

After the Unica Platform user is authenticated, the Unica Platform security filter adds the user's login name to the request as an attribute of the `USER_NAME_STRING` key before passing it to the product for processing.

The secure tokens have a default life span of 15 seconds. After the life span of the token expires, it cannot be used to invoke a protected API. Each time the Unica Platform `login` API is invoked for a user, all previous security tokens for that user are invalidated.

You can change the life span of secure tokens by setting the value of the **Token lifetime** property located on the **Settings > Configuration** page under the **General | Miscellaneous** category.

Example URL

```
http[s]://host:port/unica/api/manager/authentication/login/
```

Header parameters

Table 119. Header parameters for the login API with internal users

Parameter	Description
<code>m_user_name</code>	The internal user's Unica Platform login name.
<code>m_user_password</code>	The internal user's Unica Platform password in plain text.

Response

When login succeeds, the response is HTTP 200 with the following JSON data.

- `m_tokenId` - randomly generated token
- `m_user_name` - user name of the logged in user
- `createDate` - timestamp in the format that is shown in the following example, where the time zone is IST:

```
Mon Jul 06 18:23:35 IST 2015
```

When login fails with bad credentials, the response is HTTP 401 (unauthorized). When the `login` API is configured to be blocked, the response is 403 (forbidden). When the `login` API is configured to use HTTPS and if it is invoked on HTTP, the response is 403 (forbidden).

To log out internal users, use the Unica Platform `logout` API.

Internal user logout with the Unica Platform logout API

Use the Unica Platform `logout` API to log out internal users and delete the secure token.

The `logout` API is protected by default. The authentication parameters are expected in the request header against pre-defined keys.

Example URL

`http[s]://host:port/unica/api/manager/authentication/logout/`

Header parameters

Table 120. Header parameters for the logout API

Parameter	Description
<code>m_user_name</code>	The internal user's Unica Platform login name.
<code>m_tokenId</code>	The secure token obtained through authentication.
<code>api_auth_mode</code>	Use the value <code>manager</code> for internal users.

Response

When authentication succeeds, the response is `HTTP 200`, and the secure token is deleted. If the response is `HTTP 200`, the client application should confirm the logout.

When authentication fails, the response is `HTTP 401`.

External user authentication and logout through a federation

When Unica Platform is integrated with a supported federation, users can log in to their own system, and the client application gets a token through the Identity Provider (IdP) server provided by Unica Platform.

After a federated user is authenticated, their corresponding Unica Platform login name is added to the request as an attribute of the `USER_NAME_STRING` key.

Log out should be done at the IdP server.

Header parameters

The following table describes the header parameters to use when authenticating through the IdP server provided by Unica Platform.

Table 121. Header parameters with a federation

Parameter	Description
f_userId	User ID in the federation.
f_clientId	Client ID in the federation.
f_spId	Service provider ID in the federation.
f_tokenId	Single sign-on token from the IdP server.
api_auth_mode	Use the value <code>f_sso</code> for federated authentication.

Response

The response is `HTTP 200`, with additional items depending on the API.

SAML 2.0 based federated authentication

Unica Platform implements a SAML 2.0 based Identity Provider (IdP) that enables a single sign-on federation among Unica products or between Unica products and third party applications.

A federation is a group of IdPs and applications that works together in a trusted environment and provides services to each other using SAML 2.0 (Security Assertion Markup Language) based standards.

Applications that are members of a federation are called Service Providers (SPs). The IdP server and the SPs can be hosted on premises or on cloud.


A SAML 2.0 federation supports a variety of authentication mechanisms for single sign-on. For example, a user can be authenticated in an SP using that application's authentication mechanism (for example, in-house, OAuth, OpenId, SAML, Kerberos), and then the user can access other SPs using federated single sign-on, provided the applications are part of same federation and the user is mapped appropriately.

The IdP server creates, validates, or deletes tokens based on user mappings. Data access objects are implemented for the supported database types, and are included in the IdP server.

An administrator maps user IDs between SPs to provide single sign-on access to mapped users. For example, suppose SP_A and SP_B are both members of a federation. User1 is an account in SP_A, and User2 is an account in SP_B. The User1 account is mapped to the User2 account in the federation. When a user logs in to SP_A with User1 credentials, that user has single sign-on access to SP_B. Also, when a user logs in to SP_B with User2 credentials, that user has single sign-on access to SP_A.

Diagram

The following diagram illustrates the federation.



Components of the HCL implementation

The implementation of SAML 2.0 based federated single sign-on consists of the following components.

These components are located in the `tools/lib` directory under your Unica Platform installation.

- A SAML 2.0 based IdP server, delivered as a WAR file: `idp-server.war`
- A client façade: `idp-client.jar`

The IdP client facade is Java™ implementation with an API that works with security tokens. It is delivered as a JAR file. Javadoc™ documentation for the API is included with the Unica Platform Javadoc™.

The IdP client facade enables Java™ SPs to quickly integrate with the IdP server and become part of the federation.

Supported use cases

The current implementation enables SPs to work with security tokens to establish single sign-on authentication among the SPs.

Generating a new SAML token

The implementation can generate a new SAML token for a user who initiates a single sign-on authentication request. This user must be mapped on the IdP server. Based on the trusted party's credentials and user mapping, the IdP server creates a new security token and issues it using a SAML 2.0 assertion.

For example, if User1 from SP_A is mapped with User2 from SP_B on the IdP server, and User1 tries to access SP_B resources, the IdP server generates a security token for User1 as a trusted party.

Validating an existing SAML token

The implementation can validate an existing SAML token presented by an SP that receives the access request from a user from another SP. The SP first validates the security token and client mapping with the IdP server to identify the mapped user in its own domain.

For example, when SP_A tries to access SP_B resources on behalf of User1 and presents the IdP security token, SP_B takes this token to the IdP server. If the token is valid and User1 is mapped to an SP_B user, the IdP server resolves the SP_B user in the SP_B domain and returns the assertion.

Deleting an existing SAML token

The implementation can delete an existing SAML token for an SP user when a user logs out from the system or the session times out due to inactivity. Based on the trusted party's credentials and user mapping, the IdP server deletes the token and resets the last accessed timestamp when it receives the logout request. This does NOT delete the user's mapping.

Limitations

The current implementation does not support the following use cases.

- Creating a new user mapping between SP users via a user interface or API
- Updating an existing user mapping between SP users via a user interface or API
- Deleting an existing user mapping between SP users via a user interface or API

Federated authentication and partitions

If your Unica environment has multiple partitions, you can set up separate SAML 2.0 based federated authentication per partition. To implement this, on the **Settings > Configuration** page, you must create a new set of properties in the **Unica Platform | Security | Federated Authentication | partitions | partition[n]** category for each partition.

Configuring which audit events appear in the report

To specify the audit events that are available in the audit report and their severity, you set properties on the **Settings > Configuration** page.

1. Go to the **Settings > Configuration** page and expand the **Unica Platform | Audit Events | Audit Events Configuration** category.
2. Select the events that you want to track.

The tracked events are available for inclusion in the audit report.

3. Expand the **Unica Platform | Audit Events | Audit events severity configuration** category and click **Edit settings**.
4. Specify the severity level that you want to assign to each of the tracked events.

Select from the following options.

- No severity
- Informational
- Warning
- Critical

The specified severity appears in the audit report, and can be used in filtering the report.

If you want to track the user session event **Record login and logout events for members of the HighSeverityAccounts group**, add the users whose login and logout events you want to track to the **highSeverityAccounts** group. You do this on the **Settings > User groups** page.

This group is created automatically in the default partition during installation. In a multi-partition environment, this group is created automatically when you create a new partition using the Unica Platform `partitionTool` utility.

Platform | Audit Events

The property on this page determines whether audit events are tracked.

Is event auditing enabled?

Description

Specifies whether the audit events are tracked.

Default value

False

Valid values

True | False

Platform | Audit Events | Audit events configuration

The events you select on this page are available in the security audit reports.

Record login and logout events for all accounts

Description

Specifies whether to track the user name and the date and time for log in and log out events for all user accounts.

Record when user sessions time out for all accounts

Description

Specifies whether to track the account user name and the date and time of sessions that are automatically timed out.

Record login and logout events for members of the HighSeverityAccounts group

Description

Specifies whether to track the user name and the date and time for log in and log out events for accounts that are members of the **highSeverityAccounts** group in Unica Platform. To enable this feature, you must set a severity level for this configuration property and add users to the highSeverityAccounts group.

Record LDAP group membership changes

Description

Specifies whether to record the addition or deletion of accounts, along with the user names and dates and times of these actions, for user accounts synchronized from an LDAP server. This property applies only when Unica Platform is integrated with a supported LDAP server, such IBM Security Directory server or Windows™ Active Directory.

Record when accounts are enabled and disabled

Description

Specifies whether to record the account user name and the date and time when user accounts are enabled or disabled.

Record when account passwords change

Description

Specifies whether to record the account user name and the date and time when user passwords change.

Record when account passwords are locked

Description

Specifies whether to record the account user name and the date and time when a password is locked out due to too many incorrect login attempts.

Record when groups are created or deleted in Platform

Description

Specifies whether to record when groups are added or deleted.

Record Platform group membership changes

Description

Specifies whether to record when user accounts are added to or removed from a group.

Record Platform group permission changes

Description

Specifies whether to record changes to group permissions.

Record role creation or deletion

Description

Specifies whether to record when roles are added or deleted. Only roles that are shown on the **Settings > User roles and permissions** page are tracked.

Record role membership changes

Description

Specifies whether to record changes in role membership. Only roles that are shown on the **Settings > User roles and permissions** page are tracked.

Record role permission changes

Description

Specifies whether to record changes in role permissions. Only roles that are shown on the **Settings > User roles and permissions** page are tracked.

Record changes to properties on the configuration page

Description

Specifies whether to record changes in configuration properties on the **Settings > Configuration** page. Changes made by users on the Configuration page, or by users running the `configTool` are tracked. Configuration changes made by the installers during installation or upgrade are not tracked.

Enable audit backup

Description

Specifies whether to save audit data to the `USM_AUDIT_BACKUP` table.



Important: Because this is a bootstrap property that is read when the Unica Platform web application starts, you must stop and restart the Unica Platform web application when you change this property value.

Default value

False

Valid values

True | False

Archive data after the number of days specified here

Description

Specifies the interval, in days, between audit backups. The archived data is stored in the `USM_AUDIT_BACKUP` table and can be included in the Audit Events report when you set a custom date range that includes data from the archive.

 **Important:** Because this is a bootstrap property that is read when the Unica Platform web application starts, you must stop and restart the Unica Platform web application when you change this property value.

Keep Audit records in primary for number days specified here

Description

Specifies how many days of data to keep in the `USM_AUDIT` table for the Audit Events report. When the default settings for the Audit Events report are in effect, only the data in the `USM_AUDIT` table is shown in the report.

 **Important:** Because this is a bootstrap property that is read when the Unica Platform web application starts, you must stop and restart the Unica Platform web application when you change this property value.

Archive start time

Description

Specifies the time of day when the system moves audit data into an archive. Use the 24 hour format for this value.

 **Important:** Because this is a bootstrap property that is read when the Unica Platform web application starts, you must stop and restart the Unica Platform web application when you change this property value.

Name of group to receive audit backup notifications

Description

Specifies the Unica group whose members should receive notification of archive backups. You can specify only one group for this property. Users in this group can manage their subscription to this notification by going to their **Settings > Users** page and clicking **Notification subscriptions**.

Platform | Audit Events | Audit events severity configuration

The severity level you specify for each event on this page appears in the Audit Events report. You can use the severity level to sort and filter the report data. The events are identical to those in the **Platform | Audit Events | Audit events configuration** category.

Archived audit events

You can configure backups of audit events by setting the value of configuration properties in the **Unica Platform | Audit Events | Audit Events Configuration** category on the **Settings > Configuration** page.

The archived data is stored in the `USM_AUDIT_BACKUP` table and can be included in the Audit Events report when you set a custom date range that includes data from the archive. Loading a report that includes archived data can take longer than loading a report that does not include archived data.

The system posts a notification when an audit backup process completes. You can also configure a group of users who receive these notifications in emails.

Set the following properties to configure audit event backups.

- **Enable Audit Backup**
- **Archive data after the number of days specified here**
- **Keep Audit records in primary for number days specified here**
- **Archive start time**
- **Name of group to receive audit backup notifications**

Platform | Audit Events | Audit events configuration

The events you select on this page are available in the security audit reports.

Record login and logout events for all accounts

Description

Specifies whether to track the user name and the date and time for log in and log out events for all user accounts.

Record when user sessions time out for all accounts

Description

Specifies whether to track the account user name and the date and time of sessions that are automatically timed out.

Record login and logout events for members of the HighSeverityAccounts group

Description

Specifies whether to track the user name and the date and time for log in and log out events for accounts that are members of the **highSeverityAccounts** group in Unica Platform. To enable this feature, you must set a severity level for this configuration property and add users to the highSeverityAccounts group.

Record LDAP group membership changes

Description

Specifies whether to record the addition or deletion of accounts, along with the user names and dates and times of these actions, for user accounts synchronized from an LDAP server. This property applies only when Unica Platform is integrated with a supported LDAP server, such IBM Security Directory server or Windows™ Active Directory.

Record when accounts are enabled and disabled

Description

Specifies whether to record the account user name and the date and time when user accounts are enabled or disabled.

Record when account passwords change

Description

Specifies whether to record the account user name and the date and time when user passwords change.

Record when account passwords are locked

Description

Specifies whether to record the account user name and the date and time when a password is locked out due to too many incorrect login attempts.

Record when groups are created or deleted in Platform

Description

Specifies whether to record when groups are added or deleted.

Record Platform group membership changes

Description

Specifies whether to record when user accounts are added to or removed from a group.

Record Platform group permission changes

Description

Specifies whether to record changes to group permissions.

Record role creation or deletion

Description

Specifies whether to record when roles are added or deleted. Only roles that are shown on the **Settings > User roles and permissions** page are tracked.

Record role membership changes

Description

Specifies whether to record changes in role membership. Only roles that are shown on the **Settings > User roles and permissions** page are tracked.

Record role permission changes

Description

Specifies whether to record changes in role permissions. Only roles that are shown on the **Settings > User roles and permissions** page are tracked.

Record changes to properties on the configuration page

Description

Specifies whether to record changes in configuration properties on the **Settings > Configuration** page. Changes made by users on the Configuration page, or by users running the `configTool` are tracked. Configuration changes made by the installers during installation or upgrade are not tracked.

Enable audit backup

Description

Specifies whether to save audit data to the `USM_AUDIT_BACKUP` table.



Important: Because this is a bootstrap property that is read when the Unica Platform web application starts, you must stop and restart the Unica Platform web application when you change this property value.

Default value

False

Valid values

True | False

Archive data after the number of days specified here

Description

Specifies the interval, in days, between audit backups. The archived data is stored in the `USM_AUDIT_BACKUP` table and can be included in the Audit Events report when you set a custom date range that includes data from the archive.



Important: Because this is a bootstrap property that is read when the Unica Platform web application starts, you must stop and restart the Unica Platform web application when you change this property value.

Keep Audit records in primary for number days specified here

Description

Specifies how many days of data to keep in the `USM_AUDIT` table for the Audit Events report. When the default settings for the Audit Events report are in effect, only the data in the `USM_AUDIT` table is shown in the report.



Important: Because this is a bootstrap property that is read when the Unica Platform web application starts, you must stop and restart the Unica Platform web application when you change this property value.

Archive start time

Description

Specifies the time of day when the system moves audit data into an archive. Use the 24 hour format for this value.



Important: Because this is a bootstrap property that is read when the Unica Platform web application starts, you must stop and restart the Unica Platform web application when you change this property value.

Name of group to receive audit backup notifications

Description

Specifies the Unica group whose members should receive notification of archive backups. You can specify only one group for this property. Users in this group can manage their subscription to this notification by going to their **Settings > Users** page and clicking **Notification subscriptions**.

Configuring audit backup notifications

To notify users of the status of audit event backup, make them members of a group that you specify in a configuration property.

1. Determine the group whose members you want to receive email notifications of audit data backups.

You can use an existing group or create a new one on the **Settings > User groups** page.

You can specify only a single group to receive notifications.

2. Go to the **Settings > Configuration** page and expand the **Unica Platform | Audit Events | Audit events configuration** category.
3. Set the value of the **Name of group to receive audit backup notifications** property to the name of the group you selected.
4. Add the users who should receive notifications to the group.
5. The users who you have added to the group must subscribe to the notifications on the **Settings > Users** page.

An administrator can do this for each user, or you can inform the users that they must go to their account, click **Notification subscriptions**, and subscribe to **Audit backup** notifications.

Each time the system backs up audit data, an email notification and user interface notification is generated for the members of the group you specified, if they have subscribed to Audit Event notifications.

Configuring which audit events appear in the report

To specify the audit events that are available in the audit report and their severity, you set properties on the **Settings > Configuration** page.

1. Go to the **Settings > Configuration** page and expand the **Unica Platform | Audit Events | Audit Events Configuration** category.
2. Select the events that you want to track.

The tracked events are available for inclusion in the audit report.

3. Expand the **Unica Platform | Audit Events | Audit events severity configuration** category and click **Edit settings**.
4. Specify the severity level that you want to assign to each of the tracked events.

Select from the following options.

- No severity
- Informational
- Warning
- Critical

The specified severity appears in the audit report, and can be used in filtering the report.

If you want to track the user session event **Record login and logout events for members of the HighSeverityAccounts group**, add the users whose login and logout events you want to track to the **highSeverityAccounts** group. You do this on the **Settings > User groups** page.

This group is created automatically in the default partition during installation. In a multi-partition environment, this group is created automatically when you create a new partition using the Unica Platform `partitionTool` utility.

Modifying the audit report content and display

You can add and remove events and columns, rearrange and sort the columns, set the time span, specify which tracked events are shown in the report, and filter the information.

When you open the audit report without setting any report parameters, the following default settings are used.

- All of the events selected on the **Settings > Configuration** page under the **Unica Platform | Audit Events | Audit Events Configuration** category are shown, on multiple pages if necessary.
- No date criteria are applied.
- Events are sorted as follows: Event Date/Time (Descending), Login Name(Ascending), Severity Level (Ascending)

Use this procedure to modify these settings.

1. Go to **Analytics > Platform**.
2. To change the content of the report, do the following.
 - a. Click the **Report Parameters** button.

The Report Parameters window opens.
 - b. Complete the fields.

To set the sort order in the report, you can select from pre-defined sort orders in this window. You can also click the column headers in the report to sort on those columns.
 - c. Click **Next** to move to a page where you can select which events are shown in the report.
 - d. Click **Save and Close** to apply your selections to the report.
3. To filter the report, enter text or numbers in the **Filter** field and click the **Filter** button.

The report displays only those events that contain the filter characters in any of the columns displayed in the report.

To clear the filter, click the **X** in the Filter field.

Fields in the Report Parameters window

Use the fields on the Report Parameters page to configure the way the audit report is displayed.

Table 122. Fields in the Report Parameters window

Field	Description
Sort	Select a sort order from the drop-down menu. Various combinations of column sorting are listed, along with whether the sort is in descending or ascending order. You can also sort columns using controls on the report page.
Time Period	Select from pre-defined time periods in the drop-down list, or enter start and end dates for a custom range.
Events	Select the optional events that you want to include in the report. For an event to be available in the report, it must be selected in the Unica Platform Audit Events Audit Events Configuration category on the Settings > Configuration page.
Columns	Use the Add and Remove buttons to specify the optional columns you want to appear in the report.

configTool

The properties and values on the **Configuration** page are stored in the Unica Platform system tables. You can use the `configTool` utility to import and export configuration settings to and from the system tables.

When to use configTool

You might want to use `configTool` for the following reasons.

- To import partition and data source templates that are supplied with Unica Campaign, which you can then modify and duplicate by using the **Configuration** page.
- To register (import configuration properties for) Unica products, if the product installer is unable to add the properties to the database automatically.
- To export an XML version of configuration settings for backup or to import into a different installation of Unica.
- To delete categories that do not have the **Delete Category** link. You do this by using `configTool` to export your configuration, then manually deleting the XML that creates the category, and by using `configTool` to import the edited XML.



Important: This utility modifies the `usm_configuration` and `usm_configuration_values` tables in the Unica Platform system table database, which contains the configuration properties and their values. For best results, either create backup copies of these tables, or export your existing configurations by using `configTool` and back up the resulting file so you have a way to restore your configuration if you make an error when you use `configTool` to import.

Syntax

```
configTool -d -p "elementPath" [-o]
```

```
configTool -i -p "parent ElementPath" -f importFile [-o]
```

```
configTool -x -p "elementPath" -f exportFile
```

```
configTool -vp -p "elementPath" -f importFile [-d]
```

```
configTool -r productName -f registrationFile [-o] configTool -u productName
```

Commands

```
-d -p "elementPath" [o]
```

Delete configuration properties and their settings, specifying a path in the configuration property hierarchy.

The element path must use the internal names of categories and properties. You can obtain them by going to the **Configuration** page, selecting the wanted category or property, and

looking at the path that is displayed in parentheses in the right pane. Delimit a path in the configuration property hierarchy by using the | character, and surround the path with double quotation marks.

Note the following.

- Only categories and properties within an application can be deleted by using this command, not whole applications. Use the `-u` command to unregister a whole application.
- To delete categories that do not have the **Delete Category** link on the **Configuration** page, use the `-o` option.

When you use `-d` with the `-vp` command, the configTool deletes any child nodes in the path you specify if those nodes are not included in the XML file you specify.

```
-i -p "parentElementPath" -f importFile [o]
```

Import configuration properties and their settings from a specified XML file.

To import, you specify a path to the parent element under which you want to import your categories. The `configTool` utility imports properties under the category you specify in the path.

You can add categories at any level below the top level, but you cannot add a category at same level as the top category.

The parent element path must use the internal names of categories and properties. You can obtain them by going to the **Configuration** page, selecting the required category or property, and looking at the path that is displayed in parentheses in the right pane. Delimit a path in the configuration property hierarchy by using the | character, and surround the path with double quotation marks.

You can specify an import file location relative to the `tools/bin` directory or you can specify a full directory path. If you specify a relative path or no path, `configTool` first looks for the file relative to the `tools/bin` directory.

By default, this command does not overwrite an existing category, but you can use the `-o` option to force an overwrite.

```
-x -p "elementPath" -f exportFile
```

Export configuration properties and their settings to an XML file with a specified name.

You can export all configuration properties or limit the export to a specific category by specifying a path in the configuration property hierarchy.

The element path must use the internal names of categories and properties, which you can obtain by going to the **Configuration** page, selecting the wanted category or property, and looking at the path that is displayed in parentheses in the right pane. Delimit a path in the configuration property hierarchy by using the | character, and surround the path with double quotation marks.

You can specify an export file location relative to the current directory or you can specify a full directory path. If the file specification does not contain a separator (/ on UNIX™, / or \ on Windows™), `configTool` writes the file to the `tools/bin` directory under your Unica Platform installation. If you do not provide the `xml` extension, `configTool` adds it.

```
-vp -p "elementPath" -f importFile [-d]
```

This command is used mainly in manual upgrades, to import configuration properties. If you applied a fix pack that contains a new configuration property, and you then upgrade, importing a configuration file as part of a manual upgrade process can override values that were set when the fix pack was applied. The `-vp` command ensures that the import does not override previously set configuration values.



Important: After you use the `configTool` utility with the `-vp` option, you must restart the web application server on which Unica Platform is deployed so the changes are applied.

When you use `-d` with the `-vp` command, the `configTool` deletes any child nodes in the path you specify if those nodes are not included in the XML file you specify.

```
-r productName -f registrationFile
```

Register the application. The registration file location can be relative to the `tools/bin` directory or can be a full path. By default, this command does not overwrite an existing

configuration, but you can use the `-o` option to force an overwrite. The `productName` parameter must be one of those names that are listed above.

Note the following.

- When you use the `-r` command, the registration file must have `<application>` as the first tag in the XML.

Other files can be provided with your product that you can use to insert configuration properties into the Unica Platform database. For these files, use the `-i` command. Only the file that has the `<application>` tag as the first tag can be used with the `-r` command.

- The registration file for the Unica Platform is named `Manager_config.xml`, and the first tag is `<Suite>`. To register this file on a new installation, use the `populateDb` utility, or rerun the Unica Platform installer as described in the *Unica Platform Installation Guide*.
- After the initial installation, to re-register products other than the Unica Platform, use `configTool` with the `-r` command and `-o` to overwrite the existing properties.

The `configTool` utility uses product names as parameters with the commands that register and unregister products. With the 8.5.0 release of Unica, many product names changed. However, the names that are recognized by `configTool` did not change. The valid product names for use with `configTool` are listed below, along with the current names of the products.

Table 123. Product names for configTool registration and unregistration

Product name	Name used in configTool
Unica Platform	Manager
Unica Campaign	Campaign
Unica Collaborate	Collaborate
IBM eMessage	emessage

Table 123. Product names for configTool registration and unregistration (continued)

Product name	Name used in configTool
Unica Interact	interact
Unica Optimize	Optimize
Unica Plan	Plan
Opportunity Detect	Detect
IBM SPSS Modeler Advantage Enterprise Marketing Management Edition	SPSS
Digital Analytics	Coremetrics

-u *productName*

Unregister an application that is specified by *productName*. You do not have to include a path to the product category; the product name is sufficient, and it is required. The process removes all properties and configuration settings for the product.

Options

-o

When used with **-i** or **-r**, it overwrites an existing category or product registration (node).

When used with **-d**, you can delete a category (node) that does not have the **Delete Category** link on the **Configuration** page.

Examples

- Import configuration settings from a file named `Product_config.xml` in the `conf` directory under the Unica Platform installation.

```
configTool -i -p "Affinium" -f Product_config.xml
```

- Import one of the supplied Unica Campaign data source templates into the default Unica Campaign partition, `partition1`. The example assumes that you placed the

Oracle data source template, `OracleTemplate.xml`, in the `tools/bin` directory under the Unica Platform installation.

```
configTool -i -p "Affinium|Campaign|partitions|partition1|dataSources" -f
OracleTemplate.xml
```

- Export all configuration settings to a file named `myConfig.xml` in the `D:\backups` directory.

```
configTool -x -f D:\backups\myConfig.xml
```

- Export an existing Unica Campaign partition (complete with data source entries), save it to a file named `partitionTemplate.xml`, and store it in the default `tools/bin` directory under the Unica Platform installation.

```
configTool -x -p "Affinium|Campaign|partitions|partition1" -f
partitionTemplate.xml
```

- Manually register an application named `productName`, by using a file named `app_config.xml` in the default `tools/bin` directory under the Unica Platform installation, and force it to overwrite an existing registration of this application.

```
configTool -r product Name -f app_config.xml -o
```

- Unregister an application named `productName`.

```
configTool -u productName
```

- Run the following command to enable `encodeCSV` feature:

```
configTool -vp -p "Affinium|Plan|umoConfiguration" -f Plan_Home\conf
\Plan_encodeProperty_12.0.xml
```

- Register Unica Interact Settings as configuration menu under `AffiniumWebApps\Campaign\interact\conf\interact_setup_navigation.xml` using

```
configTool.bat -v -i -p "Affinium|suite|uiNavigation|settingsMenu" -f
"interact_setup_navigation.xml"
```

Configuration management

The Configuration page provides access to the central configuration properties for Unica applications.

Users with Admin privileges in the Unica Platform can use the Configuration page to do the following.

- Browse configuration properties, which are organized by product into a hierarchy of categories and sub-categories.
- Edit the values of configuration properties.
- Delete some categories (categories that you can delete display a **Delete Category** link on the Settings page).

You can make additional changes on the Configuration page using the configTool utility provided with Unica Platform.

Unica Platform utilities

This section provides an overview of the Unica Platform utilities, including some details that apply to all of the utilities and which are not included in the individual utility descriptions.

Location of utilities

Unica Platform utilities are located in the `tools/bin` directory under your Unica Platform installation.

List and descriptions of utilities

The Unica Platform provides the following utilities.

- [alertConfigTool \(on page 312\)](#) - registers alerts and configurations for Unica products
- [configTool \(on page 313\)](#) - imports, exports, and deletes configuration settings, including product registrations
- [datafilteringScriptTool \(on page 319\)](#) - creates data filters
- [encryptPasswords \(on page 321\)](#) - encrypts and stores passwords
- [encryptTomcatDBPasswords \(on page 322\)](#) - encrypt the database passwords that the Tomcat Application server uses internally
- [partitionTool \(on page 323\)](#) - creates database entries for partitions

- `populateDb` (on page 327) - populates the Unica Platform database
- `restoreAccess` (on page 327) - restores a user with the `platformAdminRole` role
- `scheduler_console_client` (on page 330) - lists or starts Unica Scheduler jobs that are configured to listen for a trigger.
- `quartzjobtool` (on page) - Update scheduler jobs created in version 11.1 and older versions
- `BIRTdbutil` - Installer places report design files which possesses database connection tokens. You must update them for your system database. You must run `BIRTdbutil.sh/bat` utility to update the same. See the BIRT Installation and Configuration Guide for more details.

Prerequisites for running Unica Platform utilities

The following are prerequisites for running all Unica Platform utilities.

- Run all utilities from the directory where they are located (by default, the `tools/bin` directory under your Unica Platform installation).
- On UNIX™, the best practice is to run the utilities with the same user account that runs the application server on which Unica Platform is deployed. If you run a utility with a different user account, adjust the permissions on the `platform.log` file to allow that user account to write to it. If you do not adjust permissions, the utility is not able to write to the log file and you might see some error messages, although the tool should still function correctly.

Authentication of utilities

Utilities such as `configTool` and other Unica back end utilities are designed to be used by system administrators and require physical access to the host servers for them to be invoked. For this reason, authentication for these utilities has been designed to be independent of the UI authentication mechanism. Access to these utilities is available to users with Unica Platform administrator privileges. Access to these utilities is expected to be locally defined in Unica Platform and authenticated against the same.

Troubleshooting connection issues

All of the Unica Platform utilities except `encryptPasswords` interact with the Unica Platform system tables. To connect to the system table database, these utilities use the following connection information, which is set by the installer using information provided when the Unica Platform was installed. This information is stored in the `jdbc.properties` file, located in the `tools/bin` directory under your Unica Platform installation.

- JDBC driver name
- JDBC connection URL (which includes the host, port, and database name)
- Data source login
- Data source password (encrypted)

In addition, these utilities rely on the `JAVA_HOME` environment variable, set either in the `setenv` script located in the `tools/bin` directory of your Unica Platform installation, or on the command line. The Unica Platform installer should have set this variable automatically in the `setenv` script, but it is a good practice to verify that the `JAVA_HOME` variable is set if you have a problem running a utility. The JDK must be the Sun version (not, for example, the JRockit JDK available with WebLogic).

Special characters

Characters that are designated as reserved characters in the operating system must be escaped. Consult your operating system documentation for a list of reserved characters and how to escape them.

Standard options in Unica Platform utilities

The following options are available in all Unica Platform utilities.

`-l logLevel`

Set the level of log information displayed in the console. Options are `high`, `medium`, and `low`. The default is `low`.

`-L`

Set the locale for console messages. The default locale is en_US. The available option values are determined by the languages into which the Unica Platform has been translated. Specify the locale using the ICU locale ID according to ISO 639-1 and ISO 3166.

-h

Display a brief usage message in the console.

-m

Display the manual page for this utility in the console.

-v

Display more execution details in the console.

encryptPasswords

The `encryptPasswords` utility is used to encrypt and store either of two passwords that Unica Platform uses internally.

The two passwords that the utility can encrypt are as follows.

- The password that the Unica Platform uses to access its system tables. The utility replaces an existing encrypted password (stored in the `jdbc.properties` file, located in the `tools\bin` directory under your Unica Platform installation) with a new one.
- The keystore password used by the Unica Platform when it is configured to use SSL with a certificate other than the default one supplied with the Unica Platform or the web application server. The certificate can be either a self-signed certificate or a certificate from a certificate authority.

When to use encryptPasswords

Use `encryptPasswords` as for the following reasons.

- When you change the password of the account used to access your Unica Platform system table database.
- When you have created a self-signed certificate or have obtained one from a certificate authority.

Prerequisites

- Before running `encryptPasswords` to encrypt and store a new database password, make a backup copy of the `jdbc.properties` file, located in the `tools/bin` directory under your Unica Platform installation.
- Before running `encryptPasswords` to encrypt and store the keystore password, you must have created or obtained a digital certificate and know the keystore password.

Syntax

```
encryptPasswords -d databasePassword
```

```
encryptPasswords -k keystorePassword
```

Commands

-d *databasePassword*

Encrypt the database password.

-k *keystorePassword*

Encrypt the keystore password and store it in a file named `pfile`.

Examples

- When the Unica Platform was installed, the login for the system table database account was set to `myLogin`. Now, some time after installation, you have changed the password for this account to `newPassword`. Run `encryptPasswords` as follows to encrypt and store the database password.

```
encryptPasswords -d newPassword
```

- You are configuring an Unica application to use SSL and have created or obtained a digital certificate. Run `encryptPasswords` as follows to encrypt and store the keystore password.

```
encryptPasswords -k myPassword
```

partitionTool

Partitions are associated with Unica Campaign policies and roles. These policies and roles and their partition associations are stored in the Unica Platform system tables. The `partitionTool` utility seeds the Unica Platform system tables with basic policy and role information for partitions.

When to use partitionTool

For each partition you create, you must use `partitionTool` to seed the Unica Platform system tables with basic policy and role information.

See the installation guide appropriate for your version of Unica Campaign for detailed instructions on setting up multiple partitions in Unica Campaign.

Special characters and spaces

Any partition description or user, group, or partition name that contains spaces must be enclosed in double quotation marks.

Syntax

```
partitionTool -c -s sourcePartition -n newPartitionName [-u admin_user_name]  
[-d partitionDescription] [-g groupName]
```

Commands

The following commands are available in the `partitionTool` utility.

-c

Replicates (clones) the policies and roles for an existing partition specified using the `-s` option, and uses the name specified using the `-n` option. Both of these options are required with `c`. This command does the following.

- Creates a new Unica user with the Admin role in both the Administrative Roles policy and the global policy in Unica Campaign. The partition name you specify is automatically set as this user's password.
- Creates a new Unica Platform group and makes the new Admin user a member of that group.
- Creates a new partition object.
- Replicates all the policies associated with the source partition and associates them with the new partition.
- For each replicated policy, replicates all roles associated with the policy.
- For each replicated role, maps all functions in the same way that they were mapped in the source role.
- Assigns the new Unica Platform group to the last system-defined Admin role created during role replication. If you are cloning the default partition, `partition1`, this role is the default Administrative Role (Admin).

Options

`-d partitionDescription`

Optional, used with `-c` only. Specifies a description that appears in the output from the `-list` command. Must be 256 characters or less. Enclose in double quotation marks if the description contains spaces.

`-g groupName`

Optional, used with `-c` only. Specifies the name of the Unica Platform Admin group that the utility creates. The name must be unique within this instance of Unica Platform

If not defined, the name defaults to `partition_nameAdminGroup`.

`-n partitionName`

Optional with `-list`, required with `-c`. Must be 32 characters or less.

When used with `-list`, specifies the partition whose information is listed.

When used with `-c`, specifies the name of the new partition, and the partition name you specify is used as the password for the Admin user. The partition name must match the name you gave the partition in when you configured it (using the partition template on the Configuration page).

`-s sourcePartition`

Required, used with `-c` only. The name of the source partition to be replicated.

`-u adminUserName`

Optional, used with `-c` only. Specifies the user name of the Admin user for the replicated partition. The name must be unique within this instance of Unica Platform.

If not defined, the name defaults to `partitionNameAdminUser`.

The partition name is automatically set as this user's password.

Examples

- Create a partition with the following characteristics.

- Cloned from partition1
- Partition name is `myPartition`
- Uses the default user name (`myPartitionAdminUser`) and password (`myPartition`)
- Uses the default group name (`myPartitionAdminGroup`)
- Description is "ClonedFromPartition1"

```
partitionTool -c -s partition1 -n myPartition -d "ClonedFromPartition1"
```

- Create a partition with the following characteristics.

- Cloned from partition1
- Partition name is `partition2`
- Specifies user name of `customerA` with the automatically assigned password of `partition2`

- Specifies group name of `customerAGroup`
- Description is "PartitionForCustomerAGroup"

```
partitionTool -c -s partition1 -n partition2 -u customerA -g
customerAGroup -d "PartitionForCustomerAGroup"
```

ManagerSchema_DeleteAll.sql

The `Manager_Schema_DeleteAll.sql` script removes all data from the Unica Platform system tables without removing the tables themselves. This script removes all users, groups, security credentials, data filters, and configuration settings from Unica Platform.

When to use ManagerSchema_DeleteAll.sql

You might want to use `ManagerSchema_DeleteAll.sql` if corrupted data prevents you from using an instance of Unica Platform.

Additional requirements

To make Unica Platform operational after running `ManagerSchema_DeleteAll.sql`, you must perform the following steps.

- Run the `populateDB` utility. The `populateDB` utility restores the default configuration properties, users, roles, and groups, but does not restore any users, roles, and groups you have created or imported after initial installation.
- Use the `configTool` utility with the `config_navigation.xml` file to import menu items.
- If you have performed any post-installation configuration, such as creating data filters or integrating with an LDAP server or web access control platform, you must perform these configurations again.
- If you want to restore previously existing data filters, run the `datafilteringScriptTool` utility using the XML originally created to specify the data filters.

SQL scripts for creating system tables

Use the scripts described in the following table to create Unica Platform system tables manually, when your company policy does not allow you to use the installer to create them automatically.

The scripts are shown in the order in which you must run them.

Table 124. Scripts for creating system tables

Datasource Type	Script Names
IBM® DB2®	<ul style="list-style-type: none"> • <code>ManagerSchema_DB2.sql</code> <p>If you plan to support multi-byte characters (for example, Chinese, Japanese, or Korean), use the <code>ManagerSchema_DB2_unicode.sql</code> script.</p> <ul style="list-style-type: none"> • <code>ManagerSchema__DB2_CeateFKConstraints.sql</code> • <code>active_portlets.sql</code>
Microsoft™ SQL Server	<ul style="list-style-type: none"> • <code>ManagerSchema_SqlServer.sql</code> • <code>ManagerSchema__SqlServer_CeateFKConstraints.sql</code> • <code>active_portlets.sql</code>
Informix	<ul style="list-style-type: none"> • <code>ManagerSchema_informix</code> • <code>ManagerSchema_informix_CreateFKConstraints</code> • <code>quartz_informix</code> • <code>active_portlets.sql</code>
MariaDB	<ul style="list-style-type: none"> • <code>ManagerSchema_MariaDB.sql</code> • <code>ManagerSchema_MariaDB_StoredProcedures.sql</code> • <code>ManagerSchema_MariaDB_CreateFKConstraints.sql</code> • <code>active_portlets.sql</code> • <code>quartz_MariaDB.sql</code>
Oracle	<ul style="list-style-type: none"> • <code>ManagerSchema_Oracle.sql</code> • <code>ManagerSchema__Oracle_CeateFKConstraints.sql</code> • <code>active_portlets.sql</code>

If you plan to use the scheduler feature that enables you to configure a flowchart to run at predefined intervals, you must also create the tables that support this feature. To create the scheduler tables, run the appropriate script, as described in the following table.

Table 125. Scripts for enabling the Unica Scheduler

Data Source Type	Script Name
DB2®	quartz_db2.sql
Microsoft™ SQL Server	quartz_sqlServer.sql
Oracle	quartz_oracle.sql
MariaDB	quartz_MariaDB.sql
Informix	quartz_informix.sql

When to use the create system tables scripts

You must use these scripts when you install or upgrade Unica Platform if you have not allowed the installer to create the system tables automatically, or if you have used `ManagerSchema_DropAll.sql` to delete all Unica Platform system tables from your database.

populateDb

The `populateDb` utility inserts default (seed) data in the Unica Platform system tables.

The Unica installer can populate the Unica Platform system tables with default data for Unica Platform and for Unica Campaign. However, if your company policy does not permit the installer to change the database, or if the installer is unable to connect with the Unica Platform system tables, you must insert default data in the Unica Platform system tables using this utility.

For Unica Campaign, this data includes security roles and permissions for the default partition. For Unica Platform, this data includes default users and groups, and security roles and permissions for the default partition.

Syntax

```
populateDb -n productName
```

Commands

```
-n productName
```

Insert default data into the Unica Platform system tables. Valid product names are `Manager` (for Unica Platform) and `Campaign` (for Unica Campaign).

Examples

- Insert Unica Platform default data manually.

```
populateDb -n Manager
```

- Insert Unica Campaign default data manually.

```
populateDb -n Campaign
```

ManagerSchema_DropAll.sql

The `ManagerSchema_DropAll.sql` script removes all Unica Platform system tables from a database. This script removes all tables, users, groups, security credentials, and configuration settings from Unica Platform.



Note: If you run this script against a database containing an earlier version of the Unica Platform system tables, you might receive error messages in your database client stating that constraints do not exist. You can safely ignore these messages.

When to use ManagerSchema_DropAll.sql

You might want to use `ManagerSchema_DropAll.sql` if you have uninstalled an instance of Unica Platform where the system tables are in a database that contains other tables you want to continue using.

Additional requirements

To make the Unica Platform operational after running this script, you must perform the following steps.

- Run the appropriate SQL script to re-create the system tables.
- Run the `populateDB` utility. Running the `populateDB` utility restores the default configuration properties, users, roles, and groups, but does not restore any users, roles, and groups you have created or imported after initial installation.
- Use the `configTool` utility with the `config_navigation.xml` file to import menu items.
- If you have performed any post-installation configuration, such as creating data filters or integrating with an LDAP server or web access control platform, you must perform these configurations again.

Preparing your corporate theme

Follow these guidelines to create your corporate theme for the Unica frameset.

1. When you installed Unica Platform, you may have created an EAR file containing the `unica.war` file, or you may have installed the `unica.war` file. In either case, extract your installed file as necessary to access the files and directories the `unica.war` file contains.
2. Locate the `corporatetheme.css` file, located under in the `css\theme\DEFAULT` directory.
3. See the comments in the `corporatetheme.css` file for details on which area of the framework each stylesheet specification affects.
4. See the images in the `css\theme\img` directory to guide you in creating your images.
5. Create your theme in your preferred graphics program and make a note of the image names, fonts, and hexadecimal specifications for the font and background colors.
6. Edit the `corporatetheme.css` file to use your fonts, colors, and images.

Applying your corporate theme

Follow this procedure to apply your corporate theme to the Unica user interface.

1. Place the images you want to use (for example, your logo, buttons, and icons) in a directory accessible from the machine where Unica Platform is installed. Refer to the modified `corporatetheme.css` file, created as described in a "Preparing your corporate theme," to determine where to place your images.
2. If Unica Platform is deployed, undeploy it.
3. When you installed Unica Platform, you may have created an EAR file containing the `unica.war` file, or you may have installed the `unica.war` file. In either case, do the following.
 - Make a backup of your WAR or EAR file, saving the backup with a different name (for example, `original_unica.war`). This enables you to roll back your changes if necessary.
 - Extract your installed file as necessary to access the files and directories the `unica.war` contains.
4. Place the modified `corporatetheme.css` file, created as described in "Preparing your corporate theme," in the `css\theme` directory.

This overwrites the blank `corporatetheme.css` file that is already there.

5. Re-create the `unica.war` file, and, if necessary, the EAR file that contained it.
6. Deploy the WAR or EAR file.
7. Clear your browser cache and log in to Unica.

Your new theme should be applied.