

Unica Segment Central Installation Guide



Contents

Chapter 1. Installation overview.....	1
How the installers work.....	1
Modes of installation.....	1
Unica Segment Central documentation and help.....	2
Chapter 2. Planning the Unica Segment Central installation.....	4
Prerequisites.....	4
Installation order for Unica products.....	6
Where to install Unica Segment Central and Unica Platform.....	7
Chapter 3. Configuring the web application server for your JDBC driver.....	8
Creating JDBC connections in the web application server.....	9
Information for creating JDBC connections.....	9
Chapter 4. Installing Unica Segment Central.....	17
Installing Unica Segment Central in GUI mode.....	18
Installing Unica Segment Central in console mode.....	24
Installing Unica Segment Central in silent mode.....	25
Installation prompt windows.....	27
Chapter 5. Deploying Unica Segment Central.....	31
Configuring JVM parameters for Unica products.....	31
Deploying Unica Segment Central on WebSphere.....	38
Deploying Unica Segment Central on WebLogic.....	39
Deploying Unica Segment Central on JBoss.....	40
Deploying Unica Segment Central on Tomcat.....	41
Chapter 6. Configuration of Unica Segment Central after Deployment.....	46

Granting the asm_admin user access to Unica Segment Central.....	46
Assigning custom roles and permissions to the user.....	47
Configuring datasource in Unica Segment Central.....	47
Chapter 7. Administration of Unica Segment Central.....	49
Points to consider for Campaign Segments and Segment Central.....	49
Enabling or Disabling Unica Segment Central.....	50
Configuring Unica Segment Central.....	51
Segment Central Navigation.....	51
Segment Central partitions partition[n] Content Integration dataSources (systemConfigurationTemplates).....	52
Segment Central partitions partition[n] Content Integration dataSources Audience Central.....	52
Segment Central partitions partition[n] Content Integration dataSources Segment Central.....	55
Segment Central partitions partition[n] Content Integration dataSources Journey.....	59
Segment Central partitions (partitionTemplate).....	62
Chapter 8. Uninstall Unica Segment Central.....	63
Uninstalling Unica Segment Central.....	63

Chapter 1. Installation overview

The installation of HCL Unica products is complete when you install, configure, and deploy the Unica HCL products. The Installation Guide provides detailed information about installing, configuring, and deploying the products.

How the installers work

You must use the suite installer and the product installer when you install any Unica product. For example, for installing Unica Platform and Unica Segment Central, you must use the Unica suite installer and the Unica Segment Central installer.

Make sure that you use the following guidelines before you use the Unica suite installer and the product installer:

- The suite installer and the product installer must be in the same directory on the computer where you want to install the product. When multiple versions of a product installer are present in the directory with the master installer, the master installer always shows the latest version of the product on the Unica products screen in the installation wizard.
- The default top-level directory for Unica installations is `/root/HCL/Unica` for UNIX™ or `C:\HCL\Unica` for Microsoft® Windows®. However, you can change the directory during installation.

Modes of installation

The Unica suite installer can run in one of the following modes: GUI mode / X Window System mode, Console mode, or Silent mode (also called the unattended mode). Select a mode that suits your requirements when you install Unica Segment Central.

GUI mode or X Window System mode

To install Unica Segment Central using the GUI mode, use:

- the GUI mode for Microsoft Windows
- the X Window System mode for UNIX

Console mode

To install Unica Segment Central in console mode, use the command line window



Note: To display the Installer screens correctly in console mode, configure your terminal software to support `UTF-8` character encoding. Other character encoding, such as ANSI, will not render the text correctly, and some information will not be readable.

Silent mode

To install Unica Segment Central multiple times, use the silent mode or the unattended mode. The silent mode uses response files for installation. It does not require user input during the installation process.

Unica Segment Central documentation and help

The following table describes the various tasks in the installation of Unica Segment Central.

The **Documentation** column contains names of documents where you can find more information about the tasks.

The following tables describes administrative tasks in Segment Central. The **Documentation** column contains names of documents where you can find more information about the tasks.

Table 1. Getting help

This two-columned table contains information about how to start Online Help and access PDF documentation for Segment Central. Second column contains instructions for the tasks.

Task	Instructions
Obtain PDFs	Use either of the following methods:

Table 1. Getting help

This two-columned table contains information about how to start Online Help and access PDF documentation for Segment Central. Second column contains instructions for the tasks.

(continued)

Task	Instructions
	<ul style="list-style-type: none">• Choose Help > Product Documentation to access Segment Central PDFs.• Choose Help > All Unica Suite Documentation to access all available documentation.

Chapter 2. Planning the Unica Segment Central installation

When you plan your Unica Segment Central installation, ensure the following:

- You have set up your system correctly
- You have configured your environment to deal with any failures

Prerequisites

Before you install a Unica product, you must ensure that your computer complies with all the prerequisite software and hardware.

System requirements

For information about system requirements, see the Recommended Software Environments and Minimum System Requirements guide.

Network domain requirements

The Unica products that are installed as a suite must be installed on the same network domain to comply with the browser restrictions that are designed to limit the security risks that can occur with cross-site scripting.

JVM requirements

Unica applications within a suite must be deployed on a dedicated Java™ virtual machine (JVM). You can deploy Unica Segment Central on a dedicated JVM, or you can deploy it in the same JVM of Unica Platform and Unica Campaign.

Knowledge requirements

To install Unica products, you must have a thorough knowledge of the environment in which the products are installed. This knowledge includes knowledge about operating systems, databases, and web application servers.

Internet browser settings

Make sure that your internet browser complies with the following settings:

- The browser must not cache web pages.
- The browser must not block pop-up windows.

Access permissions

Verify that you have the following network permissions to complete the installation tasks:

- Administration access for all necessary databases



Note: Administrator must have `CREATE`, `SELECT`, `INSERT`, `UPDATE`, `DELETE`, and `DROP` rights for both tables and views.

- Read and write access to the relevant directory and sub-directories for the operating system account that you use to run the web application server and Unica components
- Write permission for all files that you must edit
- Write permission for all directories where you must save a file, such as the installation directory and backup directory if you are upgrading
- Appropriate read, write, and execute permissions to run the installer

Verify that you have the administrative password for your web application server. For UNIX™, all installer files for products must have full permissions, for example, `rw-r-xr-x`. The following additional permissions are necessary for UNIX™:

- The user account that installs Segment Central and Unica Platform must be a member of the same group. This user account must have a valid home directory and have write permissions for that directory.
- All installer files for HCL Marketing Software products must have full permissions, for example, `rw-r-xr-x`.

JAVA_HOME environment variable

If a `JAVA_HOME` environment variable is defined on the computer where you install a Unica product, verify that the variable points to a supported version of JRE. For information about

system requirements, see the Recommended Software Environments and Minimum System Requirements guide.

If the JAVA_HOME environment variable points to an incorrect JRE, you must clear the JAVA_HOME variable before you run the Unica installers.

You can clear the JAVA_HOME environment variable by using one of the following methods:

- Windows™: In a command window, enter set JAVA_HOME= (leave empty) and press Enter.
- UNIX™: In the terminal, enter export JAVA_HOME= (leave empty) and press Enter.

The Unica installer installs a JRE in the top-level directory for the Unica installation. Individual Unica application installers do not install a JRE. Instead, they point to the location of the JRE that is installed by the Unica installer. You can reset the environment variable after all installations are complete.

For more information about the supported JRE, see the Recommended Software Environments and Minimum System Requirements guide.

Installation order for Unica products

When you install or upgrade multiple Unica products, you must install them in a specific order.

The following table provides information about the order that you must follow when you install or upgrade multiple Unica products.

Table 2. Installation or upgrade order for Unica products

Installation or upgrade order for Unica products

For this product or combination:	Install or upgrade in this order:
Unica Segment Central	<ol style="list-style-type: none"> 1. Unica Platform 2. Unica Campaign 3. Unica Segment Central

Where to install Unica Segment Central and Unica Platform

You can install Unica Segment Central on its own machine, where no other Unica products are installed, or on a machine that it shares with Unica Platform.

The Unica Platform application contains the common navigation, reporting, user administration, security, scheduling, and configuration management features. For each Unica environment, you must install and deploy the Unica Platform once.

Chapter 3. Configuring the web application server for your JDBC driver

The web application server where you plan to deploy Unica Segment Central must contain the correct JAR file to support JDBC connections. This enables your web application to connect to the system tables. The location of the JAR file must be included in the class path of the web application server.



Note: If you are installing Unica Segment Central on the same machine where you installed Unica Platform, this task is already complete. Continue to Creating JDBC connections in the web application server (on page 10).

1. Obtain the latest Type 4 JDBC drivers and any required associated files (for example, Oracle requires several associated files) for the database you plan to use. See the Recommended Software Environments and Minimum System Requirements guide for details.

You should always use the latest vendor-provided Type 4 driver.

- If the driver does not exist on the machine where Unica Segment Central will be installed, obtain it, and copy it to any location on the Unica Segment Central machine.
 - If you obtain the driver from a machine where the database client is installed, verify that the version is the latest supplied by the database vendor. See your consultant for a list of supported JDBC drivers.
2. Include the full path to the driver in the `CLASSPATH` of the web application server where you plan to deploy Unica Segment Central, as follows.
 - For all supported versions of WebLogic, add the `jar` files to the `CLASSPATH` variable in `DOMAIN_DIR\bin\setDomainEnv.cmd`. Yours must be the first entry of the `CLASSPATH` values to ensure that the web application server uses the correct driver. For example, if you are using SQL Server you might set the path as follows.

```
set CLASSPATH=c:\SQLDRIVER\sqljdbc.jar;%PRE_CLASSPATH%;
%WEBLOGIC_CLASSPATH%; %POST_CLASSPATH%;%WLP_POST_CLASSPATH%
```

- For all supported versions of WebSphere®, set the `CLASSPATH` in the Administration Console.

Creating JDBC connections in the web application server

The Unica Segment Central web application uses JDBC connections to communicate with the system table database and with the Unica Platform and Unica Campaign system table database.

You must create this JDBC connection in the web application server where you plan to deploy Unica Segment Central. If you are using WebLogic or Tomcat, you must add the JDBC driver to your class path manually. The installer does this automatically for WebSphere.



Important: For the connection to the database holding the Unica Platform system tables, you must use `UnicaPlatformDS` as the JNDI name. For the connection to the database holding the Unica Campaign system tables, you must use `campaignPartition1DS` as the JNDI name. If Campaign has multiple partitions, we will need the datasources for all the partitions of Campaign. These are the required JNDI names.

JDBC connections in the web application server will be required for all the user DataSources created under Campaign, this is required to use them in Segment Central.

If you expect to have many concurrent users in Unica Segment Central, you may need to increase the number of connections in your web server. For best results, set your web server to allow 50 connections.

Information for creating JDBC connections

Use default values when you create JDBC connections if specific values are not provided. For more information, see the application server documentation.



Note:

- If you are not using the default port setting for your database, make sure that you change it to the correct value.
- Do not select the database type "Informix" during installation of 12.1.0, as it is not functional.

WebLogic

Use the following values if your application server is WebLogic:

SQLServer

- Database Driver: Microsoft™ MS SQL Server Driver 2014, 2016 SP1, 2017
- Default port: 1433
- Driver class: `com.microsoft.sqlserver.jdbc.SQLServerDriver`
- Driver URL:

`jdbc:sqlserver://<your_db_host>:<your_db_port>;databaseName=<your_db_name>`

- Properties: Add `user=<your_db_user_name>`

Oracle

- Driver: Other
- Default port: 1521
- Driver class: `oracle.jdbc.OracleDriver`
- Driver URL:

`jdbc:oracle:thin:@<your_db_host>:<your_db_port>:<your_db_service_name>`

Enter the driver URL by using the format that is shown. Unica applications do not allow the use of Oracle's RAC (Real Application Cluster) format for JDBC connections.

- Properties: Add `user=<your_db_user_name>`

DB2®

- Driver: Other
- Default port: 50000
- Driver class: `com.ibm.db2.jcc.DB2Driver`
- Driver URL: `jdbc:db2://<your_db_host>:<your_db_port>/<your_db_name>`
- Properties: Add `user=<your_db_user_name>`

MariaDB

- Driver: `org.mariadb.jdbc.Driver`
- Default port: 3306
- Driver class: `com.ibm.db2.jcc.DB2Driver`
- Driver URL: `jdbc:mysql://hostname:port/databaseName`

Tomcat

Specify the native library path of the database driver JAR file on your server. For example: `db2jcc4.jar/ojdbc8.jar/sqljdbc-6.4.0.jre8.jar` to create a datasource under Tomcat Interact Instance, add folder hierarchy as `<Tomcat_Home>/conf/Catalina/localhost`, create a xml file with the name `SegmentationEngine.xml` and `SegmentCentral.xml` under localhost folder. Refer platform or Campaign xml file which is created through installers inside their respective Tomcat instance directory.



Note: If you want to encrypt password then run utility `encryptTomcatDBPasswords.sh` from `<PLATFORM_HOME>/tools/bin`. To know more about utility, see *Unica Platform Administrator Guide*.

Use the following values if your application server is Tomcat:

SQLServer

- Database Driver: Microsoft MS SQL Server Driver (Type 4) Versions: 2014, 2016 SP1, 2017
- Default port: 1433
- Driver class: `com.microsoft.sqlserver.jdbc.SQLServerDriver`

- Driver type: `javax.sql.DataSource`

- Driver URL:

`jdbc:sqlserver://<your_db_host>:<your_db_port>;databaseName=<your_db_name>`

Oracle

- Driver: Oracle JDBC Driver
- Default port: 1521
- Driver class: `oracle.jdbc.OracleDriver`
- Driver URL:

`jdbc:oracle:thin:@<your_db_host>:<your_db_port>:<your_db_service_name>`

DB2

- Driver: JCC Driver Provider
- Default port: 50000
- Driver class: `com.ibm.db2.jcc.DB2Driver`
- Driver URL: `jdbc:db2://<your_db_host>:<your_db_port>/<your_db_name>`

MariaDB

- Driver: `MariaDBDriver` (this is the mariadb jar registered with mariadb)
- Default port: 3306
- Driver class: `org.mariadb.jdbc.MariaDbDataSource`
- Driver URL: `jdbc:mariadb://<your_db_host>:<your_db_port>/<your_db_name>`

WebSphere®

Use the following values if your application server is WebSphere®:

SQLServer

- Driver: N/A
- Default port: 1433

- Driver class: `com.microsoft.sqlserver.jdbc.SQLServerConnectionPoolDataSource`
- Driver URL: `jdbc:sqlserver://<DBhostName>:1433;databaseName=<DBName>`

In the **Database Type** field, select **User-defined**.

After you create the JDBC Provider and data source, go to the **Custom Properties** for the data source, and add, modify properties as follows.

- `serverName=<your_SQL_server_name>`
- `portNumber =<SQL_Server_Port_Number>`
- `databaseName=<your_database_name>`

Add the following custom property:

Name: `webSphereDefaultIsolationLevel`

Value: 1

Datatype: Integer

Oracle

- Driver: Oracle JDBC Driver
- Default port: 1521
- Driver class: `oracle.jdbc.OracleDriver`
- Driver URL:
`jdbc:oracle:thin:@<your_db_host>:<your_db_port>:<your_db_service_name>`

Enter the driver URL by using the format that is shown. Unica applications do not allow the use of Oracle's RAC (Real Application Cluster) format for JDBC connections.

DB2®

- Driver: JCC Driver Provider
- Default port: 50000
- Driver class: `com.ibm.db2.jcc.DB2Driver`
- Driver URL: `jdbc:db2://<your_db_host>:<your_db_port>/<your_db_name>`

Add the following custom property:

Name: webSphereDefaultIsolationLevel

Value: 2

Datatype: Integer

MariaDB

- Driver: `MariaDBDriver` (this is the mariadb jar registered with mariadb)
- Default port: 3306
- Driver class: `org.mariadb.jdbc.MariaDbDataSource`
- Driver URL: `jdbc:mariadb://<your_db_host>:<your_db_port>/<your_db_name>`

JBoss

Specify the native library path of the database driver JAR file on your server. For example:

`db2jcc4.jar/ojdbc8.jar/sqljdbc-6.4.0.jre8.jar.`

Use the following values if your application server is JBoss:

SQLServer

- Database Driver: Microsoft MS SQL Server Driver (Type 4) Versions: 2014, 2016 SP1, 2017
- Default port: 1433
- Driver class: `com.microsoft.sqlserver.jdbc.SQLServerDriver`
- Driver URL:

`jdbc:sqlserver://<your_db_host>:<your_db_port>;databaseName=<your_db_name>`

For example `:/subsystem=datasources/data-source=UnicaPlatformDS:add(jndi-name="java:/UnicaPlatformDS",connection-url="jdbc:sqlserver://localhost:1433;databaseName=plat11",driver-name=sql,user-name=sa,password=test1234,valid-connection-checker-class-name="org.jboss.jca.adapters.jdbc.extensions.mssql.MSSQLValidConnectionChecker")`

Oracle

- Driver: Oracle JDBC Driver
- Default port: 1521
- Driver class: `oracle.jdbc.OracleDriver`
- Driver URL:

```
jdbc:oracle:thin:@<your_db_host>:<your_db_port>:<your_db_service_name>
>
valid-connection-checker-class-name=valid-connection-checker-class-name=
"org.jboss.jca.adapters.jdbc.extensions.oracle.OracleValidConnectionChecker"
```

For example: `/subsystem=datasources/data-source=UnicaPlatformDS:add(jndiname="java:/UnicaPlatformDS",connection-url="jdbc:oracle://localhost:1521`;databaseName=plat11",driver-name=oracle,username=plat,password=test1234,valid-connection-checker-class-name="org.jboss.jca.adapters.jdbc.extensions.oracle.OracleValidConnectionChecker")`

DB2

- Driver: JCC Driver Provider
- Default port: 50000
- Driver class: `com.ibm.db2.jcc.DB2Driver`
- Driver URL:

```
jdbc:db2://<your_db_host>:<your_db_port>/<your_db_name>
valid-connection-checker-class-name=
"org.jboss.jca.adapters.jdbc.extensions.db2.DB2ValidConnectionChecker"
```

For example: `/subsystem=datasources/data-source=UnicaPlatformDS:add(jndiname="java:/UnicaPlatformDS",connection-url="jdbc:db2://localhost:50000;databaseName=plat11",driver-name=db2,username=`

```
plat,password=test1234,valid-connection-checker-class-  
name="org.jboss.jca.adapters.jdbc.extensions.db2.DB2ValidConnectionChecker"
```

MariaDB

- Driver: `MariaDBDriver` (this is the mariadb jar registered with mariadb)
- Default port: `3306`
- Driver class: `org.mariadb.jdbc.MariaDbDataSource`
- Driver URL:

```
jdbc:mariadb://<your_db_host>:<your_db_port>/<your_db_name>
```

Chapter 4. Installing Unica Segment Central

You must run the Unica installer to start the installation of Segment Central. The Unica installer starts the product installer during the installation process. Make sure that the Unica installer and the product installer are saved at the same location.

Each time that you run the Unica suite installer, you must first enter database connection information for the Platform system tables. When the installer starts, you must enter the required information for Campaign.



Note: We can clean install Segment Central to the latest version i.e. 12.1.5 without installing the base version (12.1.4). If you have upgraded Platform and Campaign to 12.1.5, then you can directly install Segment Central to the same version without install the base version 12.1.4 first.



Important: Before you install Unica Segment Central, make sure that the available temporary space on the computer where you install Segment Central is more than three times the size of the Segment Central.

Installation files

The installation files are named according to the version of the product and the operating system on which they must be installed, except UNIX™. For UNIX™, different installation files exist for the X Window System mode and the console mode.

The following table displays examples of the installation files that are named according to the product version and the operating system:

Table 3. Installation files

Operating system	Installation file
Windows™: GUI and console mode	<i>Unica_SegmentCentral_12.1.5-.0_win.exe</i>

Table 3. Installation files
(continued)

Operating system	Installation file
UNIX™: X Window System mode	<i>Unica_SegmentCentral_12.1.5-.0_linux.bin</i>
UNIX™: Console mode	<i>Unica_SegmentCentral_12.1.5-.0_linux.bin,</i>

Installing Unica Segment Central in GUI mode

For Windows™, use the GUI mode to install Segment Central. For UNIX™, use the X Window System mode to install Segment Central.



Important: Before you use the GUI mode to install Segment Central, make sure that the available temporary space on the computer where you install Segment Central is more than three times the size of the Segment Central installer.

To install Segment Central using the GUI mode (for Windows™) or the X Window System mode (for UNIX™):


1. Go to the folder where you have saved the Unica installer and double-click the installer to start it.
2. Click **OK** on the first screen to see the **Introduction** window.
3. Follow the instructions on the installer and click **Next**.


Use the information in the following table to take the appropriate actions on each window in the Unica installer.

Table 4. Unica installer GUI

Window	Description
Introduction	This is the first window of the Unica suite installer. You can access the Seg-



Window	Description
	<p>ment Central installation and upgrade guides from this window.</p> <p>Click Next to go to the next window.</p>
Response Files Destination	<p>Click the Generate Response File check box if you want to generate response files for your product. Response files store the information that is necessary for the installation of your product. You can use response files for an unattended installation of your product.</p> <p>Click Choose to browse to a location where you want to store the response files.</p> <p>Click Next to go to the next window.</p>
HCL Unica Products	<p>In the Install Set list, select Custom to select the products that you want to install.</p> <p>In the Install Set area, you can see all the products whose installation files are in the same directory on your computer.</p> <p>In the Description field, you can view the description of the product that you select in the Install Set area.</p> <p>Click Next to go to the next window.</p>
Installation Directory	<p>Click Choose to browse to the directory where you want to install Unica.</p>


Window	Description
	Click Next to go to the next window.
Select Application Server	<p>Select one of the following application servers for the installation:</p> <ul style="list-style-type: none"> • IBM® WebSphere® • Oracle WebLogic • JBoss • Tomcat <p>Click Next to go to the next window.</p>
Platform Database Type	<p>Select the appropriate Unica Platform database type.</p> <p>Click Next to go to the next window.</p>
Platform Database Connection	<p>Enter the following information about your database:</p> <ul style="list-style-type: none"> • Database host name • Database port • Database name or System ID (SID) • Database username • Database password <p>Click Next to go to the next window.</p> <p> Important: If Unica products are installed in a distributed environment, you must use the machine name rather than the IP address, in the navigation URL, for all the applications in the suite. Also, if you are using a clustered environment and</p>

Window	Description
	 choose to use the ports that are different than the default ports 80 or 443 for deployment, do not use a port number in the value of this property.
Platform Database Connection	Review and confirm the JDBC connection. Click Next to go to the next window.
Preinstallation Summary	Review and confirm the values that you added during the installation process. Click Install to start the installation process. The Unica Platform installer invokes. If a previous instance of Unica Platform exists, the instance is upgraded to the current version. If a previous instance of Unica Platform does not exist, Unica Platform is installed.

4. Follow the instructions on the Unica Platform installer to install or upgrade Platform.
For more information, see *Unica Platform Installation Guide*.
5. In the **Installation Complete** window, click **Done**.
The Unica Platform installation is complete and the Unica Campaign installer opens.
For more information, see *Unica Campaign Installation Guide*.
6. After Unica Campaign installation is completed, Segment Central installer opens.
7. Use the information in the following table to navigate the Segment Central installer.

Table 5. Unica Segment Central installer GUI

Window	Description
Introduction	This is the first window of the Segment Central installer. Click Next to go to the next window.
License Agreement	Carefully read the agreement. Use Print to print the agreement. Click Next after you accept the agreement.
Installation Directory	Click Choose to browse to the directory where you want to install Segment Central. Click Next to go to the next window.
Components	Select J2EE Application and click Next to go to the next window. If you wish to take a backup of the previous install, select the checkbox and provide a location to take the backup. Click Next .
Unica Campaign Database Type	Select a database on which Unica Campaign is setup and click Next to go to the next window.  Note: Do not select the database type "Informix" during installation of 12.1.0, as it is not functional.
Unica Campaign Database Connection	Enter the following details for the Campaign database: <ul style="list-style-type: none"> • Database host name • Database port • Database system ID (SID) • Database username • Password  Important: If Unica products are installed in a distributed environment, you must use the machine name rather than the IP address, in the navigation

Window	Description
	<p> URL, for all the applications in the suite. Also, if you are using a clustered environment and choose to use the ports that are different than the default ports 80 or 443 for deployment, do not use a port number in the value of this property.</p> <p>Click Next to go to the next window.</p>
JDBC connection	<p>Review and confirm the JDBC connection.</p> <p>Click Next to go to the next window.</p>
Unica Segment Central Connection Settings	<p>Enter the following connection settings:</p> <ul style="list-style-type: none"> • Network domain name • Host name • Port number <p>Select the Use secure connection check box if necessary.</p> <p>Click Next to go to the next window.</p>
Unica Segment Central Internal URL Connection Settings	<p>Enter the following connection settings:</p> <ul style="list-style-type: none"> • Network domain name • Host name • Port number <p>Select the Use secure connection check box if necessary.</p> <p>Click Next to go to the next window.</p>
Unica Segment Central Segmentation Engine URL Connection Settings	<p>Enter the following connection settings:</p> <ul style="list-style-type: none"> • Network domain name • Host name • Port number <p>Select the Use secure connection check box if necessary.</p> <p>Click Next to go to the next window.</p>

Window	Description
Pre-Installation Summary	Review and confirm the values that you added during the installation process. Click Install to start the installation process. The Segment Central installer opens.
Installation Complete	Click Done to close the Platform installer and go back to the Unica installer.

8. In the **Installation Complete** window, click **Done** to exit the Segment Central installer and go back to the Unica installer.
9. Follow the instructions on the Unica installer to finish installing Segment Central.

Installing Unica Segment Central in console mode

The console mode allows you to install Unica Segment Central command-line window. You can select various options in the command-line window to complete tasks such as selecting the products to install or selecting the home directory for the installation.

Before you install Segment Central, ensure that you have configured the following.

- An application server profile
- A database schema

To display the installer screens correctly in console mode, configure your terminal software to support `UTF-8` character encoding. Other character encodings, such as `ANSI`, do not render the text correctly, and some information is not readable with these encodings.

1. Open a command-line prompt window and navigate to the directory where you have saved the Unica installer and the Interact installer.
2. Complete one of the following actions to run the Unica installer.
 - For Windows™, enter the following command:

```
Unica_installer_full_name -i console
```

For example, `HCL_Unica_Installer_12.1.5.0_win.exe -i console`

- For UNIX™, invoke the `HCL_Unica_installer_full_name.sh` file.

For example: `HCL_Unica_Installer_12.1.5.0.sh`

3. Run the Unica installer file.

For example: `HCL_Unica_Installer_12.1.5.0.sh`

4. Follow the directions that are displayed in the command-line prompt. Use the following guidelines when you must select an option in the command-line prompt:

- The default options are defined by the symbol `[X]`.
- To select or clear an option, type the number that is defined for the option, and then press `Enter`.

For example, suppose that the following list displays the components that you can install:

- 1 `[X]` Unica Platform
- 2 `[X]` Unica Campaign
- 3 `[X]` Unica Segment Central

5. The Unica installer launches the Unica Platform installer during the installation process. Follow the instructions in the command-line prompt window of the Platform installer.
6. After you enter `quit` in the Unica Segment Central installer command-line prompt window, the window shuts down. Follow the instructions in the command-line prompt window of the Unica installer to complete the installation of Unica Segment Central.



Note: If any error occurs during the installation, a log file is generated. You must exit the installer to view the log file.

Installing Unica Segment Central in silent mode

Use the unattended or silent mode to install Unica Segment Central multiple times.

Before you install Segment Central, make sure that you have configured the following elements:

- An application server profile
- A database schema

When you install Unica Segment Central by using the silent mode, response files are used to obtain the information that is required during installation. You must create response files for a silent installation of your product. You can create response files by using one of the following methods:

- Using the sample response files as a template for creating your response files. The sample response files are included with your product installers in the **ResponseFiles** compressed archive. For more information about sample response files, see .
- Running the product installers in the GUI (Windows™) or X Window System (UNIX™) mode or the console mode before you install the product in the silent mode. One response file is created for the Unica suite installer, and one or more response files are created for your product installer. The files are created in the directory that you specify.



Important: For security reasons, the installer does not save database passwords in the response files. When you create response files, you must edit each response file to enter database passwords. Open each response file and search for PASSWORD to find where you must edit the response file.

When the installer runs in the silent mode, it looks for the response files in the following directories sequentially:

- In the directory where the Unica installer is saved
- In the home directory of the user who installs the product

Make sure that all response files are in the same directory. You can change the path where response files are read by adding arguments to the command line. For example:
`-DUNICA_REPLAY_READ_DIR="myDirPath" -f myDirPath/installer.properties`

Use the following command for Windows™:

- `HCL_Unica_installer_full_name -i silent`

For example:

```
HCL_Unica_Installer_12.1.5.0_win.exe -i silent
```

Use the following command for Linux™:

- `HCL_Unica_installer_full_name _operating_system .bin -i silent`

For example:

```
./HCL_Unica_Installer_12.1.5.0_linux.bin -i silent
-DUNICA_REPLAY_READ_DIR=
/opt/HCL/Silent12 -f /opt/HCL/Silent12/installer.properties
```

Installation prompt windows

During the installation of Unica Segment Central, several prompt windows display. After you enter the required information, prompt windows display your responses and require a confirmation before you continue. Prompt windows give you the opportunity to make corrections, if needed.

For reference, an example of the prompts that display during installation on a UNIX™ server using console mode follows. Be sure to read and follow the instructions that display during your actual installation.

Use the following example to help you gather required information before you begin your installation and for reference during your installation.

Table 6. Example installation prompts and responses

Prompt	Response
-bash-4.0\$	Initial prompt. Supply the name of the master installer file and any variables for the database setup utility that you want to use for the installation.

Table 6. Example installation prompts and responses (continued)

Prompt	Response
Choose Locale	Supply a number to choose one of the listed languages. To use the default locale, 2- English, press Enter.
Introduction	<p>If a previous version of the product is installed, an upgrade is initiated.</p> <p>If the same version of the product is installed, proceeding drops all tables and data.</p>
Response Files Generation	Supply a number to choose whether to generate response files for use in an unattended installation. If you generate response files, you can supply a destination path.
Choose Product Features	<p>A numbered list of features displays. Features with a check mark [x] are selected for installation, features with no check mark [] are not selected. To change the selections, supply numbers to switch from selected to cleared (or vice versa) by using a comma-separated list, then press Enter.</p> <p>For example, you see this list of features:</p> <pre data-bbox="721 1383 1455 1516">1- Unica Platform 2- Unica Segment Central</pre> <p>To install Unica Platform only, supply 2 and press Enter.</p>
Master (Unica Platform) installation	
Installation Directory	
Select Application Server	

Table 6. Example installation prompts and responses (continued)

Prompt	Response
Platform Database Type	Supply information for the Unica Platform system table database.
Platform Database Host Name	
Platform Database Port	
Platform Database Name/System ID (SID)	
Platform Database User Name	
Platform Database Password	
JDBC Connection	
JDBC Driver Classpath	
Product-specific (Unica Segment Central) installation	
Introduction	For each product feature you chose to install, the specific product name displays followed by the reinstallation warning.
Installation Directory	
Campaign Database Configuration	<p>Supply a number to choose automatic or manual.</p> <ul style="list-style-type: none"> • Select the database used in Unica Campaign. • Configure the requested values for Campaign database.
JDBC Connection	Configure the path for JDBC connection
Unica Segment Central Settings	Configure connection setting values like Network domain, Host name, and Port number.

Table 6. Example installation prompts and responses (continued)

Prompt	Response
Deployment EAR file	Supply a number to choose whether to create an enterprise archive (EAR) file

Chapter 5. Deploying Unica Segment Central

We need to deploy two wars **SegmentationEngine.war** and **SegmentCentral.war**.

It is assumed that you know how to work with your web application server. Consult your web application server documentation for details about things like how to use the Administration console.

Configuring JVM parameters for Unica products

You must configure the following JVM parameters in the Unica products.

Table 7. Unica Products and the JVM Parameters to be Configured

Unica Product Name	JVM Parameters
Unica Centralized Offer Management	<ul style="list-style-type: none">• <code>-DUNICA_PLATFORM_CACHE_ENABLED=true</code>• <code>-DUNICA_PLATFORM_LOCAL_CACHE_ENABLED=true</code>• <code>-Dclient.encoding.override=UTF-8</code>• <code>-DOFFER_HOME=<CentralizedOffer_home_directory_path></code>
Unica Contact Central	<ul style="list-style-type: none">• <code>-DCONTACTCENTRAL_HOME</code>• <code>-DUNICA_PLATFORM_HOME</code>
Unica Content Integration	<ul style="list-style-type: none">• <code>-DASSET_PICKER_HOME</code>• <code>-DUNICA_PLATFORM_HOME</code>
Unica Segment Central	<ul style="list-style-type: none">• <code>-DSEGMENT_CENTRAL_HOME=<Segmentcentral_home_directory_path></code>
Unica Audience Central	<ul style="list-style-type: none">• <code>-DAUDIENCE_CENTRAL_HOME=<AudienceCentral_home_directory_path></code>
Unica Deliver	<ul style="list-style-type: none">• <code>-Dcampaign.deliveretl.disabled=true</code>

Table 7. Unica Products and the JVM Parameters to be Configured (continued)

Unica Product Name	JVM Parameters
Unica Interact	<p data-bbox="751 359 1032 390">Interact design time</p> <p data-bbox="751 426 1360 510">The following are the JVM parameters for Interact design time:</p> <ul data-bbox="816 575 1377 1640" style="list-style-type: none"> <li data-bbox="816 575 1377 606">• <code>Interact.UsernameToAlwaysDeployFor</code> <li data-bbox="816 627 1377 711">• <code>com.unicacorp.interact.deliver-templateTimeout</code> <li data-bbox="816 732 1377 764">• <code>DeploymentServletParameterEncoding</code> <li data-bbox="816 785 1377 869">• <code>com.unicacorp.interact.flexoffers-defaultDateTimeFormat</code> <li data-bbox="816 890 1377 974">• <code>com.unicacorp.interact.flexoffers-defaultDateFormat</code> <li data-bbox="816 995 1377 1079">• <code>com.unicacorp.Campaign.interact-offermapping.batchsize</code> <li data-bbox="816 1100 1377 1184">• <code>com.unicacorp.Campaign.interact-offermapping.service.synctimeout</code> <li data-bbox="816 1205 1377 1236">• <code>com.unicacorp.interact.cacheTTL</code> <li data-bbox="816 1257 1377 1341">• <code>com.unicacorp.interact.cacheRefreshIntervalInMin</code> <li data-bbox="816 1362 1377 1446">• <code>com.unicacorp.interact.enableDTPerfLogging</code> <li data-bbox="816 1467 1377 1551">• <code>com.unicacorp.interact.compressAPIResponse</code> <li data-bbox="816 1572 1377 1604">• <code>ignoreSpecialCharacterValidator</code> <li data-bbox="816 1625 1377 1656">• <code>Interact.CustomStringDelimiter</code> <p data-bbox="751 1703 984 1734">Interact run time</p> <p data-bbox="751 1770 1360 1854">The following are the JVM parameters for Interact run time:</p>

Table 7. Unica Products and the JVM Parameters to be Configured (continued)

Unica Product Name	JVM Parameters
	<ul style="list-style-type: none"> • INTERACT_HOME • com.unicacorp.interact.deliver- templateTimeout • INBOUND_GATEWAYS_USING_MAPPING_- FROM_PROPERTIES • com.hcl.interact.http.proxyProto- col • com.hcl.interact.http.proxyHost • com.hcl.interact.http.proxyPort • com.hcl.interact.http.proxyUser- name • com.hcl.interact.http.proxyPass- word • interact.jmx.monitoring.port • interact.runtime.instance.name • interact.offerserving.maxOfferAl- locationInMemoryPerInstance • interact.offerserving.maxDistribu- tionPerIntervalPerInstanceFactor • interact.ignitePort • com.unicacorp.interact.chDupe- CheckLimit • com.unicacorp.interact.rhDupe- CheckLimit • com.unicacorp.interact.chSuppress- Dupe • com.unicacorp.interact.rhSuppress- Dupe • com.unicacorp.interact.testclient- nullValue

Table 7. Unica Products and the JVM Parameters to be Configured (continued)

Unica Product Name	JVM Parameters
	<ul style="list-style-type: none"> • <code>interact.ehcache.config</code> • <code>interact.api.dateFormat</code> • <code>com.hcl.interact.testrun.rowlimit</code> • <code>Interact.DisableExceptionStackTracesInMacros</code> • <code>com.unicacorp.interact.enableDetailStats</code> • <code>com.unica.interact.deployment.timeoutInSecs</code> • <code>com.ibm.interact.instance.name</code> • <code>com.unicacorp.interact.invalidPaths</code> • <code>interact.XSessResponseConsumerManager.generateOnlyOneResponse</code> • <code>tryToPreserveInexactFloatValues</code> • <code>com.unicacorp.interact.propertyRefreshInterval</code> • <code>com.unicacorp.interact.scheduledTasksProcessInterval</code> • <code>com.unicacorp.interact.eventpatterns.parallelism</code> • <code>com.unicacorp.interact.eventpatterns.restartRetries</code> • <code>com.unicacorp.interact.eventpatterns.evaluateTimeoutMilli</code> • <code>com.unicacorp.interact.eventpatterns.restartRetryDelayInSec</code> • <code>Interact.advisoryMessageEncodingOverrides</code>

Table 7. Unica Products and the JVM Parameters to be Configured (continued)

Unica Product Name	JVM Parameters
	<ul style="list-style-type: none"> • <code>com.unica.interact.api.insertSessionIDAsCookie</code> • <code>com.unica.interact.api.SessionIDCookieName</code> • <code>InteractMsgCode</code> • <code>com.ibm.interact.triggeredmessage.enableJMSConsumer</code> • <code>com.unicacorp.interact.maxLengthInFormatMacro</code> • <code>ContinueEvaluatingBranchAndAdvOptTreatmentLogicDespiteExMessageList</code> • <code>DisableDecisionProcessBoxAndAdvOptTreatmentLogging</code> • <code>TwoDigitYearStartDate</code> • <code>Interact.enableTwoDigitYearFix</code> • <code>com.ibm.interact.evpatetl.conf</code> • <code>com.unicacorp.interact.minTreatmentsPerThread</code> • <code>com.unicacorp.interact.maxTreatmentPoolSize</code> • <code>CircuitBreaker.processTimeoutMillis</code> • <code>com.unicacorp.interact.event.asyncTimeoutMSec</code> • <code>com.unicacorp.interact.eventActionTimeout</code> • <code>Interact.HTMI.Enabled</code> • <code>Interact.HTMI.MaxRequestDurationInMs</code> • <code>Interact.HTMI.RecordIndividualAPIs</code>

Table 7. Unica Products and the JVM Parameters to be Configured (continued)

Unica Product Name	JVM Parameters
	<ul style="list-style-type: none"> • <code>Interact.HTMI.MaxStartSessionDurationInMs</code> • <code>Interact.HTMI.MaxGetOffersDurationInMs</code> • <code>Interact.HTMI.MaxPostEventDurationInMs</code> • <code>Interact.HTMI.MaxGetProfileDurationInMs</code> • <code>Interact.HTMI.LogErrorsEveryNthTime</code> • <code>Interact.HTMI.UseMillisecondTimers</code> • <code>Interact.HTMI.Debug</code> • <code>com.unicacorp.interact.suppressWarningOnAnonymousUser</code> • <code>com.hcl.interact.eventpatterns.printPatternAction</code> • <code>com.hcl.interact.eventpatterns.eagerPersist</code> • <code>com.ibm.interact.triggeredmessage.addPerfData</code> • <code>com.unicacorp.interact.learning.disableAggregator</code> • <code>com.unicacorp.interact.learning.disableDeletion</code> • <code>com.unicacorp.interact.learning.ignoreInterval</code> • <code>interact.services.loader.saveLoaderFiles</code> • <code>ConvertEveryNULLAttributeValueToAJEPNullConstant</code>

Table 7. Unica Products and the JVM Parameters to be Configured (continued)

Unica Product Name	JVM Parameters
	<ul style="list-style-type: none"> • <code>includeJoinInfo</code> • <code>com.unicacorp.interact.deployment.reloadTimeout</code> • <code>com.ibm.interact.lockTimeWarningThreshold</code> • <code>com.unicacorp.interact.cache.maxWaitTime</code> • <code>DEFAULT_PERSISTENCE_PROVIDER</code>
Unica Journey	
Unica Plan	<ul style="list-style-type: none"> • <code>-Dplan.log4j.config=<plan_home>/conf/plan_log4j.xml</code> • <code>-Dplan.log4j.async=TRUE</code> • <code>-Dplan.home=<plan_home></code>
Unica Platform	<ul style="list-style-type: none"> • <code>-REMOVE_REQUESTED_AUTHN_CONTEXT=TRUE</code> • <code>-DENABLE_PLATFORM_LOG4J_XML_LOGGING=TRUE</code> • <code>-DENABLE_PERSISTENT_NAMEID_FORMAT=TRUE</code> • <code>-DUNICA_PLATFORM_HOME=<platform_home_directory_path></code>



Note: For the Oracle database - If atleast one of the ID field(s) defined in audience, is of type number and data in the mapped table column consists of decimal point numbers, then don't use `-Doracle.jdbc.J2EE13Compliant=true` JVM parameter. Also, deploy this product in separate JVM than other unica products deployed with said JVM argument.

Deploying Unica Segment Central on WebSphere

You can deploy the Unica Segment Central application from a WAR file on the WebSphere® Application Server (WAS).

Consider the following points before you deploy Unica Segment Central on WebSphere:

- Verify that your version of WebSphere® meets the requirements that are described in the *Recommended Software Environments and Minimum System Requirements* document, including any necessary fix packs or upgrades.
- You use the WebSphere® Integrated Solutions console to configure your WebSphere® Application Server. The steps that follow provide guidance for setting specific controls.



Note: Different versions of WebSphere® Application Server present user interface controls in varying sequences and with alternative labels.

Complete the following steps to set up the environment for deploying Unica Segment Central:

1. Configure the JVM: On the **Application servers > <server> > Process definition > Java Virtual Machine** form, identify the Classpath then add the following entries as Generic JVM arguments, separated by a space:

- `-DSEGMENT_CENTRAL_HOME=<UNICA_HOME>\<Segment_Home>`

where `<Unica_Home>` is the path to the top-level HCL directory and

`<Segment_Home>` is the path to the directory where you installed Unica Segment Central. Typically, this path is `<UNICA_HOME>\Segment_Home`.

- For your installation to support non-ASCII characters, example for Portuguese or for locales that require multi-byte characters, add the following arguments to Generic JVM Arguments at the server level:

```
-Dfile.encoding=UTF-8
-Dclient.encoding.override=UTF-8
```

- **set** "JAVA_OPTS=%JAVA_OPTS% -DUNICA_PLATFORM_CACHE_ENABLED=true"

2. Set the JSP Compilation level in the WebSphere application server to 18.

Deploying Unica Segment Central on WebLogic

Use the following guidelines for deploying Unica Segment Central on WebLogic.

- Unica products customize the JVM used by WebLogic. You might create a WebLogic instance dedicated to Unica products if you encounter JVM-related errors.
- Do not install more than one Unica Segment Central application under the same WebLogic domain.
- Verify that the Software Development Kit (SDK) selected for the WebLogic domain you are using is the Sun SDK by looking in the startup script (`startWebLogic.cmd`) for the `JAVA_VENDOR` variable. It should be set to `JAVA_VENDOR=Sun`. If it is set to `JAVA_VENDOR=BEA`, JRockit has been selected. JRockit is not supported. To change the selected SDK, refer to the WebLogic documentation.

Complete the following steps to deploy Unica Segment Central to WebLogic:

1. If you are configuring WebLogic to use the IIS plug-in, review the WebLogic documentation to determine whether you have additional requirements.
2. From the `bin` directory under your WebLogic domain directory, locate and open the `setDomainEnv` script in a text editor. Scroll to the `JAVA_OPTIONS` property and add the following entries. Use a space to separate entries.

- **set** "JAVA_OPTS=%JAVA_OPTS% -DUNICA_PLATFORM_CACHE_ENABLED=true
-DSEGMENT_CENTRAL_HOME=<UNICA_HOME>\<Segment_Home>"

where `<UNICA_HOME>` is the path to the top-level directory and `<Segment_Home>` is the path to the directory where you installed Unica Segment Central.

- For your installation to support non-ASCII characters, example for Portuguese or for locales that require multi-byte characters, add the following arguments to Generic JVM Arguments at the server level:

```
-Dfile.encoding=UTF-8  
-Dclient.encoding.override=UTF-8
```

3. Save and close the file.
4. Restart WebLogic.
5. Deploy Unica Segment Central as a web application module.
6. Start the deployed web application.

Deploying Unica Segment Central on JBoss

You can deploy Unica products on JBOSS application server. Use the following guidelines when you deploy Unica Segment Central on JBOSS:

1. Verify that your version of JBoss meets the requirements that are described in the *Recommended Software Environments and Minimum System Requirements* guide, including any necessary fix packs or upgrades.
2. HCL Marketing Software products customizes the JVM used by JBoss. You might need to create a JBoss instance that is dedicated to HCL Marketing Software products, if you encounter JVM-related errors.
3. If you are deploying in a production environment, set the JVM memory heap size parameters to at least 1024 by adding the following line to the `standalone.conf` file in the `JBOSS_EAP_HOME/bin`:

```
JAVA_OPTS="-Xms1024m -Xmx1024m -XX:MetaspaceSize=96M -  
XX:MaxMetaspaceSize=256m "
```

These are the suggested minimum values. Analyze your sizing requirements to determine correct values for your needs. Depending upon system load `-Xmx` and `MaxMetaspaceSize` value should be adjusted.



Note: A 64-bit application server and JVM are usually required for values greater than 2048.

4. Modify the `JAVA_OPTIONS` parameter to add the following value in `setenv.bat/sh`:

```
set "JAVA_OPTS=%JAVA_OPTS% -DUNICA_PLATFORM_CACHE_ENABLED=true
-Dclient.encoding.override=UTF-8
-DSEGMENT_CENTRAL_HOME=<UNICA_HOME>\<Segment_Home>"
```

5. Navigate to the JBoss Enterprise Application management Console, for example `http://<Jboss_Host_IP>:<Port>/management`.
6. Deploy `SegmentCentral.war` and `SegmentationEngine.war` on JBOSS.
7. You can also deploy `SegmentCentral.war` and `SegmentationEngine.war` using `jboss-cli.bat/sh`. Run the following command:

```
jboss-cli.bat/sh
```

and connect to the JBoss instance using the following command:

```
connect <Jboss_Host_IP>:<JBOSS management Port>
deploy <UNICA_HOME>/<Segment_Home>/SegmentCentral.war
deploy <UNICA_HOME>/<Segment_Home>/SegmentationEngine.war
```

8. After making the changes, restart the JBoss application server.

Deploying Unica Segment Central on Tomcat

You must follow a set of guidelines when you deploy Unica Segment Central on Apache Tomcat.

Ensure that the version of Apache Tomcat meets the requirements that are described in the Recommended Software Environments and Minimum System Requirements document.



Note: Deployment of EAR file is not supported on Apache Tomcat.

Use the following guidelines when you deploy Unica Segment Central on Apache Tomcat:

1. From the bin directory, inside the Apache Tomcat installation directory (Inside the `<Tomcat_Instance_Home>\instanceN\bin`), locate or create the `setenv.sh` or `setenv.bat` script appropriate for your operating system in a text editor, and add or modify `JAVA_OPTIONS` property, and add the following entries. Use a space to separate entries.

- `-DSEGMENT_CENTRAL_HOME=<UNICA_HOME>\<Segment_Home>`

Where `<UNICA_HOME>` is the path to the top-level directory and `<Segment_Home>` is the path to the directory where you installed Unica Segment Central.

```
set "JAVA_OPTS=%JAVA_OPTS%
-DSEGMENT_CENTRAL_HOME=<SegmentCentral_home>
-DUNICA_PLATFORM_CACHE_ENABLED=true"
```

- For your installation to support non-ASCII characters, example for Portuguese or for locales that require multi-byte characters, add the following arguments to Generic JVM Arguments at the server level:

```
-Dfile.encoding=UTF-8
-Dclient.encoding.override=UTF-8
```

2. Create the `SegmentCentral.xml` file and place in `<Tomcat_Install_Home>\instanceN\conf\Catalina\localhost`. The following is a sample file

```
<?xml version="1.0"?>
<Context docBase="<SEGMENT_HOME>\SegmentCentral.war">
  <Resource name="UnicaPlatformDS"
    factory="com.unica.manager.tomcat.utils.TomcatDSFactory"
    auth="Application" type="javax.sql.DataSource"
      maxActive="30" maxIdle="10" maxWait="10000"
      username="<USER_NAME>"
    password="<ENCRYPTED_PASSWORD>"
    driverClassName="com.microsoft.sqlserver.jdbc.SQLServerDriver"

    url="jdbc:sqlserver://Host:port;databaseName=<Platform_DB_Name>" />
```

```

        <Resource name="campaignPartition1DS"
factory="com.unica.manager.tomcat.utils.TomcatDSFactory"
auth="Application" type="javax.sql.DataSource"
                maxActive="30" maxIdle="10" maxWait="10000"
                username="<USER_NAME>"
password="<ENCRYPTED_PASSWORD>"
driverClassName="com.microsoft.sqlserver.jdbc.SQLServerDriver"

url="jdbc:sqlserver://Host:port;databaseName=<Campaign_Partition1_DB_
NAME>" />

        <Resource name="campaignPartition2DS"
factory="com.unica.manager.tomcat.utils.TomcatDSFactory"
auth="Application" type="javax.sql.DataSource"
                maxActive="30" maxIdle="10" maxWait="10000"
                username="<USER_NAME>"
password="<ENCRYPTED_PASSWORD>"
driverClassName="com.microsoft.sqlserver.jdbc.SQLServerDriver"

url="jdbc:sqlserver://Host:port;databaseName=<Campaign_Partition2_DB_
NAME>" />
</Context>

```

3. Create the `SegmentationEngine.xml` file and place in `<Tomcat_Install_Home>\instanceN\conf\Catalina\localhost`. The following is a sample file

```

<?xml version="1.0"?>
<Context docBase="<SEGMENT_HOME>\SegmentationEngine.war">
        <Resource name="UnicaPlatformDS"
factory="com.unica.manager.tomcat.utils.TomcatDSFactory"
auth="Application" type="javax.sql.DataSource"
                maxActive="30" maxIdle="10" maxWait="10000"

```

```

        username="<USER_NAME>"
password="<ENCRYPTED_PASSWORD>"
driverClassName="com.microsoft.sqlserver.jdbc.SQLServerDriver"

url="jdbc:sqlserver://Host:port;databaseName=<Platform_DB_Name>"/>

    <Resource name="campaignPartition1DS"
factory="com.unica.manager.tomcat.utils.TomcatDSFactory"
auth="Application" type="javax.sql.DataSource"
        maxActive="30" maxIdle="10" maxWait="10000"
        username="<USER_NAME>"
password="<ENCRYPTED_PASSWORD>"
driverClassName="com.microsoft.sqlserver.jdbc.SQLServerDriver"

url="jdbc:sqlserver://Host:port;databaseName=<Campaign_Partition1_DB_
NAME>"/>

    <Resource name="campaignPartition2DS"
factory="com.unica.manager.tomcat.utils.TomcatDSFactory"
auth="Application" type="javax.sql.DataSource"
        maxActive="30" maxIdle="10" maxWait="10000"
        username="<USER_NAME>"
password="<ENCRYPTED_PASSWORD>"
driverClassName="com.microsoft.sqlserver.jdbc.SQLServerDriver"

url="jdbc:sqlserver://Host:port;databaseName=<Campaign_Partition2_DB_
NAME>"/>
</Context>

```

4. Inside `<PLATFORM_HOME>/tools/bin`, encrypt the password using `encryptTomcatDBPasswords.bat/sh`.

```
encryptTomcatDBPasswords.bat -d <PASSWORD>
```

5. Copy the database driver in `<Tomcat_Instance_Home>\lib`.
6. Start the Segment Central application by running the following command:

```
startup.sh/bat instanceN
```


Chapter 6. Configuration of Unica Segment Central after Deployment

- If you change any datasource configuration in Unica Campaign, it requires restarting the Segment Central, SegmentationEngine application .



Note: Before restarting the SegmentationEngine wait for the publishing segments to get published.

- After you deploy and start the Unica Segment Central application, log in and verify the installation. There are some basic configuration steps such as adding user role, configuring the datasource for temp table creation.

Granting the `asm_admin` user access to Unica Segment Central

The default admin user (`asm_admin`) can access the Unica Segment Central configuration properties automatically. However, there are no default users with access to the Unica Segment Central application until you configure them.

Steps for granting `asm_admin` access to Unica Segment Central:

1. Assign the SegmentCentralUser role to `asm_admin` user.
2. Log back in as `asm_admin`.
3. Verify that you have access to Unica Segment Central (classic UI) features by selecting **Marketing Central > Segment Central**.
4. Verify that you have access to Unica Segment Central (Neo UI) features by selecting **Plan and Manage > Segment Central**.



Note: For more details on assigning **User Roles**, see *Campaign Administrator's Guide*.

Assigning custom roles and permissions to the user

For Unica Segment Central, set user roles and permissions in Unica Campaign.

To set user roles and permissions in Unica Campaign, complete the following step:

1. From the Unica Platform home page, select **Settings > User roles and permissions**.

The User roles and permissions page appears.

2. In the left panel, expand **Unica Campaign > partition(n)**, where n is the number of the partition.

3. Select **Global Policy**

The **Global Policy** page appears.

4. Select **Add roles and assign permissions**.

The **(Global Policy)** page appears.

5. Click **Save and edit permissions**.

The **(Permissions for Global Policy)** page appears.

6. Expand **Segments** and select the following permissions for all the displayed operations in **Add segments, Edit segments, Delete segments, Move segments, View segment summary, Add segment folders, Edit segment folders, Delete segment folders, Move segment folders, Change segment state** and **Copy segments**:

- Folder Owner
- Owner
- Admin
- Execute
- Design
- Review

For more details on user role, see Unica Campaign Administrator's Guide.

Configuring datasource in Unica Segment Central

1. Multiple user databases can be configured in Unica Segment Central. For configuring a datasource complete the below steps:
 - a. In **Unica Segment Central**, choose **Settings > Configuration**
 - b. Go to `Campaign|partitions|partition[n]|dataSources`.
 - c. Select the Datasource



Note: After installation, you need to ensure that data sources should be created in the app server. Also, they should have the same JNDI name.

2. After the installation of Segment Central, a new node will be created at `Affinium|Campaign|partitions|partition1|segmentCentral`. By default, the field value will be blank, you need to provide datasource name where temp tables for Segment Central will be created. Anyone of the supported and configured datasource can be used.



Note: We can have multiple user datasources but only one datasource for creating temp tables.

Chapter 7. Administration of Unica Segment Central

After installing Unica Segment Central, the administrator must complete a few procedures to activate and use Unica Segment Central. The list of procedures are:

- Adding Segment Central User role
- Enabling Unica Segment Central (By default, it is enabled)
- Configuring Unica Segment Central parameters

Points to consider for Campaign Segments and Segment Central

- When creating segments from SegmentCentral, base table mappings created in AudienceCentral will be used. Once we enable segment central, Campaign segments menu under Campaign will not be available. However, you can create new segments from campaign flowcharts, but they will get listed inside segment central. Segments created from Campaign flowcharts will display **relevant in Campaign** and **used in Campaign**. From 12.1.5 onwards Campaign names will not redirect user to the respective campaign and/or flowcharts
- Segment central analysis tab does not have the legacy reports, those will be made available in future releases.
- Base table mapping created from Audience Central will be used by Segment Central for creating segments.
- Though it is not restricted from installation perspective, AudienceCentral and SegmentCentral both should be installed and deployed to be useful as functionally they are dependent on each other.
- Segment central does not consider any post scripts and flag for bin file creation flag. Bin file will not be created through segment central irrespective of the flag value. However, segment creation through campaign flowcharts will continue their behaviour with the bin file creation, DS selection, post scripts etc.
- User should delete Audience levels/ base table mappings on their responsibility- we display the number of segments which are using a particular mapping. While deleting

will make the corresponding segments to fail after republishing but it can be used with created temp tables if not republished.

- Segment Central supports following databases as user data source(s) - Microsoft SQL Serer, MariaDB, Oracle, DB2.
- Segment Central capability is not at par with Campaign segments. For advance segmentation user can continue with Campaign Segmentation capability, even when segment central is enabled.
- Even after switching to SegmentCentral, user can still create segments in campaign and interact in the same way, but the listing will be under SegmentCentral.
- Existing permissions in Campaign are used for segments and segment folders. Any user having create and edit segment permission, can also test run the segment in respective action. There is no separate permission required for test run.

Enabling or Disabling Unica Segment Central

After assigning the **SegmentCentralUser** role to the administrator, enable Unica Segment Central to access the application. For more information, see Adding a new user role to the administrator (on page)

To enable or disable Unica Segment Central, complete the following steps:

1. Select **Settings > Configuration**.

The **Configuration** page appears.

2. In the **Configuration properties** panel, select **Unica Platform**

The **Settings for 'Unica Platform'** page appears in the right panel.

3. Select **Edit settings**.

The **(Unica Platform) Edit Settings** page opens.

4. To enable Unica Segment Central, for the field **Enable Segment Central management?**, select **Yes**. To disable Unica Segment Central, select **No**.

5. Click **Save changes**.

Based on your selection in Step 4, Unica Segment Central will either be enabled or disabled.

Configuring Unica Segment Central

To configure Unica Segment Central, the administrator must have the SegmentCentralUser role. For more information, Adding a new user role to the administrator (on page)

To configure Unica Audience Central, from the Unica homepage, select **Settings > Configuration** . The **Configuration** page appears.

Segment Central | Navigation

Provide values for the optional/mandatory fields:

- **welcomePageURI** - The Uniform Resource Identifier of the Segment Central index page. This value is used internally by Unica applications. Changes to this value are not recommended.

Default value: `jsp/index.jsp`

- **seedName** - Used internally by Unica applications. Changes to this value are not recommended.

Default value: `SegentCentral`

- **type** - Used internally by Unica applications. Changes to this value are not recommended.

Default value: `SegmentCentral`

- **httpPort** - The port number that is used by the application server for connections to the **Segment Central** application.

Default value: `7001`

- **httpsPort** - The port number that is used by the application server for secure connections to the Segment Central application.

Default value: `7001`

- **serverURL** - The URL of the Segment Central installation. Accepts locators with either the HTTP or HTTPS protocol. If users access Segment Central with the Chrome browser, use the fully qualified domain name (FQDN) in the URL. If the FQDN is not used, the Chrome browser cannot access the product URLs.

Default value: `http://<domain-name>:<port-number>/SegmentCentral`

- **logoutURL** - Used internally. Changes to this value are not recommended. Unica Platform uses this value to call the logout handler of each registered application if the user clicks the logout link in suite.

Default value: `/j_spring_security_logout`

- **serverURLInternal** - Specifies the internal URL of the Segment Central server. This value is used internally by Unica applications. Changes to this value are not recommended.

Default value: `[HOST_URL_INTERNAL]/SegmentCentral`

- **displayName** - Used internally.

Default value: `Segment Central`

- **segmentationEngineUrl** - Specifies the Engine URL of the Segment Central Engine. This value is used internally by Unica applications. Changes to this value are not recommended.



Note: If the setup is configured over an HTTP protocol, ensure that **Secure API access over HTTPS** parameter, within **Unica Platform > Security > API management > Segment Central > segmentCentral V1 APIs**, is set to `Disabled`.

Segment Central | partitions | partition[n] | Content Integration | dataSources | (systemConfigurationTemplates)

For more information, see Unica Content Integration Installation and Configuration Guide.

Segment Central | partitions | partition[n] | Content Integration | dataSources | Audience Central

Provide values for the optional/mandatory fields:

- **systemIdentifier**

`AudienceCentral`



Note: If it is multi partition Unica environment, then the system identifier should be:

- For partition 1 - AudienceCentral SCP1
- For partition 2 - AudienceCentral SCP2
- For partition 3 - AudienceCentral SCP3 and so on.

- **userCredentials**

Logged-in user

- **defaultUserCredentials**

Blank

- **dataSourceNameForCredentials**

Blank

- **anonymousContentAccess**

Yes

- **additionalParameters**

Blank

For more information, see Unica Content Integration Installation and Configuration Guide

Segment Central | partitions | partition[n] | Content Integration | dataSources | Audience Central | httpGateway

Provide values for the optional/mandatory fields:

- **baseUrl** -

Default value: http://<localhost>/AudienceCentral

- **contentBaseUrl** -

Default value: http://<localhost>/AudienceCentral

- **bypassProxy** -

Default value: No

Segment Central | partitions | partition[n] | Content Integration | dataSources | Audience Central | httpGateway | rest

Provide values for the optional/mandatory fields:

- **authenticationType** -

Default value: UnicaToken

Segment Central | partitions | partition[n] | Content Integration | dataSources | Audience Central | ci.kafka.configuration

Provide values for the optional/mandatory fields:

- **ci.kafka.bootstrapServers** -

Default value: (Blank)

- **ci.kafka.securityProtocol** -

Default value: NONE

- **ci.kafka.saslMechanism** -

Default value: PLAIN

- **ci.kafka.userForDataSource** -

Default value: (Blank)

- **ci.kafka.dataSourceNameForSaslJaasConfig** -

Default value: (Blank)

- **ci.kafka.trustStoreLocation** -

Default value: (Blank)

- **ci.kafka.dataSourceNameForTrustStorePassword** -

Default value: (Blank)

- **ci.kafka.keystoreLocation** -

Default value: (Blank)

- **ci.kafka.dataSourceNameForKeyStorePassword** -

Default value: (Blank)

- **ci.kafka.dataSourceNameForKeyPassword** -

Default value: (Blank)

- **ci.kafka.kerberosConfFilePath** -

Default value: (Blank)

- **ci.kafka.kerberosKeytabFilePath** -

Default value: (Blank)

- **ci.kafka.kerberosPrincipal** -

Default value: (Blank)

- **ci.kafka.kerberosServiceName** -

Default value: kafka

Segment Central | partitions | partition[n] | Content Integration |
dataSources | Audience Central | qos | retryPolicy

Provide values for the optional/mandatory fields:

- **retryCount** -

Default value: 1

- **initialDelay** -

Default value: 1000

- **delayMultiplier** -

Default value: 1

Segment Central | partitions | partition[n] | Content Integration |
dataSources | Segment Central

Provide values for the optional/mandatory fields:

- **systemIdentifier**

SegmentCentral



Note: If it is multi partition Unica environment, then the system identifier should be:

- For partition 1 - SegmentCentral SCP1
- For partition 2 - SegmentCentral SCP2
- For partition 3 - SegmentCentral SCP3 and so on.

• **userCredentials**

Logged-in user

• **defaultUserCredentials**

Blank

• **dataSourceNameForCredentials**

Blank

• **anonymousContentAccess**

Yes

• **additionalParameters**

audience-event-interpretter.kafka.max-consumers: <max-consumers_num>

audience-event-interpretter.kafka.max-poll-records: <max-poll-records_num>

audience-event-interpretter.kafka.fetch.max.wait.ms: <max.wait.ms.value>

audience-event-interpretter.kafka.topics: <SC_CIF_INTEGRATION>

audience-event-interpretter.kafka.topics.SC_CIF_INTEGRATION.format: Json

audience-event-interpretter.kafka.fetch.min.bytes: 8388608

audience-event-interpretter.kafka.fetch.max.bytes: 8388608

audience-event-interpretter.kafka.max.partition.fetch.bytes: 8388608

For more information, see Unica Content Integration Installation and Configuration Guide



Note:



If your setup has Docker provided configurations, in the Configurations panel access, for the **additionalParameters** field, the multiple parameters are separated by a space. To use the configurations provided by Docker, edit the configuration and for the **additionalParameters** field ensure that all parameters are separated by a new line.

Segment Central | partitions | partition[n] | Content Integration | dataSources | Segment Central | httpGateway

Provide values for the following optional/mandatory fields:

- **baseUrl** -

Default value: http://<localhost>/AudienceCentral

- **contentBaseUrl** -

Default value: http://<localhost>/AudienceCentral

- **bypassProxy** -

Default value: No

Segment Central | partitions | partition[n] | Content Integration | dataSources | Segment Central | httpGateway | rest

Provide values for the following optional/mandatory fields:

- **authenticationType** -

Default value: UnicaToken

Segment Central | partitions | partition[n] | Content Integration | dataSources | Segment Central | ci.kafka.configuration

Provide values for the following optional/mandatory fields:

- **ci.kafka.bootstrapServers** -

Default value: (Blank)

- **ci.kafka.securityProtocol** -

Default value: NONE

- **ci.kafka.saslMechanism** -

Default value: PLAIN

- **ci.kafka.userForDataSource** -

Default value: (Blank)

- **ci.kafka.dataSourceNameForSaslJaasConfig** -

Default value: (Blank)

- **ci.kafka.trustStoreLocation** -

Default value: (Blank)

- **ci.kafka.dataSourceNameForTrustStorePassword** -

Default value: (Blank)

- **ci.kafka.keystoreLocation** -

Default value: (Blank)

- **ci.kafka.dataSourceNameForKeyStorePassword** -

Default value: (Blank)

- **ci.kafka.dataSourceNameForKeyPassword** -

Default value: (Blank)

- **ci.kafka.kerberosConfFilePath** -

Default value: (Blank)

- **ci.kafka.kerberosKeytabFilePath** -

Default value: (Blank)

- **ci.kafka.kerberosPrincipal** -

Default value: (Blank)

- **ci.kafka.kerberosServiceName** -

Default value: kafka

Segment Central | partitions | partition[n] | Content Integration | dataSources | Segment Central | qos | retryPolicy

Provide values for the following optional/mandatory fields:

- **retryCount** -

Default value: 1

- **initialDelay** -

Default value: 1000

- **delayMultiplier** -

Default value: 1

Segment Central | partitions | partition[n] | Content Integration | dataSources | Journey

Provide values for the optional/mandatory fields:

- **systemIdentifier**

Journey



Note: If it is multi partition Unica environment, then the system identifier should be:

- For partition 1 - Journey SCP1
- For partition 2 - Journey SCP2
- For partition 3 - Journey SCP3 and so on.

- **userCredentials**

Default user

- **defaultUserCredentials**

asm_admin

- **dataSourceNameForCredentials**

journey_ds

- **anonymousContentAccess**

Yes

- **additionalParameters**

event-publisher-service.kafka.topics: CIFINTEGRATION

event-publisher-service.kafka.topics.CIFINTEGRATION.value.format: Json

event-publisher-service.kafka.batch.size: 32768

event-publisher-service.kafka.linger.ms: 100

event-publisher-service.kafka.compression.type: gzip

For more information, see Unica Content Integration Installation and Configuration Guide.

Segment Central | partitions | partition[n] | Content Integration | dataSources | Journey | httpGateway

Provide values for the following optional/mandatory fields:

- **baseUrl** -

Default value: http://<localhost>/AudienceCentral

- **contentBaseUrl** -

Default value: http://<localhost>/AudienceCentral

- **bypassProxy** -

Default value: No

Segment Central | partitions | partition[n] | Content Integration | dataSources | Journey | httpGateway | rest

Provide values for the following optional/mandatory fields:

- **authenticationType** -

Default value: UnicaToken

Segment Central | partitions | partition[n] | Content Integration | dataSources | Journey | ci.kafka.configuration

Provide values for the following optional/mandatory fields:

- **ci.kafka.bootstrapServers** -

Default value: (Blank)

- **ci.kafka.securityProtocol** -

Default value: NONE

- **ci.kafka.saslMechanism** -

Default value: PLAIN

- **ci.kafka.userForDataSource** -

Default value: (Blank)

- **ci.kafka.dataSourceNameForSaslJaasConfig** -

Default value: (Blank)

- **ci.kafka.trustStoreLocation** -

Default value: (Blank)

- **ci.kafka.dataSourceNameForTrustStorePassword** -

Default value: (Blank)

- **ci.kafka.keystoreLocation** -

Default value: (Blank)

- **ci.kafka.dataSourceNameForKeyStorePassword** -

Default value: (Blank)

- **ci.kafka.dataSourceNameForKeyPassword** -

Default value: (Blank)

- **ci.kafka.kerberosConfFilePath** -

Default value: (Blank)

- **ci.kafka.kerberosKeytabFilePath** -

Default value: (Blank)

- **ci.kafka.kerberosPrincipal** -

Default value: (Blank)

- **ci.kafka.kerberosServiceName** -

Default value: kafka

Segment Central | partitions | partition[n] | Content Integration | dataSources | Journey Central | qos | retryPolicy

Provide values for the following optional/mandatory fields:

- **retryCount** -

Default value: 1

- **initialDelay** -

Default value: 1000

- **delayMultiplier** -

Default value: 1

Segment Central | partitions | (partitionTemplate)

If system has multiple partitions, additional partitions can be added by below settings.

Provide values for the mandatory/optional fields:

- **New category name** - The name provided for a new partition.

Default value: (blank)

Click **Save changes**

Chapter 8. Uninstall Unica Segment Central

You can choose to Uninstall Unica Segment Central.

Uninstalling Unica Segment Central

To uninstall Unica Segment Central, run the uninstaller. When you run the uninstaller, the files that were created during the installation process are removed. For example, files such as configuration files, installer registry information, and user data are removed from the computer.

When you install Unica products, an uninstaller is included in the `Uninstall_Product` directory, where Product is the name of your product. On Microsoft Windows, an entry is also added to the **Add or Remove Programs** list in the Control Panel.

If you manually remove the files in your installation directory instead of running the uninstaller, the result might be an incomplete installation if you later reinstall a product in the same location. After uninstalling a product, its database is not removed. The uninstaller only removes default files that are created during installation. Any file that is created or generated after installation is not removed.



Note: On UNIX, the same user account that installed Segment Central must run the uninstaller.

1. If you have deployed the Segment Central web application, undeploy the SegmentCentral web application and SegmentationEngine application from your web application server.
2. Shut down web application server.
3. Stop the processes that are related to Segment Central.
4. Complete one of the following steps to uninstall Segment Central:

- Click the Unica Segment Central uninstaller that exists in the `Uninstall_Product` directory. The uninstaller runs in the mode in which you installed Unica Segment Central.
- In a command-line window, navigate to the directory where the uninstaller exists, and run the following command to uninstall Unica Segment Central by using the console mode:

```
Uninstall_Product -i console
```

- In a command-line window, navigate to the directory where the uninstaller exists, and run the following command to uninstall Unica Segment Central by using the silent mode:

```
Uninstall_Product -i silent
```

When you uninstall Unica Segment Central, using the silent mode, the uninstallation process does not present any dialogs for user interaction.

5. Start web application server.



Note: After uninstallation, to continue using Unica Campaign's Segment management feature, you must disable Unica Segment Central.